

L Number	Hits	Search Text	DB	Time stamp
5	0	deferred adj breakpoint	USPAT	2004/02/11 22:58
6	0	deferred adj breakpoint	USPAT; US-PGPUB; EPO; JPO; DERWENT	2004/02/11 22:59
7	1	deferred adj breakpoint	USPAT; US-PGPUB; EPO; JPO; DERWENT	2004/02/11 22:59
-	0	("US20020129337A1").PN.	USPAT; US-PGPUB	2004/02/11 09:39
-	1	("20020129337").PN.	USPAT; US-PGPUB	2004/02/10 17:11
-	1	("5901315").PN.	USPAT; US-PGPUB	2004/02/10 19:07
-	20	JPDA	USPAT; US-PGPUB; EPO; JPO	2004/02/10 19:07
-	5	JPDA and debugger	USPAT; US-PGPUB; EPO; JPO	2004/02/10 19:42
-	16	BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/10 19:42
-	3	(JPDA and debugger) and BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/10 19:42


-	48	{"5901315" "6052515" "6463578" "5848274" "5995744" "6144933" "6212650" "6212650" "6637024" "6353923" "6249907" "6226761" "6226761" "6647544" "6247020" "6282702" "6011916" "6357019" "6249803" "6360258" "6553565" "6430707" "6477666" "6430570" "6011920" "6189139" "6134603" "5781778" "5794046" "6074427" "6412106" "6081665" "6442751" "6202208" "6256752" "6691302" "6131109" "5678028" "5771385" "5394544" "5450586" "5680542" "5689684" "5701488" "6058393" "6126328" "6388533" "6321378" "5596714" "5513317") .pn.	USPAT	2004/02/11 09:41
---	----	---	-------	---------------------

-	0	(("5901315" "6052515" "6463578" "5848274" "5995744" "6144933" "6212650" "6212650" "6637024" "6353923" "6249907" "6226761" "6226761" "6647544" "6247020" "6282702" "6011916" "6357019" "6249803" "6360258" "6553565" "6430707" "6477666" "6430570" "6011920" "6189139" "6134603" "5781778" "5794046" "6074427" "6412106" "6081665" "6442751" "6202208" "6256752" "6691302" "6131109" "5678028" "5771385" "5394544" "5450586" "5680542" "5689684" "5701488" "6058393" "6126328" "6388533" "6321378" "5596714" "5513317").pn.) and JPDA	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:42
---	---	---	---------------------------------	---------------------

-	0	(("5901315" "6052515" "6463578" "5848274" "5995744" "6144933" "6212650" "6212650" "6637024" "6353923" "6249907" "6226761" "6226761" "6647544" "6247020" "6282702" "6011916" "6357019" "6249803" "6360258" "6553565" "6430707" "6477666" "6430570" "6011920" "6189139" "6134603" "5781778" "5794046" "6074427" "6412106" "6081665" "6442751" "6202208" "6256752" "6691302" "6131109" "5678028" "5771385" "5394544" "5450586" "5680542" "5689684" "5701488" "6058393" "6126328" "6388533" "6321378" "5596714" "5513317") .pn.) and JPDA	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:42
---	---	--	---------------------------------	---------------------

-	0	(("5901315" "6052515" "6463578" "5848274" "5995744" "6144933" "6212650" "6212650" "6637024" "6353923" "6249907" "6226761" "6226761" "6647544" "6247020" "6282702" "6011916" "6357019" "6249803" "6360258" "6553565" "6430707" "6477666" "6430570" "6011920" "6189139" "6134603" "5781778" "5794046" "6074427" "6412106" "6081665" "6442751" "6202208" "6256752" "6691302" "6131109" "5678028" "5771385" "5394544" "5450586" "5680542" "5689684" "5701488" "6058393" "6126328" "6388533" "6321378" "5596714" "5513317").pn.) and (Java adj platform adj Debugger adj architecture) Java adj platform adj Debugger adj architecture jpda adj api JPDA InputStream same BufferedReader InputStream BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:43
-	4	Java adj platform adj Debugger adj architecture	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:46
-	2	jpda adj api	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:46
-	20	JPDA	USPAT; US-PGPUB; EPO; JPO	2004/02/11 09:48
-	0	InputStream same BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:27
-	94	InputStream	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:32
-	0	BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:27

-	16	BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:27
-	6	InputStream and BufferedReader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:32
-	1	InputStream and BufferedWriter	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:32
-	89	OutputStream	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:32
-	1	OutputStream and BufferedWriter	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:33
-	2	BufferedWriter	USPAT; US-PGPUB; EPO; JPO	2004/02/11 14:33
-	3	((("5548717") or ("5706502") or ("6061518"))).PN.	USPAT	2004/02/11 20:10
-	7	(US-5901315-\$ or US-6061518-\$ or US-5706502-\$ or US-5548717-\$).did. or (US-20020129337-\$ or US-20030154284-\$ or US-20020073063-\$).did.	USPAT; US-PGPUB	2004/02/11 20:10
-	2	((US-5901315-\$ or US-6061518-\$ or US-5706502-\$ or US-5548717-\$).did. or (US-20020129337-\$ or US-20030154284-\$ or US-20020073063-\$).did.) and (class same load\$3)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 20:12
-	1	((US-5901315-\$ or US-6061518-\$ or US-5706502-\$ or US-5548717-\$).did. or (US-20020129337-\$ or US-20030154284-\$ or US-20020073063-\$).did.) and (obtain\$3 same number same line) and (breakpoint same request\$3)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 20:13
-	20	(obtain\$3 same number same line) and (breakpoint same request\$3)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 20:13
-	1	((obtain\$3 same number same line) and (breakpoint same request\$3)) and (breakpoint same suspen\$5 same polic\$3)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 20:16
-	1	((obtain\$3 same number same line) and (breakpoint same request\$3)) and (breakpoint same suspen\$5)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 20:42
-	1	getSystemClassLoader	USPAT; US-PGPUB; EPO; JPO	2004/02/11 21:11
-	120	Java and (set\$4 same breakpoint)	USPAT; US-PGPUB; EPO; JPO	2004/02/11 21:12
-	2	{Java and (set\$4 same breakpoint)) and jpda	USPAT; US-PGPUB; EPO; JPO	2004/02/11 21:12



[Advanced Search](#)

[Preferences](#)

[Language Tools](#)

[Search Tips](#)

JPDA

Google Search

[Web](#) - [Images](#) - [Groups](#) - [Directory](#) - [News](#)

Searched the web for **JPDA**.

Results 1 - 10 of about 18,900. Search took 0.14 seconds.

Java Platform Debugger Architecture (JPDA)

Java Platform Debugger Architecture (JPDA) is the debugging support for the Java 2 Platform. ... Core Java. Java Platform Debugger Architecture (JPDA). ...

java.sun.com/products/jpda/index.jsp - 21k - [Cached](#) - [Similar pages](#)

Java(tm) Platform Debugger Architecture

The Java Platform Debugger Architecture (JPDA) consists of three interfaces designed for use by debuggers in development environments for desktop systems. ...

java.sun.com/j2se/1.4.2/docs/guide/jpda/ - 5k - [Cached](#) - [Similar pages](#)

[[More results from java.sun.com](#)]

Javangelist :: JPDA

... JPDA. Created by funzel. ... Viewed 229 times. [edit] [attach]. "JavaTM Platform Debugger Architecture (JPDA) is the debugging support for the Java 2 Platform. ...

javangelist.snipsnap.org/space/JPDA - 16k - [Cached](#) - [Similar pages](#)

JPDA Links

JPDA Links. HOME ... J2EE. General Servlets/JSPs RMI/JNDI EJB/CORBA JMS Jini/JavaSpaces SNMP/JMX Security/JAAS Connector JPDA. Persistence. JDBC ...

www.volantec.biz/jpda.htm - 9k - [Cached](#) - [Similar pages](#)

Java-Channel - Query results

... Search. Search: JPDA. ... 8 results. 1. Jylog. jylog.sourceforge.net, Jylog is a JPDA based logger which extracts information from an executing JVM at runtime. ...

www.java-channel.org/query.jsp?cids=c_2176 - 28k - [Cached](#) - [Similar pages](#)

Java 2 on FreeBSD

JPDA. ... The source code for the JPDA extensions are part of the JDK 1.3 Beta, which is available from Sun here (download the Java 2 SDK 1.3 Beta). ...

www.eyesbeyond.com/freebsd/Java/jpda.html - 3k - [Cached](#) - [Similar pages](#)

JPDA Support?

[[Date Prev](#)][[Date Next](#)][[Thread Prev](#)][[Thread Next](#)][[Date Index](#)][[Thread Index](#)]

JPDA Support? From: Chuck.Irvine. Subject: JPDA Support? ...

mail.gnu.org/archive/html/ddd/2000-11/msg00025.html - 5k - [Cached](#) - [Similar pages](#)

JPDA

[[Date Prev](#)][[Date Next](#)][[Thread Prev](#)][[Thread Next](#)][[Date Index](#)][[Thread Index](#)] JPDA.

From: Jack D. Unrue. Subject: JPDA. Date: Sat, 3 Mar 2001 14:21:08 -0700. ...

mail.gnu.org/archive/html/classpath/2001-03/msg00003.html - 5k - [Cached](#) - [Similar pages](#)

[[More results from mail.gnu.org](#)]

Japan Package Design Assosiation

JPDA is a private organization that represents the field of the package design in Japan. The ... industry. JPDA is pursuing steady activities. ...

www.jpda.or.jp/english/ - 11k - [Cached](#) - [Similar pages](#)

[[More results from www.jpda.or.jp](#)]

日本パッケージデザイン協会

“年間日本のパッケージデザイン2003 vol.10” 全国の書

店にて絶賛発売中!! 最新情報はWhat's Newをご覧ください ...

Description: 協会の概要ならびに啓蒙や教育、交流事業を紹介。出版案内、会員作品、工コ...

Category: [World](#) > [Japanese](#) > [アート](#) > [デザイン](#) > [工業デザイン](#)

www.jpda.or.jp/ - 14k - Cached - Similar pages



Result Page: 1 2 3 4 5 6 7 8 9 10 **Next**

JPDA Google Search Search within results

Dissatisfied with your search results? [Help us improve.](#)

Get the [Google Toolbar](#): Google Search Web PageRank 16 blocked Auto

[Google Home](#) - [Advertise with Us](#) - [Business Solutions](#) - [Services & Tools](#) - [Jobs, Press, & Help](#)

©2004 Google

developers.sun.com

» search tips | Search:

In Deve



The Source for Java Developers

[Developers Home](#) > [Products & Technologies](#) > [Java Technology](#) > [J2SE](#) > [Core Java](#) >

[Profile and Register](#)

Core Java

Java Platform Debugger Architecture (JPDA)

Downloads

- Early Access

Reference

- Documentation
- FAQs
- White Papers
- Tested Configurations

Community

- Forums
- Bug Database

Learning

- Tutorials & Code Camps

Java Platform Debugger Architecture (JPDA) provides the infrastructure you need to build end-user debugger applications for the Java 2 Platform, Standard Edition (J2SE). It includes the following three-layered APIs: Java Debug Interface (JDI), a high-level Java programming language interface, including support for remote debugging; Java Debug Wire Protocol (JDWP), which defines the format of information and requests transferred between the debugging process and the debugger front end; and Java Virtual Machine Debug Interface (JVMDI), a low-level native interface that defines the services a Java virtual machine must provide for debugging.

Note to Developers

JPDA is included in the Java 2 Platform, Standard Edition (J2SE) SDK 1.3 and later, on all platforms, and in SDK 1.2.2 for Linux. The download is required only to add the Java Debug Interface (JDI) and Java Debug Wire Protocol (JDWP) to the J2SE SDK 1.2.2 on Solaris and Microsoft Windows platforms.

What's New

November 2003

Enhancements to JPDA Software in J2SE 1.4 The latest enhancements in the J2SE 1.4 family include full-speed debugging support, HotSwap, instance filters, support for debugging other languages, and VMDeathRequests. See the J2SE 1.4.1 for details.

Community

Events

2004 JavaOne Conference,
San Francisco, CA

Be there! Join the thousands of developers worldwide who come to the JavaOne conference each year in San Francisco to immerse themselves in Java technology, the latest innovations, the community, and the learning opportunities. » [Read More](#)

Comments

You may send comments about JPDA to: java-debugger@sun.com

Note on J2PA APIs

JPDA software includes the following three-layered APIs:

- JDI: Java Debug Interface, a high-level Java programming language interface, including support for remote debugging.
- JDWP: Java Debug Wire Protocol, which defines the format of information and requests transferred between the debugging process and the debugger front end.
- JVMDI: Java Virtual Machine Debug Interface, a low-level native interface that defines the services a Java virtual machine must provide for debugging.



Raghavan "Rags"
Srinivas, Staff
Engineer,
Developer and
Security Expert



[Company Info](#) | [About SDK](#) | [Press](#) | [Contact Us](#) | [Employment](#)
[How to Buy](#) | [Licensing](#) | [Terms of Use](#) | [Privacy](#) | [Trademarks](#)

Copyright 1994-2004 Sun Microsystems, Inc.

Related Links

Popular Downlo

- J2SE 1.4.2
- Java Web Servi
- Pack 1.3

Technical Topic

- Performance
- Web Services
- Security
- Desktop

Products and To

- J2SE 1.5 (comi
- J2SE 1.4.2
- Desktop Java
- Java Web Servi
- J2EE
- Java Dynamic A
- (JDMC)
- Sun Java Studi

Sun Resources

- java.net
- Java Upgrade F
- New to Java Ce
- Professional Ce
- Professional Tr
- JavaOne Online

A Sun Developer Ne

Unless otherwise not
technical manuals he
articles, FAQs, samp
this license.



Content Fe

developers.sun.com

» search tips | Search: in Deve

The Source for Java Developers

[Developers Home](#) > [Products & Technologies](#) > [Java Technology](#) > [J2SE](#) > [Core Java](#) > [JPDA](#) > [References](#)
[Profile and Register](#)

Reference

Java Platform Debugger Architecture - Documentation

Downloads

- Early Access

Reference

- Documentation
- FAQs
- White Papers
- Tested Configurations

Community

- Forums
- Bug Database

Learning

- Tutorials & Code Camps

The Java Platform Debugger Architecture (JPDA) consists of three interfaces designed for use by debuggers in development environments for desktop systems. The Java Virtual Machine Debugger Interface defines the services a VM must provide for debugging. The Java Debug Wire Protocol defines the format of information and requests transferred between the process being debugged and the debugger front end, which implements the Java Debug Interface. The Java Debug Interface defines information and requests at the user code level.

[Java Platform Debugger Architecture Documentation --- SDK 1.4.2](#)

[Java Platform Debugger Architecture Documentation --- SDK 1.4.1](#)

[Java Platform Debugger Architecture Documentation --- SDK 1.4.0](#)

[Java Platform Debugger Architecture Documentation --- SDK 1.3.1](#)

[Java Platform Debugger Architecture Documentation --- JPDA 1.0](#)

Related Links

Popular Downloads

- [Java Platform C Architecture](#)
- [J2SE 1.4.2](#)
- [Sun Java Studio](#)

Products and Tools

- [J2SE 1.5 \(future\)](#)
- [J2SE 1.3.1 \(pre\)](#)
- [HotSwap](#)

Sun Resources

- [Professional Training](#)
- [Professional Certification](#)
- [Developer Technology](#)



[Company Info](#) | [About SDN](#) | [Press](#) | [Contact Us](#) | [Employment](#)
[How to Buy](#) | [Licensing](#) | [Terms of Use](#) | [Privacy](#) | [Trademarks](#)

Copyright 1994-2004 Sun Microsystems, Inc.

A Sun Developer Notice

Unless otherwise noted, technical manuals, articles, FAQs, sample code, and other content are the property of Sun Microsystems, Inc. and are provided under the terms of the [Creative Commons Attribution-NonCommercial-ShareAlike license](#).

Content License

Java™ 2 Platform, Standard Edition, v 1.4.1

API Specification

This document is the API specification for the Java 2 Platform, Standard Edition, version 1.4.1.

See:

Description

Java 2 Platform Packages	
<u>java.applet</u>	Provides the classes necessary to create an applet and the classes an applet uses to communicate with its applet context.
<u>java.awt</u>	Contains all of the classes for creating user interfaces and for painting graphics and images.
<u>java.awt.color</u>	Provides classes for color spaces.
<u>java.awt.datatransfer</u>	Provides interfaces and classes for transferring data between and within applications.
<u>java.awt.dnd</u>	Drag and Drop is a direct manipulation gesture found in many Graphical User Interface systems that provides a mechanism to transfer information between two entities logically associated with presentation elements in the GUI.
<u>java.awt.event</u>	Provides interfaces and classes for dealing with different types of events fired by AWT components.
<u>java.awt.font</u>	Provides classes and interface relating to fonts.
<u>java.awt.geom</u>	Provides the Java 2D classes for defining and performing operations on objects related to two-dimensional geometry.
<u>java.awt.im</u>	Provides classes and interfaces for the input method framework.
<u>java.awt.im.spi</u>	Provides interfaces that enable the development of input methods that can be used with any Java runtime environment.
<u>java.awt.image</u>	Provides classes for creating and modifying images.
<u>java.awt.image.renderable</u>	Provides classes and interfaces for producing rendering-independent images.

<u>java.awt.print</u>	Provides classes and interfaces for a general printing API.
<u>java.beans</u>	Contains classes related to developing <i>beans</i> -- components based on the JavaBeans™ architecture.
<u>java.beans.beancontext</u>	Provides classes and interfaces relating to bean context.
<u>java.io</u>	Provides for system input and output through data streams, serialization and the file system.
<u>java.lang</u>	Provides classes that are fundamental to the design of the Java programming language.
<u>java.lang.ref</u>	Provides reference-object classes, which support a limited degree of interaction with the garbage collector.
<u>java.lang.reflect</u>	Provides classes and interfaces for obtaining reflective information about classes and objects.
<u>java.math</u>	Provides classes for performing arbitrary-precision integer arithmetic (BigInteger) and arbitrary-precision decimal arithmetic (BigDecimal).
<u>java.net</u>	Provides the classes for implementing networking applications.
<u>java.nio</u>	Defines buffers, which are containers for data, and provides an overview of the other NIO packages.
<u>java.nio.channels</u>	Defines channels, which represent connections to entities that are capable of performing I/O operations, such as files and sockets; defines selectors, for multiplexed, non-blocking I/O operations.
<u>java.nio.channels.spi</u>	Service-provider classes for the <u>java.nio.channels</u> package.
<u>java.nio.charset</u>	Defines charsets, decoders, and encoders, for translating between bytes and Unicode characters.
<u>java.nio.charset.spi</u>	Service-provider classes for the <u>java.nio.charset</u> package.
<u>java.rmi</u>	Provides the RMI package.
<u>java.rmi.activation</u>	Provides support for RMI Object Activation.
<u>java.rmi.dgc</u>	Provides classes and interface for RMI distributed garbage-collection (DGC).
<u>java.rmi.registry</u>	Provides a class and two interfaces for the RMI registry.
<u>java.rmi.server</u>	Provides classes and interfaces for supporting the server side of RMI.
<u>java.security</u>	Provides the classes and interfaces for the security framework.

<u>java.security.acl</u>	The classes and interfaces in this package have been superseded by classes in the java.security package.
<u>java.security.cert</u>	Provides classes and interfaces for parsing and managing certificates, certificate revocation lists (CRLs), and certification paths.
<u>java.security.interfaces</u>	Provides interfaces for generating RSA (Rivest, Shamir and Adleman AsymmetricCipher algorithm) keys as defined in the RSA Laboratory Technical Note PKCS#1, and DSA (Digital Signature Algorithm) keys as defined in NIST's FIPS-186.
<u>java.security.spec</u>	Provides classes and interfaces for key specifications and algorithm parameter specifications.
<u>java.sql</u>	Provides the API for accessing and processing data stored in a data source (usually a relational database) using the Java™ programming language.
<u>java.text</u>	Provides classes and interfaces for handling text, dates, numbers, and messages in a manner independent of natural languages.
<u>java.util</u>	Contains the collections framework, legacy collection classes, event model, date and time facilities, internationalization, and miscellaneous utility classes (a string tokenizer, a random-number generator, and a bit array).
<u>java.util.jar</u>	Provides classes for reading and writing the JAR (Java ARchive) file format, which is based on the standard ZIP file format with an optional manifest file.
<u>java.util.logging</u>	Provides the classes and interfaces of the Java™ 2 platform's core logging facilities.
<u>java.util.prefs</u>	This package allows applications to store and retrieve user and system preference and configuration data.
<u>java.util.regex</u>	Classes for matching character sequences against patterns specified by regular expressions.
<u>java.util.zip</u>	Provides classes for reading and writing the standard ZIP and GZIP file formats.
<u>javax.accessibility</u>	Defines a contract between user-interface components and an assistive technology that provides access to those components.
<u>javax.crypto</u>	Provides the classes and interfaces for cryptographic operations.
<u>javax.crypto.interfaces</u>	Provides interfaces for Diffie-Hellman keys as defined in

	RSA Laboratories' PKCS #3.
<u>javax.crypto.spec</u>	Provides classes and interfaces for key specifications and algorithm parameter specifications.
<u>javax.imageio</u>	The main package of the Java Image I/O API.
<u>javax.imageio.event</u>	A package of the Java Image I/O API dealing with synchronous notification of events during the reading and writing of images.
<u>javax.imageio.metadata</u>	A package of the Java Image I/O API dealing with reading and writing metadata.
<u>javax.imageio.plugins.jpeg</u>	Classes supporting the built-in JPEG plug-in.
<u>javax.imageio.spi</u>	A package of the Java Image I/O API containing the plug-in interfaces for readers, writers, transcoders, and streams, and a runtime registry.
<u>javax.imageio.stream</u>	A package of the Java Image I/O API dealing with low-level I/O from files and streams.
<u>javax.naming</u>	Provides the classes and interfaces for accessing naming services.
<u>javax.naming.directory</u>	Extends the <code>javax.naming</code> package to provide functionality for accessing directory services.
<u>javax.naming.event</u>	Provides support for event notification when accessing naming and directory services.
<u>javax.naming.ldap</u>	Provides support for LDAPv3 extended operations and controls.
<u>javax.naming.spi</u>	Provides the means for dynamically plugging in support for accessing naming and directory services through the <code>javax.naming</code> and related packages.
<u>javax.net</u>	Provides classes for networking applications.
<u>javax.net.ssl</u>	Provides classes for the secure socket package.
<u>javax.print</u>	Provides the principal classes and interfaces for the Java™ Print Service API.
<u>javax.print.attribute</u>	Provides classes and interfaces that describe the types of Java™ Print Service attributes and how they can be collected into attribute sets.
<u>javax.print.attribute.standard</u>	Package <code>javax.print.attribute.standard</code> contains classes for specific printing attributes.
<u>javax.print.event</u>	Package <code>javax.print.event</code> contains event classes and listener interfaces.
<u>javax.rmi</u>	Contains user APIs for RMI-IIOP.

<u>javax.rmi.CORBA</u>	Contains portability APIs for RMI-IIOP.
<u>javax.security.auth</u>	This package provides a framework for authentication and authorization.
<u>javax.security.auth.callback</u>	This package provides the classes necessary for services to interact with applications in order to retrieve information (authentication data including usernames or passwords, for example) or to display information (error and warning messages, for example).
<u>javax.security.auth.kerberos</u>	This package contains utility classes related to the Kerberos network authentication protocol.
<u>javax.security.auth.login</u>	This package provides a pluggable authentication framework.
<u>javax.security.auth.spi</u>	This package provides the interface to be used for implementing pluggable authentication modules.
<u>javax.security.auth.x500</u>	This package contains the classes that should be used to store X500 Principal and X500 Private Credentials in a <i>Subject</i> .
<u>javax.security.cert</u>	Provides classes for public key certificates.
<u>javax.sound.midi</u>	Provides interfaces and classes for I/O, sequencing, and synthesis of MIDI (Musical Instrument Digital Interface) data.
<u>javax.sound.midi.spi</u>	Supplies interfaces for service providers to implement when offering new MIDI devices, MIDI file readers and writers, or sound bank readers.
<u>javax.sound.sampled</u>	Provides interfaces and classes for capture, processing, and playback of sampled audio data.
<u>javax.sound.sampled.spi</u>	Supplies abstract classes for service providers to subclass when offering new audio devices, sound file readers and writers, or audio format converters.
<u>javax.sql</u>	Provides the API for server side data source access and processing from the Java™ programming language.
<u>javax.swing</u>	Provides a set of "lightweight" (all-Java language) components that, to the maximum degree possible, work the same on all platforms.
<u>javax.swing.border</u>	Provides classes and interface for drawing specialized borders around a Swing component.
<u>javax.swing.colorchooser</u>	Contains classes and interfaces used by the JColorChooser component.
<u>javax.swing.event</u>	Provides for events fired by Swing components.

<u>javax.swing.filechooser</u>	Contains classes and interfaces used by the JFileChooser component.
<u>javax.swing.plaf</u>	Provides one interface and many abstract classes that Swing uses to provide its pluggable look-and-feel capabilities.
<u>javax.swing.plaf.basic</u>	Provides user interface objects built according to the Basic look and feel.
<u>javax.swing.plaf.metal</u>	Provides user interface objects built according to the Java look and feel (once codenamed <i>Metal</i>), which is the default look and feel.
<u>javax.swing.plaf.multi</u>	Provides user interface objects that combine two or more look and feels.
<u>javax.swing.table</u>	Provides classes and interfaces for dealing with javax.swing.JTable.
<u>javax.swing.text</u>	Provides classes and interfaces that deal with editable and noneditable text components.
<u>javax.swing.text.html</u>	Provides the class HTMLEditorKit and supporting classes for creating HTML text editors.
<u>javax.swing.text.html.parser</u>	Provides the default HTML parser, along with support classes.
<u>javax.swing.text.rtf</u>	Provides a class (RTFEditorKit) for creating Rich-Text-Format text editors.
<u>javax.swing.tree</u>	Provides classes and interfaces for dealing with javax.swing.JTree.
<u>javax.swing.undo</u>	Allows developers to provide support for undo/redo in applications such as text editors.
<u>javax.transaction</u>	Contains three exceptions thrown by the ORB machinery during unmarshalling.
<u>javax.transaction.xa</u>	Provides the API that defines the contract between the transaction manager and the resource manager, which allows the transaction manager to enlist and delist resource objects (supplied by the resource manager driver) in JTA transactions.
<u>javax.xml.parsers</u>	Provides classes allowing the processing of XML documents.
<u>javax.xml.transform</u>	This package defines the generic APIs for processing transformation instructions, and performing a transformation from source to result.
<u>javax.xml.transform.dom</u>	This package implements DOM-specific transformation APIs.

<u>javax.xml.transform.sax</u>	This package implements SAX2-specific transformation APIs.
<u>javax.xml.transform.stream</u>	This package implements stream- and URI- specific transformation APIs.
<u>org.ietf.jgss</u>	This package presents a framework that allows application developers to make use of security services like authentication, data integrity and data confidentiality from a variety of underlying security mechanisms like Kerberos, using a unified API.
<u>org.omg.CORBA</u>	Provides the mapping of the OMG CORBA APIs to the Java™ programming language, including the class ORB, which is implemented so that a programmer can use it as a fully-functional Object Request Broker (ORB).
<u>org.omg.CORBA_2_3</u>	The CORBA_2_3 package defines additions to existing CORBA interfaces in the Java 2 Standard Edition. These changes occurred in recent revisions to the CORBA API defined by the OMG. The new methods were added to interfaces derived from the corresponding interfaces in the CORBA package. This provides backward compatibility and avoids breaking the JCK tests.
<u>org.omg.CORBA_2_3.portable</u>	Provides methods for the input and output of value types, and contains other updates to the org/omg/CORBA/portable package.
<u>org.omg.CORBA.DynAnyPackage</u>	Provides the exceptions used with the DynAny interface (InvalidValue, Invalid, InvalidSeq, and TypeMismatch).
<u>org.omg.CORBA.ORBPackage</u>	Provides the exception InvalidName, which is thrown by the method ORB.resolve_initial_references and the exception InconsistentTypeCode, which is thrown by the Dynamic Any creation methods in the ORB class.
<u>org.omg.CORBA.portable</u>	Provides a portability layer, that is, a set of ORB APIs that makes it possible for code generated by one vendor to run on another vendor's ORB.
<u>org.omg.CORBA.TypeCodePackage</u>	Provides the user-defined exceptions BadKind and Bounds, which are thrown by methods in in the class TypeCode.
<u>org.omg.CosNaming</u>	Provides a naming service for Java IDL.
<u>org.omg.CosNaming.NamingContextExtPackage</u>	This package contains the following classes, which are used in org.omg.CosNaming.NamingContextExt:
<u>org.omg.CosNaming.NamingContextPackage</u>	This package contains Exception classes for the org.omg.CosNaming package.
	This package contains the Dynamic module specified in

<u>org.omg.Dynamic</u>	the OMG Portable Interceptor specification, http://cgi.omg.org/cgi-bin/doc?ptc/2000-08-06 , section 21.9.
<u>org.omg.DynamicAny</u>	Provides classes and interfaces that enable traversal of the data value associated with an any at runtime, and extraction of the primitive constituents of the data value.
<u>org.omg.DynamicAny.DynAnyFactoryPackage</u>	This package contains classes and exceptions from the DynAnyFactory interface of the DynamicAny module specified in the OMG <i>The Common Object Request Broker: Architecture and Specification</i> , http://cgi.omg.org/cgi-bin/doc?formal/99-10-07 , section 9.2.2.
<u>org.omg.DynamicAny.DynAnyPackage</u>	This package contains classes and exceptions from the DynAny interface of the DynamicAny module specified in the OMG <i>The Common Object Request Broker: Architecture and Specification</i> , http://cgi.omg.org/cgi-bin/doc?formal/99-10-07 , section 9.2.
<u>org.omg.IOP</u>	This package contains the IOP module specified in the OMG document <i>The Common Object Request Broker: Architecture and Specification</i> , http://cgi.omg.org/cgi-bin/doc?formal/99-10-07 , section 13.6.
<u>org.omg.IOP.CodecFactoryPackage</u>	This package contains the exceptions specified in the IOP::CodecFactory interface (as part of the Portable Interceptors spec).
<u>org.omg.IOP.CodecPackage</u>	This package is generated from the IOP::Codec IDL interface definition.
<u>org.omg.Messaging</u>	This package contains the Messaging module specified in the OMG CORBA Messaging specification, http://cgi.omg.org/cgi-bin/doc?formal/99-10-07 .
<u>org.omg.PortableInterceptor</u>	Provides a mechanism to register ORB hooks through which ORB services can intercept the normal flow of execution of the ORB.
<u>org.omg.PortableInterceptor.ORBInitInfoPackage</u>	This package contains the exceptions and typedefs from the ORBInitInfo local interface of the PortableInterceptor module specified in the OMG Portable Interceptor specification, http://cgi.omg.org/cgi-bin/doc?ptc/2000-08-06 , section 21.7.2.
<u>org.omg.PortableServer</u>	Provides classes and interfaces for making the server side of your applications portable across multivendor ORBs.
<u>org.omg.PortableServer.CurrentPackage</u>	Provides method implementations with access to the identity of the object on which the method was invoked.

<u>org.omg.PortableServer.POAManagerPackage</u>	Encapsulates the processing state of the POAs it is associated with.
<u>org.omg.PortableServer.POAPackage</u>	Allows programmers to construct object implementations that are portable between different ORB products.
<u>org.omg.PortableServer.portable</u>	Provides classes and interfaces for making the server side of your applications portable across multivendor ORBs.
<u>org.omg.PortableServer.ServantLocatorPackage</u>	Provides classes and interfaces for locating the servant.
<u>org.omg.SendingContext</u>	Provides support for the marshalling of value types.
<u>org.omg.stub.java.rmi</u>	Contains RMI-IIOP Stubs for the Remote types that occur in the <code>java.rmi</code> package.
<u>org.w3c.dom</u>	Provides the interfaces for the Document Object Model (DOM) which is a component API of the <u>Java API for XML Processing</u> .
<u>org.xml.sax</u>	Provides the classes and interfaces for the Simple API for XML (SAX) which is a component of the <u>Java API for XML Processing</u> .
<u>org.xml.sax.ext</u>	Provides extension classes and interfaces for the Simple API for XML (SAX) which is a component of the <u>Java API for XML Processing</u> .
<u>org.xml.sax.helpers</u>	Provides helper classes for the Simple API for XML (SAX) which is a component of the <u>Java API for XML Processing</u> .

This document is the API specification for the Java 2 Platform, Standard Edition, version 1.4.1.

Overview Package Class Use [Tree](#) [Deprecated](#) [Index](#) [Help](#)

*Java™ 2 Platform
Std. Ed. v1.4.1*

[PREV](#) [NEXT](#)

[**FRAMES**](#) [NO FRAMES](#) [All Classes](#)

[Submit a bug or feature](#)

For further API reference and developer documentation, see [Java 2 SDK SE Developer Documentation](#). That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Copyright 2002 Sun Microsystems, Inc. All rights reserved. Use is subject to [license terms](#).

All Classes

AbstractAction
AbstractBorder
AbstractButton
AbstractCellEditor
AbstractCollection
AbstractColorChooserPanel
AbstractDocument
AbstractDocument.AttributeContext
AbstractDocument.Content
AbstractDocument.ElementEdit
AbstractInterruptibleChannel
AbstractLayoutCache
AbstractLayoutCache.NodeDimensions
AbstractList
AbstractListModel
AbstractMap
AbstractMethodError
AbstractPreferences
AbstractSelectableChannel
AbstractSelectionKey
AbstractSelector
AbstractSequentialList
AbstractSet
AbstractSpinnerModel
AbstractTableModel
AbstractUndoableEdit
AbstractWriter
AccessControlContext
AccessControlException
AccessController
AccessException
Accessible
AccessibleAction
AccessibleBundle
AccessibleComponent
AccessibleContext
AccessibleEditableText
AccessibleExtendedComponent
AccessibleExtendedTable
AccessibleHyperlink
AccessibleHypertext
AccessibleIcon
AccessibleKeyBinding
AccessibleObject
AccessibleRelation
AccessibleRelationSet
AccessibleResourceBundle
AccessibleRole
AccessibleSelection

AccessibleState
AccessibleStateSet
AccessibleTable
AccessibleTableModelChange
AccessibleText
AccessibleValue
AccountExpiredException
Acl
AclEntry
AclNotFoundException
Action
ActionEvent
ActionListener
ActionMap
ActionMapUIResource
Activatable
ActivateFailedException
ActivationDesc
ActivationException
ActivationGroup
ActivationGroup_Stub
ActivationGroupDesc
ActivationGroupDesc.CommandEnvironment
ActivationGroupID
ActivationID
ActivationInstantiator
ActivationMonitor
ActivationSystem
Activator
ActiveEvent
AdapterActivator
AdapterActivatorOperations
AdapterAlreadyExists
AdapterAlreadyExistsHelper
AdapterInactive
AdapterInactiveHelper
AdapterNonExistent
AdapterNonExistentHelper
AddressHelper
Adjustable
AdjustmentEvent
AdjustmentListener
Adler32
AffineTransform
AffineTransformOp
AlgorithmParameterGenerator
AlgorithmParameterGeneratorSpi
AlgorithmParameters
AlgorithmParameterSpec
AlgorithmParametersSpi

AllPermission
AlphaComposite
AlreadyBound
AlreadyBoundException
AlreadyBoundHelper
AlreadyBoundHolder
AlreadyConnectedException
AncestorEvent
AncestorListener
Annotation
Any
AnyHolder
AnySeqHelper
AnySeqHelper
AnySeqHolder
AppConfigurationEntry
AppConfigurationEntry.LoginModuleControlFlag
Applet
AppletContext
AppletInitializer
AppletStub
ApplicationException
Arc2D
Arc2D.Double
Arc2D.Float
Area
AreaAveragingScaleFilter
ARG_IN
ARG_INOUT
ARG_OUT
ArithmeticException
Array
Array
ArrayIndexOutOfBoundsException
ArrayList
Arrays
ArrayStoreException
AssertionError
AsyncBoxView
AsynchronousCloseException
Attr
Attribute
Attribute
AttributedCharacterIterator
AttributedCharacterIterator.Attribute
AttributedString
AttributeException
AttributeInUseException
AttributeList
AttributeList

AttributeListImpl
AttributeModificationException
Attributes
Attributes
Attributes
Attributes.Name
AttributeSet
AttributeSet
AttributeSet.CharacterAttribute
AttributeSet.ColorAttribute
AttributeSet.FontAttribute
AttributeSet.ParagraphAttribute
AttributeSetUtilities
AttributesImpl
AudioClip
AudioFileFormat
AudioFileFormat.Type
AudioFileReader
AudioFileWriter
AudioFormat
AudioFormat.Encoding
AudioInputStream
AudioPermission
AudioSystem
AuthenticationException
AuthenticationNotSupportedException
Authenticator
AuthPermission
Autoscroll
AWTError
AWTEvent
AWTEventListener
AWTEventListenerProxy
AWTEventMulticaster
AWTException
AWTKeyStroke
AWTPermission
BackingStoreException
BAD_CONTEXT
BAD_INV_ORDER
BAD_OPERATION
BAD_PARAM
BAD_POLICY
BAD_POLICY_TYPE
BAD_POLICY_VALUE
BAD_TYPECODE
BadKind
BadLocationException
BadPaddingException
BandCombineOp

BandedSampleModel
BasicArrowButton
BasicAttribute
BasicAttributes
BasicBorders
BasicBorders.ButtonBorder
BasicBorders.FieldBorder
BasicBorders.MarginBorder
BasicBorders.MenuBarBorder
BasicBorders.RadioButtonBorder
BasicBorders.RolloverButtonBorder
BasicBorders.SplitPaneBorder
BasicBorders.ToggleButtonBorder
BasicButtonListener
BasicButtonUI
BasicCheckBoxMenuItemUI
BasicCheckBoxUI
BasicColorChooserUI
BasicComboBoxEditor
BasicComboBoxEditor.UIResource
BasicComboBoxRenderer
BasicComboBoxRenderer.UIResource
BasicComboBoxUI
BasicComboPopup
BasicDesktopIconUI
BasicDesktopPaneUI
BasicDirectoryModel
BasicEditorPaneUI
BasicFileChooserUI
BasicFormattedTextFieldUI
BasicGraphicsUtils
BasicHTML
BasicIconFactory
BasicInternalFrameTitlePane
BasicInternalFrameUI
BasicLabelUI
BasicListUI
BasicLookAndFeel
BasicMenuBarUI
BasicMenuItemUI
BasicMenuUI
BasicOptionPaneUI
BasicOptionPaneUI.ButtonAreaLayout
BasicPanelUI
BasicPasswordFieldUI
BasicPermission
BasicPopupMenuSeparatorUI
BasicPopupMenuUI
BasicProgressBarUI
BasicRadioButtonMenuItemUI

BasicRadioButtonUI
BasicRootPaneUI
BasicScrollBarUI
BasicScrollPaneUI
BasicSeparatorUI
BasicSliderUI
BasicSpinnerUI
BasicSplitPaneDivider
BasicSplitPaneUI
BasicStroke
BasicTabbedPaneUI
BasicTableHeaderUI
BasicTableUI
BasicTextAreaUI
BasicTextFieldUI
BasicTextPaneUI
BasicTextUI
BasicTextUI.BasicCaret
BasicTextUI.BasicHighlighter
BasicToggleButtonUI
BasicToolBarSeparatorUI
BasicToolBarUI
BasicToolTipUI
BasicTreeUI
BasicViewportUI
BatchUpdateException
BeanContext
BeanContextChild
BeanContextChildComponentProxy
BeanContextChildSupport
BeanContextContainerProxy
BeanContextEvent
BeanContextMembershipEvent
BeanContextMembershipListener
BeanContextProxy
BeanContextServiceAvailableEvent
BeanContextServiceProvider
BeanContextServiceProviderBeanInfo
BeanContextServiceRevokedEvent
BeanContextServiceRevokedListener
BeanContextServices
BeanContextServicesListener
BeanContextServicesSupport
BeanContextServicesSupport.BCSSServiceProvider
BeanContextSupport
BeanContextSupport.BCSIterator
BeanDescriptor
BeanInfo
Beans
BevelBorder

Bidi
BigDecimal
BigInteger
BinaryRefAddr
BindException
Binding
Binding
BindingHelper
BindingHolder
BindingIterator
BindingIteratorHelper
BindingIteratorHolder
BindingIteratorOperations
BindingIteratorPOA
BindingListHelper
BindingListHolder
BindingType
BindingTypeHelper
BindingTypeHolder
BitSet
Blob
BlockView
Book
Boolean
BooleanControl
BooleanControl.Type
BooleanHolder
BooleanSeqHelper
BooleanSeqHolder
Border
BorderFactory
BorderLayout
BorderUIResource
BorderUIResource.BevelBorderUIResource
BorderUIResource.CompoundBorderUIResource
BorderUIResource.EmptyBorderUIResource
BorderUIResource.EtchedBorderUIResource
BorderUIResource.LineBorderUIResource
BorderUIResource.MatteBorderUIResource
BorderUIResource.TitledBorderUIResource
BoundedRangeModel
Bounds
Bounds
Box
Box.Filler
BoxedValueHelper
BoxLayout
BoxView
BreakIterator
Buffer

BufferCapabilities
BufferCapabilities.FlipContents
BufferedImage
BufferedImageFilter
BufferedImageOp
BufferedInputStream
BufferedOutputStream
BufferedReader
BufferedWriter
BufferOverflowException
BufferStrategy
BufferUnderflowException
Button
ButtonGroup
ButtonModel
ButtonUI
Byte
ByteArrayInputStream
ByteArrayOutputStream
ByteBuffer
ByteChannel
ByteHolder
ByteLookupTable
ByteOrder
Calendar
CallableStatement
Callback
CallbackHandler
CancelablePrintJob
CancelledKeyException
CannotProceed
CannotProceedException
CannotProceedHelper
CannotProceedHolder
CannotRedoException
CannotUndoException
Canvas
CardLayout
Caret
CaretEvent
CaretListener
CDATASection
CellEditor
CellEditorListener
CellRendererPane
Certificate
Certificate
Certificate
Certificate.CertificateRep
CertificateEncodingException

CertificateEncodingException
CertificateException
CertificateException
CertificateExpiredException
CertificateExpiredException
CertificateFactory
CertificateFactorySpi
CertificateNotYetValidException
CertificateNotYetValidException
CertificateParsingException
CertificateParsingException
CertPath
CertPath.CertPathRep
CertPathBuilder
CertPathBuilderException
CertPathBuilderResult
CertPathBuilderSpi
CertPathParameters
CertPathValidator
CertPathValidatorException
CertPathValidatorResult
CertPathValidatorSpi
CertSelector
CertStore
CertStoreException
CertStoreParameters
CertStoreSpi
ChangedCharSetException
ChangeEvent
ChangeListener
Channel
ChannelBinding
Channels
Character
Character.Subset
Character.UnicodeBlock
CharacterCodingException
CharacterData
CharacterIterator
CharArrayReader
CharArrayWriter
CharBuffer
CharConversionException
CharHolder
CharSeqHelper
CharSeqHolder
CharSequence
Charset
CharsetDecoder
CharsetEncoder

CharsetProvider
Checkbox
CheckboxGroup
CheckboxMenuItem
CheckedInputStream
CheckedOutputStream
Checksum
Choice
ChoiceCallback
ChoiceFormat
Chromaticity
Cipher
CipherInputStream
CipherOutputStream
CipherSpi
Class
ClassCastException
ClassCircularityError
ClassDesc
ClassFormatError
ClassLoader
ClassNotFoundException
ClientRequestInfo
ClientRequestInfoOperations
ClientRequestInterceptor
ClientRequestInterceptorOperations
Clip
Clipboard
ClipboardOwner
Clob
Cloneable
CloneNotSupportedException
ClosedByInterruptException
ClosedChannelException
ClosedSelectorException
CMMException
Codec
CodecFactory
CodecFactoryHelper
CodecFactoryOperations
CodecOperations
CoderMalfunctionError
CoderResult
CodeSets
CodeSource
CodingErrorAction
CollationElementIterator
CollationKey
Collator
Collection

CollectionCertStoreParameters
Collections
Color
ColorChooserComponentFactory
ColorChooserUI
ColorConvertOp
ColorModel
ColorSelectionModel
ColorSpace
ColorSupported
ColorUIResource
ComboBoxEditor
ComboBoxModel
ComboBoxUI
ComboPopup
COMM_FAILURE
Comment
CommunicationException
Comparable
Comparator
Compiler
CompletionStatus
CompletionStatusHelper
Component
ComponentAdapter
ComponentColorModel
ComponentEvent
ComponentIdHelper
ComponentInputMap
ComponentInputMapUIResource
ComponentListener
ComponentOrientation
ComponentSampleModel
ComponentUI
ComponentView
Composite
CompositeContext
CompositeName
CompositeView
CompoundBorder
CompoundControl
CompoundControl.Type
CompoundEdit
CompoundName
Compression
ConcurrentModificationException
Configuration
ConfigurationException
ConfirmationCallback
ConnectException

ConnectException
ConnectIOException
Connection
ConnectionEvent
ConnectionEventListener
ConnectionPendingException
ConnectionPoolDataSource
ConsoleHandler
Constructor
Container
ContainerAdapter
ContainerEvent
ContainerListener
ContainerOrderFocusTraversalPolicy
ContentHandler
ContentHandler
ContentHandlerFactory
ContentModel
Context
Context
ContextList
ContextNotEmptyException
ContextualRenderedImageFactory
Control
Control
Control.Type
ControlFactory
ControllerEventListener
ConvolveOp
CookieHolder
Copies
CopiesSupported
CRC32
CredentialExpiredException
CRL
CRLException
CRLSelector
CropImageFilter
CSS
CSS.Attribute
CTX_RESTRICT_SCOPE
CubicCurve2D
CubicCurve2D.Double
CubicCurve2D.Float
Currency
Current
Current
Current
CurrentHelper
CurrentHelper

CurrentHelper
CurrentHolder
CurrentOperations
CurrentOperations
CurrentOperations
Cursor
Customizer
CustomMarshal
CustomValue
DATA_CONVERSION
DatabaseMetaData
DataBuffer
DataBufferByte
DataBufferDouble
DataBufferFloat
DataBufferInt
DataBufferShort
DataBufferUShort
DataFlavor
DataFormatException
DatagramChannel
DatagramPacket
DatagramSocket
DatagramSocketImpl
DatagramSocketImplFactory
DataInput
DataInputStream
DataInputStream
DataLine
DataLine.Info
DataOutput
DataOutputStream
DataOutputStream
DataSource
DataTruncation
Date
Date
DateFormat
DateFormat.Field
DateFormatSymbols
DateFormatter
DateTimeAtCompleted
DateTimeAtCreation
DateTimeAtProcessing
DateTimeSyntax
DebugGraphics
DecimalFormat
DecimalFormatSymbols
DeclHandler
DefaultBoundedRangeModel

DefaultButtonModel
DefaultCaret
DefaultCellEditor
DefaultColorSelectionModel
DefaultComboBoxModel
DefaultDesktopManager
DefaultEditorKit
DefaultEditorKit.BeepAction
DefaultEditorKit.CopyAction
DefaultEditorKit.CutAction
DefaultEditorKit.DefaultKeyTypedAction
DefaultEditorKit.InsertBreakAction
DefaultEditorKit.InsertContentAction
DefaultEditorKit.InsertTabAction
DefaultEditorKit.PasteAction
DefaultFocusManager
DefaultFocusTraversalPolicy
DefaultFormatter
DefaultFormatterFactory
DefaultHandler
DefaultHighlighter
DefaultHighlighter.DefaultHighlightPainter
DefaultKeyboardFocusManager
DefaultListCellRenderer
DefaultListCellRenderer.UIResource
DefaultListModel
DefaultListSelectionModel
DefaultMenuLayout
DefaultMetalTheme
DefaultMutableTreeNode
DefaultPersistenceDelegate
DefaultSingleSelectionModel
DefaultStyledDocument
DefaultStyledDocument.AttributeUndoableEdit
DefaultStyledDocument.ElementSpec
DefaultTableCellRenderer
DefaultTableCellRenderer.UIResource
DefaultTableColumnModel
DefaultTableModel
DefaultTextUI
DefaultTreeCellEditor
DefaultTreeCellRenderer
DefaultTreeModel
DefaultTreeSelectionModel
DefinitionKind
DefinitionKindHelper
Deflater
DeflaterOutputStream
Delegate
Delegate

Delegate
DelegationPermission
DESedeKeySpec
DesignMode
DESKeySpec
DesktopIconUI
DesktopManager
DesktopPaneUI
Destination
Destroyable
DestroyFailedException
DGC
DHGenParameterSpec
DHKey
DHParameterSpec
DHPrivateKey
DHPrivateKeySpec
DHPublicKey
DHPublicKeySpec
Dialog
Dictionary
DigestException
DigestInputStream
DigestOutputStream
Dimension
Dimension2D
DimensionUIResource
DirContext
DirectColorModel
DirectoryManager
DirObjectFactory
DirStateFactory
DirStateFactory.Result
DisplayMode
DnDConstants
Doc
DocAttribute
DocAttributeSet
DocFlavor
DocFlavor.BYTE_ARRAY
DocFlavor.CHAR_ARRAY
DocFlavor.INPUT_STREAM
DocFlavor.READER
DocFlavor.SERVICE_FORMATTED
DocFlavor.STRING
DocFlavor.URL
DocPrintJob
Document
Document
DocumentBuilder

DocumentBuilderFactory
DocumentEvent
DocumentEvent.ElementChange
DocumentEvent.EventType
DocumentFilter
DocumentFilter.FilterBypass
DocumentFragment
DocumentHandler
DocumentListener
DocumentName
DocumentParser
DocumentType
DomainCombiner
DomainManager
DomainManagerOperations
DOMException
DOMImplementation
DOMLocator
DOMResult
DOMSource
Double
DoubleBuffer
DoubleHolder
DoubleSeqHelper
DoubleSeqHolder
DragGestureEvent
DragGestureListener
DragGestureRecognizer
DragSource
DragSourceAdapter
DragSourceContext
DragSourceDragEvent
DragSourceDropEvent
DragSourceEvent
DragSourceListener
DragSourceMotionListener
Driver
DriverManager
DriverPropertyInfo
DropTarget
DropTarget.DropTargetAutoScroller
DropTargetAdapter
DropTargetContext
DropTargetDragEvent
DropTargetDropEvent
DropTargetEvent
DropTargetListener
DSAKey
DSAKeyPairGenerator
DSAParameterSpec

DSAParams
DSAPrivateKey
DSAPrivateKeySpec
DSAPublicKey
DSAPublicKeySpec
DTD
DTDConstants
DTDHandler
DuplicateName
DuplicateNameHelper
DynamicImplementation
DynamicImplementation
DynAny
DynAny
DynAnyFactory
DynAnyFactoryHelper
DynAnyFactoryOperations
DynAnyHelper
DynAnyOperations
DynAnySeqHelper
DynArray
DynArray
DynArrayHelper
DynArrayOperations
DynEnum
DynEnum
DynEnumHelper
DynEnumOperations
DynFixed
DynFixed
DynFixedHelper
DynFixedOperations
DynSequence
DynSequence
DynSequenceHelper
DynSequenceOperations
DynStruct
DynStruct
DynStructHelper
DynStructOperations
DynUnion
DynUnion
DynUnionHelper
DynUnionOperations
DynValue
DynValue
DynValueBox
DynValueBoxOperations
DynValueCommon
DynValueCommonOperations

DynValueHelper
DynValueOperations
EditorKit
Element
Element
Element
ElementIterator
Ellipse2D
Ellipse2D.Double
Ellipse2D.Float
EmptyBorder
EmptyStackException
EncodedKeySpec
Encoder
Encoding
ENCODING_CDR_ENCAPS
EncryptedPrivateKeyInfo
Entity
Entity
EntityReference
EntityResolver
EnumControl
EnumControl.Type
Enumeration
EnumSyntax
Environment
EOFException
Error
ErrorHandler
ErrorListener
ErrorManager
EtchedBorder
Event
EventContext
EventDirContext
EventHandler
EventListener
EventListenerList
EventListenerProxy
EventObject
EventQueue
EventSetDescriptor
Exception
ExceptionInInitializerError
ExceptionList
ExceptionHandler
ExemptionMechanism
ExemptionMechanismException
ExemptionMechanismSpi
ExpandVetoException

ExportException
Expression
ExtendedRequest
ExtendedResponse
Externalizable
FactoryConfigurationError
FailedLoginException
FeatureDescriptor
Fidelity
Field
FieldNameHelper
FieldNameHelper
FieldPosition
FieldView
File
FileCacheImageInputStream
FileCacheImageOutputStream
FileChannel
FileChannel.MapMode
FileChooserUI
FileDescriptor
FileDialog
FileFilter
FileFilter
FileHandler
FileImageInputStream
FileImageOutputStream
FileInputStream
FileLock
FileLockInterruptedException
FilenameFilter
FileNameMap
FileNotFoundException
FileOutputStream
FilePermission
FileReader
FileSystemView
FileView
FileWriter
Filter
FilteredImageSource
FilterInputStream
FilterOutputStream
FilterReader
FilterWriter
Finishings
FixedHeightLayoutCache
FixedHolder
FlatteningPathIterator
FlavorException

FlavorMap
FlavorTable
Float
FloatBuffer
FloatControl
FloatControl.Type
FloatHolder
FloatSeqHelper
FloatSeqHolder
FlowLayout
FlowView
FlowView.FlowStrategy
FocusAdapter
FocusEvent
FocusListener
FocusManager
FocusTraversalPolicy
Font
FontFormatException
FontMetrics
FontRenderContext
FontUIResource
Format
Format.Field
FormatConversionProvider
FormatMismatch
FormatMismatchHelper
Formatter
FormView
ForwardRequest
ForwardRequest
ForwardRequestHelper
ForwardRequestHelper
Frame
FREE_MEM
GapContent
GatheringByteChannel
GeneralPath
GeneralSecurityException
GlyphJustificationInfo
GlyphMetrics
GlyphVector
GlyphView
GlyphView.GlyphPainter
GradientPaint
GraphicAttribute
Graphics
Graphics2D
GraphicsConfigTemplate
GraphicsConfiguration

GraphicsDevice
GraphicsEnvironment
GrayFilter
GregorianCalendar
GridBagConstraints
GridBagLayout
GridLayout
Group
GSSContext
GSSCredential
GSSException
GSSManager
GSSName
Guard
GuardedObject
GZIPInputStream
GZIPOutputStream
Handler
HandlerBase
HandshakeCompletedEvent
HandshakeCompletedListener
HasControls
HashAttributeSet
HashDocAttributeSet
HashMap
HashPrintJobAttributeSet
HashPrintRequestAttributeSet
HashPrintServiceAttributeSet
HashSet
Hashtable
HeadlessException
HierarchyBoundsAdapter
HierarchyBoundsListener
HierarchyEvent
HierarchyListener
Highlighter
Highlighter.Highlight
Highlighter.HighlightPainter
HostnameVerifier
HTML
HTML.Attribute
HTML.Tag
HTML.UnknownTag
HTMLDocument
HTMLDocument.Iterator
HTMLEditorKit
HTMLEditorKit.HTMLFactory
HTMLEditorKit.HTMLTextAction
HTMLEditorKit.InsertHTMLTextAction
HTMLEditorKit.LinkController

HTMLEditorKit.Parser
HTMLEditorKit.ParserCallback
HTMLFrameHyperlinkEvent
HTMLWriter
HttpsURLConnection
HttpURLConnection
HyperlinkEvent
HyperlinkEvent.EventType
HyperlinkListener
ICC_ColorSpace
ICC_Profile
ICC_ProfileGray
ICC_ProfileRGB
Icon
IconUIResource
IconView
ID_ASSIGNMENT_POLICY_ID
ID_UNIQUENESS_POLICY_ID
IdAssignmentPolicy
IdAssignmentPolicyOperations
IdAssignmentPolicyValue
IdentifierHelper
Identity
IdentityHashMap
IdentityScope
IDLEntity
IDLType
IDLTypeHelper
IDLTypeOperations
IdUniquenessPolicy
IdUniquenessPolicyOperations
IdUniquenessPolicyValue
IIOByteBuffer
IIOException
IIOImage
IIOInvalidTreeException
IIOMetadata
IIOMetadataController
IIOMetadataFormat
IIOMetadataFormatImpl
IIOMetadataNode
IIOParam
IIOParamController
IIOReadProgressListener
IIOReadUpdateListener
IIOReadWarningListener
IIORegistry
IIOServiceProvider
IIOWriteProgressListener
IIOWriteWarningListener

IllegalAccessError
IllegalAccessException
IllegalArgumentException
IllegalBlockingModeException
IllegalBlockSizeException
IllegalCharsetNameException
IllegalComponentStateException
IllegalMonitorStateException
IllegalPathStateException
IllegalSelectorException
IllegalStateException
IllegalThreadStateException
Image
ImageCapabilities
ImageConsumer
ImageFilter
ImageGraphicAttribute
ImageIcon
ImageInputStream
ImageInputStreamImpl
ImageInputStreamSpi
ImageIO
ImageObserver
ImageOutputStream
ImageOutputStreamImpl
ImageOutputStreamSpi
ImageProducer
ImageReader
ImageReaderSpi
ImageReaderWriterSpi
ImageReadParam
ImageTranscoder
ImageTranscoderSpi
ImageTypeSpecifier
ImageView
ImageWriteParam
ImageWriter
ImageWriterSpi
ImagingOpException
IMP_LIMIT
IMPLICIT_ACTIVATION_POLICY_ID
ImplicitActivationPolicy
ImplicitActivationPolicyOperations
ImplicitActivationPolicyValue
IncompatibleClassChangeError
InconsistentTypeCode
InconsistentTypeCode
InconsistentTypeCodeHelper
IndexColorModel
IndexedPropertyDescriptor

IndexOutOfBoundsException
IndirectionException
Inet4Address
Inet6Address
InetAddress
InetSocketAddress
Inflater
InflaterInputStream
InheritableThreadLocal
InitialContext
InitialContextFactory
InitialContextFactoryBuilder
InitialDirContext
INITIALIZE
InitialLdapContext
InlineView
InputContext
InputEvent
InputMap
InputMapUIResource
InputMethod
InputMethodContext
InputMethodDescriptor
InputMethodEvent
InputMethodHighlight
InputMethodListener
InputMethodRequests
InputSource
InputStream
InputStream
InputStream
InputStreamReader
InputSubset
InputVerifier
Insets
InsetsUIResource
InstantiationError
InstantiationException
Instrument
InsufficientResourcesException
IntBuffer
Integer
IntegerSyntax
Interceptor
InterceptorOperations
INTERNAL
InternalError
InternalFrameAdapter
InternalFrameEvent
InternalFrameFocusTraversalPolicy

InternalFrameListener
InternalFrameUI
InternationalFormatter
InterruptedException
InterruptedIOException
InterruptedNamingException
InterruptibleChannel
INTF_REPOS
IntHolder
IntrospectionException
Introspector
INV_FLAG
INV_IDENT
INV_OBJREF
INV_POLICY
Invalid
INVALID_TRANSACTION
InvalidAddress
InvalidAddressHelper
InvalidAddressHolder
InvalidAlgorithmParameterException
InvalidAttributeIdentifierException
InvalidAttributesException
InvalidAttributeValueException
InvalidClassException
InvalidDnDOperationException
InvalidKeyException
InvalidKeySpecException
InvalidMarkException
InvalidMidiDataException
InvalidName
InvalidName
InvalidName
InvalidNameException
InvalidNameHelper
InvalidNameHelper
InvalidNameHolder
InvalidObjectException
InvalidParameterException
InvalidParameterSpecException
InvalidPolicy
InvalidPolicyHelper
InvalidPreferencesFormatException
InvalidSearchControlsException
InvalidSearchFilterException
InvalidSeq
InvalidSlot
InvalidSlotHelper
InvalidTransactionException
InvalidTypeForEncoding

InvalidTypeForEncodingHelper
InvalidValue
InvalidValue
InvalidValueHelper
InvocationEvent
InvocationHandler
InvocationTargetException
InvokeHandler
IOException
IOR
IORHelper
IORHolder
IORInfo
IORInfoOperations
IORInterceptor
IORInterceptorOperations
IObject
IObjectOperations
IstringHelper
ItemEvent
ItemListener
ItemSelectable
Iterator
IvParameterSpec
JApplet
JarEntry
JarException
JarFile
JarInputStream
JarOutputStream
JarURLConnection
JButton
JCheckBox
JCheckBoxMenuItem
JColorChooser
JComboBox
JComboBox.KeySelectionManager
JComponent
JDesktopPane
JDialog
JEditorPane
JFileChooser
JFormattedTextField
JFormattedTextField.AbstractFormatter
JFormattedTextField.AbstractFormatterFactory
JFrame
JInternalFrame
JInternalFrame.JDesktopIcon
JLabel
JLayeredPane

JList
JMenu
JMenuBar
JMenuItem
JobAttributes
JobAttributes.DefaultSelectionType
JobAttributes.DestinationType
JobAttributes.DialogType
JobAttributes.MultipleDocumentHandlingType
JobAttributes.SidesType
JobHoldUntil
JobImpressions
JobImpressionsCompleted
JobImpressionsSupported
JobKOctets
JobKOctetsProcessed
JobKOctetsSupported
JobMediaSheets
JobMediaSheetsCompleted
JobMediaSheetsSupported
JobMessageFromOperator
JobName
JobOriginatingUserName
JobPriority
JobPrioritySupported
JobSheets
JobState
JobStateReason
JobStateReasons
JOptionPane
JPanel
JPasswordField
JPEGHuffmanTable
JPEGImageReadParam
JPEGImageWriteParam
JPEGQTable
JPopupMenu
JPopupMenu.Separator
JProgressBar
JRadioButton
JRadioButtonMenuItem
JRootPane
JScrollBar
JScrollPane
JSeparator
JSlider
JSpinner
JSpinner.DateEditor
JSpinner.DefaultEditor
JSpinner.ListEditor

JSpinner.NumberEditor
JSplitPane
JTabbedPane
JTable
JTableHeader
JTextArea
JTextComponent
JTextComponent.KeyBinding
JTextField
JTextPane
JToggleButton
JToggleButton.ToggleButtonModel
JToolBar
JToolBar.Separator
JToolTip
JTree
JTree.DynamicUtilTreeNode
JTree.EmptySelectionModel
JViewport
JWindow
KerberosKey
KerberosPrincipal
KerberosTicket
Kernel
Key
KeyAdapter
KeyAgreement
KeyAgreementSpi
KeyboardFocusManager
KeyEvent
KeyEventDispatcher
KeyEventPostProcessor
KeyException
KeyFactory
KeyFactorySpi
KeyGenerator
KeyGeneratorSpi
KeyListener
KeyManagementException
KeyManager
KeyManagerFactory
KeyManagerFactorySpi
Keymap
KeyPair
KeyPairGenerator
KeyPairGeneratorSpi
KeySpec
KeyStore
KeyStoreException
KeyStoreSpi

KeyStroke
Label
LabelUI
LabelView
LanguageCallback
LastOwnerException
LayeredHighlighter
LayeredHighlighter.LayerPainter
LayoutFocusTraversalPolicy
LayoutManager
LayoutManager2
LayoutQueue
LDAPCertStoreParameters
LdapContext
LdapReferralException
Lease
Level
LexicalHandler
LIFESPAN_POLICY_ID
LifespanPolicy
LifespanPolicyOperations
LifespanPolicyValue
LimitExceededException
Line
Line.Info
Line2D
Line2D.Double
Line2D.Float
LineBorder
LineBreakMeasurer
LineEvent
LineEvent.Type
LineListener
LineMetrics
LineNumberInputStream
LineNumberReader
LineUnavailableException
LinkageError
LinkedHashMap
LinkedHashSet
LinkedList
LinkException
LinkLoopException
LinkRef
List
List
ListCellRenderer
ListDataEvent
ListDataListener
ListIterator

ListModel
ListResourceBundle
ListSelectionEvent
ListSelectionListener
ListSelectionModel
ListUI
ListView
LoaderHandler
Locale
LocalObject
LocateRegistry
LOCATION_FORWARD
Locator
LocatorImpl
Logger
LoggingPermission
LoginContext
LoginException
LoginModule
LogManager
LogRecord
LogStream
Long
LongBuffer
LongHolder
LongLongSeqHelper
LongLongSeqHolder
LongSeqHelper
LongSeqHolder
LookAndFeel
LookupOp
LookupTable
Mac
MacSpi
MalformedInputException
MalformedLinkException
MalformedURLException
ManagerFactoryParameters
Manifest
Map
Map.Entry
MappedByteBuffer
MARSHAL
MarshalException
MarshaledObject
MaskFormatter
Matcher
Math
MatteBorder
Media

MediaName
MediaPrintableArea
MediaSize
MediaSize.Engineering
MediaSize.ISO
MediaSize.JIS
MediaSize.NA
MediaSize.Other
MediaSizeName
MediaTracker
MediaTray
Member
MemoryCacheImageInputStream
MemoryCacheImageOutputStream
MemoryHandler
MemoryImageSource
Menu
MenuBar
MenuBarUI
MenuComponent
MenuContainer
MenuDragMouseEvent
MenuDragMouseListener
MenuElement
MenuEvent
MenuItem
MenuItemUI
MenuKeyEvent
MenuKeyListener
MenuListener
MenuSelectionManager
MenuShortcut
MessageDigest
MessageDigestSpi
MessageFormat
MessageFormat.Field
MessageProp
MetaEventListener
MetalBorders
MetalBorders.ButtonBorder
MetalBorders.Flush3DBorder
MetalBorders.InternalFrameBorder
MetalBorders.MenuBarBorder
MetalBorders.MenuItemBorder
MetalBorders.OptionDialogBorder
MetalBorders.PaletteBorder
MetalBorders.PopupMenuBorder
MetalBorders.RolloverButtonBorder
MetalBorders.ScrollPaneBorder
MetalBorders.TableHeaderBorder

MetalBorders.TextFieldBorder
MetalBorders.ToggleButtonBorder
MetalBorders.ToolBarBorder
MetalButtonUI
MetalCheckBoxIcon
MetalCheckBoxUI
MetalComboBoxButton
MetalComboBoxEditor
MetalComboBoxEditor.UIResource
MetalComboBoxIcon
MetalComboBoxUI
MetalDesktopIconUI
MetalFileChooserUI
MetalIconFactory
MetalIconFactory.FileIcon16
MetalIconFactory.FolderIcon16
MetalIconFactory.PaletteCloseIcon
MetalIconFactory.TreeControlIcon
MetalIconFactory.TreeFolderIcon
MetalIconFactory.TreeLeafIcon
MetalInternalFrameTitlePane
MetalInternalFrameUI
MetalLabelUI
MetalLookAndFeel
MetalPopupMenuSeparatorUI
MetalProgressBarUI
MetalRadioButtonUI
MetalRootPaneUI
MetalScrollBarUI
MetalScrollbar
MetalScrollPaneUI
MetalSeparatorUI
MetalSliderUI
MetalSplitPaneUI
MetalTabbedPaneUI
MetalTextFieldUI
MetalTheme
MetalToggleButtonUI
MetalToolBarUI
MetalToolTipUI
MetalTreeUI
MetaMessage
Method
MethodDescriptor
MidiChannel
MidiDevice
MidiDevice.Info
MidiDeviceProvider
MidiEvent
MidiFileFormat

MidiFileReader
MidiFileWriter
MidiMessage
MidiSystem
MidiUnavailableException
MimeTypeParseException
MinimalHTMLWriter
MissingResourceException
Mixer
Mixer.Info
MixerProvider
ModificationItem
Modifier
MouseAdapter
MouseDragGestureRecognizer
MouseEvent
MouseInputAdapter
MouseListener
MouseListener
MouseMotionAdapter
MouseMotionListener
MouseWheelEvent
MouseWheelListener
MultiButtonUI
MulticastSocket
MultiColorChooserUI
MultiComboBoxUI
MultiDesktopIconUI
MultiDesktopPaneUI
MultiDoc
MultiDocPrintJob
MultiDocPrintService
MultiFileChooserUI
MultiInternalFrameUI
MultiLabelUI
MultiListUI
MultiLookAndFeel
MultiMenuBarUI
MultiMenuItemUI
MultiOptionPaneUI
MultiPanelUI
MultiPixelPackedSampleModel
MultipleComponentProfileHelper
MultipleComponentProfileHolder
MultipleDocumentHandling
MultipleMaster
MultiPopupMenuUI
MultiProgressBarUI
MultiRootPaneUI
MultiScrollbarUI

MultiScrollPaneUI
MultiSeparatorUI
MultiSliderUI
MultiSpinnerUI
MultiSplitPaneUI
MultiTabbedPaneUI
MultiTableHeaderUI
MultiTableUI
MultiTextUI
MultiToolBarUI
MultiToolTipUI
MultiTreeUI
MultiViewportUI
MutableAttributeSet
MutableComboBoxModel
MutableTreeNode
Name
NameAlreadyBoundException
NameCallback
NameClassPair
NameComponent
NameComponentHelper
NameComponentHolder
NamedNodeMap
NamedValue
NameDynAnyPair
NameDynAnyPairHelper
NameDynAnyPairSeqHelper
NameHelper
NameHolder
NameNotFoundException
NameParser
NamespaceChangeListener
NamespaceSupport
NameValuePair
NameValuePair ~
NameValuePairHelper
NameValuePairHelper
NameValuePairSeqHelper
Naming
NamingContext
NamingContextExt
NamingContextExtHelper
NamingContextExtHolder
NamingContextExtOperations
NamingContextExtPOA
NamingContextHelper
NamingContextHolder
NamingContextOperations
NamingContextPOA

NamingEnumeration
NamingEvent
NamingException
NamingExceptionEvent
NamingListener
NamingManager
NamingSecurityException
NavigationFilter
NavigationFilter.FilterBypass
NegativeArraySizeException
NetPermission
NetworkInterface
NO_IMPLEMENT
NO_MEMORY
NO_PERMISSION
NO_RESOURCES
NO_RESPONSE
NoClassDefFoundError
NoConnectionPendingException
NoContext
NoContextHelper
Node
NodeChangeEvent
NodeChangeListener
NodeList
NoInitialContextException
NoninvertibleTransformException
NonReadableChannelException
NonWritableChannelException
NoPermissionException
NoRouteToHostException
NoServant
NoServantHelper
NoSuchAlgorithmException
NoSuchAttributeException
NoSuchElementException
NoSuchFieldError
NoSuchFieldException
NoSuchMethodError
NoSuchMethodException
NoSuchObjectException
NoSuchPaddingException
NoSuchProviderException
NotActiveException
Notation
NotBoundException
NotContextException
NotEmpty
NotEmptyHelper
NotEmptyHolder

NotFound
NotFoundHelper
NotFoundHolder
NotFoundReason
NotFoundReasonHelper
NotFoundReasonHolder
NotOwnerException
NotSerializableException
NotYetBoundException
NotYetConnectedException
NullCipher
NullPointerException
Number
NumberFormat
NumberFormat.Field
NumberFormatException
NumberFormatter
NumberOfDocuments
NumberOfInterveningJobs
NumberUp
NumberUpSupported
NumericShaper
NVList
OBJ_ADAPTER
Object
Object
OBJECT_NOT_EXIST
ObjectAlreadyActive
ObjectAlreadyActiveHelper
ObjectChangeListener
ObjectFactory
ObjectFactoryBuilder
ObjectHelper
ObjectHolder
ObjectIdHelper
ObjectImpl
ObjectImpl
ObjectInput
ObjectInputStream
ObjectInputStream.GetField
ObjectInputValidation
ObjectNotActive
ObjectNotActiveHelper
ObjectOutput
ObjectOutputStream
ObjectOutputStream.PutField
ObjectStreamClass
ObjectStreamConstants
ObjectStreamException
ObjectStreamField

ObjectView
ObjID
Observable
Observer
OctetSeqHelper
OctetSeqHolder
Oid
OMGVMCID
OpenType
Operation
OperationNotSupportedException
Option
OptionalDataException
OptionPaneUI
ORB
ORB
ORBInitializer
ORBInitializerOperations
ORBInitInfo
ORBInitInfoOperations
OrientationRequested
OutOfMemoryError
OutputDeviceAssigned
OutputKeys
OutputStream
OutputStream
OutputStream
OutputStreamWriter
OverlappingFileLockException
OverlayLayout
Owner
Package
PackedColorModel
Pageable
PageAttributes
PageAttributes.ColorType
PageAttributes.MediaType
PageAttributes.OrientationRequestedType
PageAttributes.OriginType
PageAttributes.PrintQualityType
PageFormat
PageRanges
PagesPerMinute
PagesPerMinuteColor
Paint
PaintContext
PaintEvent
Panel
PanelUI
Paper

ParagraphView
ParagraphView
Parameter
ParameterBlock
ParameterDescriptor
ParameterMetaData
ParameterMode
ParameterModeHelper
ParameterModeHolder
ParseException
ParsePosition
Parser
Parser
ParserAdapter
ParserConfigurationException
ParserDelegator
ParserFactory
PartialResultException
PasswordAuthentication
PasswordCallback
PasswordView
Patch
PathIterator
Pattern
PatternSyntaxException
PBEKey
PBEKeySpec
PBEParameterSpec
PDLOverrideSupported
Permission
Permission
PermissionCollection
Permissions
PERSIST_STORE
PersistenceDelegate
PhantomReference
Pipe
Pipe.SinkChannel
Pipe.SourceChannel
PipedInputStream
PipedOutputStream
PipedReader
PipedWriter
PixelGrabber
PixelInterleavedSampleModel
PKCS8EncodedKeySpec
PKIXBuilderParameters
PKIXCertPathBuilderResult
PKIXCertPathChecker
PKIXCertPathValidatorResult

PKIXParameters
PlainDocument
PlainView
POA
POAHelper
POAManager
POAManagerOperations
POAOperations
Point
Point2D
Point2D.Double
Point2D.Float
Policy
Policy
Policy
PolicyError
PolicyErrorCodeHelper
PolicyErrorHelper
PolicyErrorHolder
PolicyFactory
PolicyFactoryOperations
PolicyHelper
PolicyHolder
PolicyListHelper
PolicyListHolder
PolicyNode
PolicyOperations
PolicyQualifierInfo
PolicyTypeHelper
Polygon
PooledConnection
Popup
PopupFactory
PopupMenu
PopupMenuEvent
PopupMenuListener
PopupMenuUI
Port
Port.Info
PortableRemoteObject
PortableRemoteObjectDelegate
PortUnreachableException
Position
Position.Bias
PreferenceChangeEvent
PreferenceChangeListener
Preferences
PreferencesFactory
PreparedStatement
PresentationDirection

Principal
Principal
PrincipalHolder
Printable
PrinterAbortException
PrinterException
PrinterGraphics
PrinterInfo
PrinterIOException
PrinterIsAcceptingJobs
PrinterJob
PrinterLocation
PrinterMakeAndModel
PrinterMessageFromOperator
PrinterMoreInfo
PrinterMoreInfoManufacturer
PrinterName
PrinterResolution
PrinterState
PrinterStateReason
PrinterStateReasons
PrinterURI
PrintEvent
PrintException
PrintGraphics
PrintJob
PrintJobAdapter
PrintJobAttribute
PrintJobAttributeEvent
PrintJobAttributeListener
PrintJobAttributeSet
PrintJobEvent
PrintJobListener
PrintQuality
PrintRequestAttribute
PrintRequestAttributeSet
PrintService
PrintServiceAttribute
PrintServiceAttributeEvent
PrintServiceAttributeListener
PrintServiceAttributeSet
PrintServiceLookup
PrintStream
PrintWriter
PRIVATE_MEMBER
PrivateCredentialPermission
PrivateKey
PrivilegedAction
PrivilegedActionException
PrivilegedExceptionAction

Process
ProcessingInstruction
ProfileDataException
ProfileIdHelper
ProgressBarUI
ProgressMonitor
ProgressMonitorInputStream
Properties
PropertyChangeEvent
PropertyChangeListener
PropertyChangeListenerProxy
PropertyChangeSupport
PropertyDescriptor
PropertyEditor
PropertyEditorManager
PropertyEditorSupport
PropertyPermission
PropertyResourceBundle
PropertyVetoException
ProtectionDomain
ProtocolException
Provider
ProviderException
Proxy
PSSParameterSpec
PUBLIC_MEMBER
PublicKey
PushbackInputStream
PushbackReader
QuadCurve2D
QuadCurve2D.Double
QuadCurve2D.Float
QueuedJobCount
Random
RandomAccess
RandomAccessFile
Raster
RasterFormatException
RasterOp
RC2ParameterSpec
RC5ParameterSpec
ReadableByteChannel
Reader
ReadOnlyBufferException
Receiver
Rectangle
Rectangle2D
Rectangle2D.Double
Rectangle2D.Float
RectangularShape

Ref
RefAddr
Reference
Reference
Referenceable
ReferenceQueue
ReferenceUriSchemesSupported
ReferralException
ReflectPermission
Refreshable
RefreshFailedException
RegisterableService
Registry
RegistryHandler
RemarshalException
Remote
RemoteCall
RemoteException
RemoteObject
RemoteRef
RemoteServer
RemoteStub
RenderableImage
RenderableImageOp
RenderableImageProducer
RenderContext
RenderedImage
RenderedImageFactory
Renderer
RenderingHints
RenderingHints.Key
RepaintManager
ReplicateScaleFilter
RepositoryIdHelper
Request
REQUEST_PROCESSING_POLICY_ID
RequestInfo
RequestInfoOperations
RequestingUserName
RequestProcessingPolicy
RequestProcessingPolicyOperations
RequestProcessingPolicyValue
RescaleOp
ResolutionSyntax
Resolver
ResolveResult
ResourceBundle
ResponseHandler
Result
ResultSet

All Classes (Java 2 Platform SE v1.4.1)

SAXParser
SAXParserFactory
SAXResult
SAXSource
SAXTransformerFactory
ScatteringByteChannel
SchemaViolationException
Scrollable
Scrollbar
ScrollBarUI
ScrollPane
ScrollPaneAdjustable
ScrollPaneConstants
ScrollPaneLayout
ScrollPaneLayout.UIResource
ScrollPaneUI
SealedObject
SearchControls
SearchResult
SecretKey
SecretKeyFactory
SecretKeyFactorySpi
SecretKeySpec
SecureClassLoader
SecureRandom
SecureRandomSpi
Security
SecurityException
SecurityManager
SecurityPermission
Segment
SelectableChannel
SelectionKey
Selector
SelectorProvider
SeparatorUI
Sequence
SequenceInputStream
Sequencer
Sequencer.SyncMode
Serializable
SerializablePermission
Servant
SERVANT_RETENTION_POLICY_ID
ServantActivator
ServantActivatorHelper
ServantActivatorOperations
ServantActivatorPOA
ServantAlreadyActive
ServantAlreadyActiveHelper

[ServantLocator](#)
[ServantLocatorHelper](#)
[ServantLocatorOperations](#)
[ServantLocatorPOA](#)
[ServantManager](#)
[ServantManagerOperations](#)
[ServantNotActive](#)
[ServantNotActiveHelper](#)
[ServantObject](#)
[ServantRetentionPolicy](#)
[ServantRetentionPolicyOperations](#)
[ServantRetentionPolicyValue](#)
[ServerCloneException](#)
[ServerError](#)
[ServerException](#)
[ServerNotActiveException](#)
[ServerRef](#)
[ServerRequest](#)
[ServerRequestInfo](#)
[ServerRequestInfoOperations](#)
[ServerRequestInterceptor](#)
[ServerRequestInterceptorOperations](#)
[ServerRuntimeException](#)
[ServerSocket](#)
[ServerSocketChannel](#)
[ServerSocketFactory](#)
[ServiceContext](#)
[ServiceContextHelper](#)
[ServiceContextHolder](#)
[ServiceContextListHelper](#)
[ServiceContextListHolder](#)
[ServiceDetail](#)
[ServiceDetailHelper](#)
[ServiceIdHelper](#)
[ServiceInformation](#)
[ServiceInformationHelper](#)
[ServiceInformationHolder](#)
[ServicePermission](#)
[ServiceRegistry](#)
[ServiceRegistry.Filter](#)
[ServiceUI](#)
[ServiceUIFactory](#)
[ServiceUnavailableException](#)
[Set](#)
[SetOfIntegerSyntax](#)
[SetOverrideType](#)
[SetOverrideTypeHelper](#)
[Severity](#)
[Shape](#)
[ShapeGraphicAttribute](#)

SheetCollate
Short
ShortBuffer
ShortBufferException
ShortHolder
ShortLookupTable
ShortMessage
ShortSeqHelper
ShortSeqHolder
Sides
Signature
SignatureException
SignatureSpi
SignedObject
Signer
SimpleAttributeSet
SimpleBeanInfo
SimpleDateFormat
SimpleDoc
SimpleFormatter
SimpleTimeZone
SinglePixelPackedSampleModel
SingleSelectionModel
Size2DSyntax
SizeLimitExceededException
SizeRequirements
SizeSequence
Skeleton
SkeletonMismatchException
SkeletonNotFoundException
SliderUI
Socket
SocketAddress
SocketChannel
SocketException
SocketFactory
SocketHandler
SocketImpl
SocketImplFactory
SocketOptions
SocketPermission
SocketSecurityException
SocketTimeoutException
SoftBevelBorder
SoftReference
SortedMap
SortedSet
SortingFocusTraversalPolicy
Soundbank
SoundbankReader

SoundbankResource
Source
SourceDataLine
SourceLocator
SpinnerDateModel
SpinnerListModel
SpinnerModel
SpinnerNumberModel
SpinnerUI
SplitPaneUI
Spring
SpringLayout
SpringLayout.Constraints
SQLData
SQLException
SQLInput
SQLOutput
SQLPermission
SQLWarning
SSLContext
SSLContextSpi
SSLException
SSLHandshakeException
SSLKeyException
SSLPeerUnverifiedException
SSLPermission
SSLProtocolException
SSLServerSocket
SSLServerSocketFactory
SSLSession
SSLSessionBindingEvent
SSLSessionBindingListener
SSLSessionContext
SSLSocket
SSLSocketFactory
Stack
StackOverflowError
StackTraceElement
StartTlsRequest
StartTlsResponse
State
StateEdit
StateEditable
StateFactory
Statement
Statement
Streamable
StreamableValue
StreamCorruptedException
StreamHandler

StreamPrintService
StreamPrintServiceFactory
StreamResult
StreamSource
StreamTokenizer
StrictMath
String
StringBuffer
StringBufferInputStream
StringCharacterIterator
StringContent
StringHolder
StringIndexOutOfBoundsException
StringNameHelper
StringReader
StringRefAddr
StringSelection
StringSeqHelper
StringSeqHolder
StringTokenizer
StringValueHelper
StringWriter
Stroke
Struct
StructMember
StructMemberHelper
Stub
StubDelegate
StubNotFoundException
Style
StyleConstants
StyleConstants.CharacterConstants
StyleConstants.ColorConstants
StyleConstants.FontConstants
StyleConstants.ParagraphConstants
StyleContext
StyledDocument
StyledEditorKit
StyledEditorKit.AlignmentAction
StyledEditorKit.BoldAction
StyledEditorKit.FontFamilyAction
StyledEditorKit.FontSizeAction
StyledEditorKit.ForegroundAction
StyledEditorKit.ItalicAction
StyledEditorKit.StyledTextAction
StyledEditorKit.UnderlineAction
StyleSheet
StyleSheet.BoxPainter
StyleSheet.ListPainter
Subject

SubjectDomainCombiner
SUCCESSFUL
SupportedValuesAttribute
SwingConstants
SwingPropertyChangeSupport
SwingUtilities
SYNC_WITH_TRANSPORT
SyncFailedException
SyncScopeHelper
Synthesizer
SysexMessage
System
SYSTEM_EXCEPTION
SystemColor
SystemException
SystemFlavorMap
TabableView
TabbedPaneUI
TabExpander
TableCellEditor
TableCellRenderer
TableColumn
TableColumnModel
TableColumnModelEvent
TableColumnModelListener
TableHeaderUI
TableModel
TableModelEvent
TableModelListener
TableUI
TableView
TabSet
TabStop
TAG_ALTERNATE_IIO_P_ADDRESS
TAG_CODE_SETS
TAG_INTERNET_IOP
TAG_JAVA_CODEBASE
TAG_MULTIPLE_COMPONENTS
TAG_ORB_TYPE
TAG_POLICIES
TagElement
TaggedComponent
TaggedComponentHelper
TaggedComponentHolder
TaggedProfile
TaggedProfileHelper
TaggedProfileHolder
TargetDataLine
TCKind
Templates

TemplatesHandler
Text
TextAction
TextArea
TextAttribute
TextComponent
TextEvent
TextField
TextHitInfo
TextInputCallback
TextLayout
TextLayout.CaretPolicy
TextListener
TextMeasurer
TextOutputCallback
TextSyntax
TextUI
TexturePaint
Thread
THREAD_POLICY_ID
ThreadDeath
ThreadGroup
ThreadLocal
ThreadPolicy
ThreadPolicyOperations
ThreadPolicyValue
Throwable
Tie
TileObserver
Time
TimeLimitExceededException
Timer
Timer
TimerTask
Timestamp
TimeZone
TitledBorder
ToolBarUI
Toolkit
ToolTipManager
ToolTipUI
TooManyListenersException
Track
TRANSACTION_REQUIRED
TRANSACTION_ROLLEDBACK
TransactionRequiredException
TransactionRolledbackException
TransactionService
Transferable
TransferHandler

TransformAttribute
Transformer
TransformerConfigurationException
TransformerException
TransformerFactory
TransformerFactoryConfigurationError
TransformerHandler
TRANSIENT
Transmitter
Transparency
TRANSPORT_RETRY
TreeCellEditor
TreeCellRenderer
TreeExpansionEvent
TreeExpansionListener
TreeMap
TreeModel
TreeModelEvent
TreeModelListener
TreeNode
TreePath
TreeSelectionEvent
TreeSelectionListener
TreeSelectionModel
TreeSet
TreeUI
TreeWillExpandListener
TrustAnchor
TrustManager
TrustManagerFactory
TrustManagerFactorySpi
TypeCode
TypeCodeHolder
TypeMismatch
TypeMismatch
TypeMismatch
TypeMismatchHelper
TypeMismatchHelper
Types
UID
UIDefaults
UIDefaults.ActiveValue
UIDefaults.LazyInputMap
UIDefaults.LazyValue
UIDefaults.ProxyLazyValue
UIManager
UIManager.LookAndFeelInfo
UIResource
ULongLongSeqHelper
ULongLongSeqHolder

ULongSeqHelper
ULongSeqHolder
UndeclaredThrowableException
UndoableEdit
UndoableEditEvent
UndoableEditListener
UndoableEditSupport
UndoManager
UnexpectedException
UnicastRemoteObject
UnionMember
UnionMemberHelper
UNKNOWN
UnknownEncoding
UnknownEncodingHelper
UnknownError
UnknownException
UnknownGroupException
UnknownHostException
UnknownHostException
UnknownObjectException
UnknownServiceException
UnknownUserException
UnknownUserExceptionHelper
UnknownUserExceptionHandler
UnmappableCharacterException
UnmarshalException
UnmodifiableSetException
UnrecoverableKeyException
Unreferenced
UnresolvedAddressException
UnresolvedPermission
UnsatisfiedLinkError
UnsolicitedNotification
UnsolicitedNotificationEvent
UnsolicitedNotificationListener
UNSUPPORTED_POLICY
UNSUPPORTED_POLICY_VALUE
UnsupportedAddressTypeException
UnsupportedAudioFileException
UnsupportedCallbackException
UnsupportedCharsetException
UnsupportedClassVersionError
UnsupportedEncodingException
UnsupportedFlavorException
UnsupportedLookAndFeelException
UnsupportedOperationException
URI
URIException
URIResolver

URISyntax
URISyntaxException
URL
URLClassLoader
URLConnection
URLDecoder
URLEncoder
URLStreamHandler
URLStreamHandlerFactory
URLStringHelper
USER_EXCEPTION
UserException
UShortSeqHelper
UShortSeqHolder
UTFDataFormatException
Util
UtilDelegate
Utilities
ValueBase
ValueBaseHelper
ValueBaseHolder
ValueFactory
ValueHandler
ValueMember
ValueMemberHelper
VariableHeightLayoutCache
Vector
VerifyError
VersionSpecHelper
VetoableChangeListener
VetoableChangeListenerProxy
VetoableChangeSupport
View
ViewFactory
ViewportLayout
ViewportUI
VirtualMachineError
Visibility
VisibilityHelper
VM_ABSTRACT
VM_CUSTOM
VM_NONE
VM_TRUNCATABLE
VMID
VoiceStatus
Void
VolatileImage
WCharSeqHelper
WCharSeqHolder
WeakHashMap

WeakReference
Window
WindowAdapter
WindowConstants
WindowEvent
WindowFocusListener
WindowListener
WindowStateListener
WrappedPlainView
WritableByteChannel
WritableRaster
WritableRenderedImage
WriteAbortedException
Writer
WrongAdapter
WrongAdapterHelper
WrongPolicy
WrongPolicyHelper
WrongTransaction
WrongTransactionHelper
WrongTransactionHolder
WStringSeqHelper
WStringSeqHolder
WStringValueHelper
X500Principal
X500PrivateCredential
X509Certificate
X509Certificate
X509CertSelector
X509CRL
X509CRLEntry
X509CRLSelector
X509EncodedKeySpec
X509Extension
X509KeyManager
X509TrustManager
XAConnection
XADataSource
XAException
XAResource
Xid
XMLDecoder
XMLEncoder
XMLFilter
XMLFilterImpl
XMLFormatter
XMLReader
XMLReaderAdapter
XMLReaderFactory
ZipEntry

ZipException
ZipFile
ZipInputStream
ZipOutputStream
ZoneView
_BindingIteratorImplBase
_BindingIteratorStub
_DynAnyFactoryStub
_DynAnyStub
_DynArrayStub
_DynEnumStub
_DynFixedStub
_DynSequenceStub
_DynStructStub
_DynUnionStub
_DynValueStub
_IDLTypeStub
_NamingContextExtStub
_NamingContextImplBase
_NamingContextStub
_PolicyStub
_Remote_Stub
_ServantActivatorStub
_ServantLocatorStub

BasicToolBarSeparatorUI() - Constructor for class javax.swing.plaf.basic.BasicToolBarSeparatorUI

BasicToolBarUI - class javax.swing.plaf.basic.BasicToolBarUI.

A Basic L&F implementation of ToolBarUI.

BasicToolBarUI.DockingListener - class javax.swing.plaf.basic.BasicToolBarUI.DockingListener.

This inner class is marked "public" due to a compiler bug.

BasicToolBarUI.DockingListener(BasicToolBarUI, JToolBar) - Constructor for class javax.swing.plaf.basic.BasicToolBarUI.DockingListener

BasicToolBarUI.DragWindow - class javax.swing.plaf.basic.BasicToolBarUI.DragWindow.

BasicToolBarUI.FrameListener - class javax.swing.plaf.basic.BasicToolBarUI.FrameListener.

BasicToolBarUI.FrameListener(BasicToolBarUI) - Constructor for class javax.swing.plaf.basic.BasicToolBarUI.FrameListener

BasicToolBarUI.PropertyListener - class javax.swing.plaf.basic.BasicToolBarUI.PropertyListener.

BasicToolBarUI.PropertyListener(BasicToolBarUI) - Constructor for class javax.swing.plaf.basic.BasicToolBarUI.PropertyListener

BasicToolBarUI.ToolBarContListener - class javax.swing.plaf.basic.BasicToolBarUI.ToolBarContListener.

BasicToolBarUI.ToolBarContListener(BasicToolBarUI) - Constructor for class javax.swing.plaf.basic.BasicToolBarUI.ToolBarContListener

BasicToolBarUI.ToolBarFocusListener - class javax.swing.plaf.basic.BasicToolBarUI.ToolBarFocusListener.

BasicToolBarUI.ToolBarFocusListener(BasicToolBarUI) - Constructor for class javax.swing.plaf.basic.BasicToolBarUI.ToolBarFocusListener

BasicToolBarUI() - Constructor for class javax.swing.plaf.basic.BasicToolBarUI

BasicToolTipUI - class javax.swing.plaf.basic.BasicToolTipUI.

Standard tool tip L&F.

BasicToolTipUI() - Constructor for class javax.swing.plaf.basic.BasicToolTipUI

BasicTreeUI - class javax.swing.plaf.basic.BasicTreeUI.

The basic L&F for a hierarchical data structure.

BasicTreeUI.CellEditorHandler - class javax.swing.plaf.basic.BasicTreeUI.CellEditorHandler.

Listener responsible for getting cell editing events and updating the tree accordingly.

BasicTreeUI.CellEditorHandler(BasicTreeUI) - Constructor for class javax.swing.plaf.basic.BasicTreeUI.CellEditorHandler

BasicTreeUI.ComponentHandler - class javax.swing.plaf.basic.BasicTreeUI.ComponentHandler.

Updates the preferred size when scrolling (if necessary).

BasicTreeUI.ComponentHandler(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.ComponentHandler

BasicTreeUI.FocusHandler - class javax.swing.plaf.basic.BasicTreeUI.FocusHandler.

Repaints the lead selection row when focus is lost/gained.

BasicTreeUI.FocusHandler(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.FocusHandler

BasicTreeUI.KeyHandler - class javax.swing.plaf.basic.BasicTreeUI.KeyHandler.

This is used to get multiple key down events to appropriately generate events.

BasicTreeUI.KeyHandler(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.KeyHandler

BasicTreeUI.MouseHandler - class javax.swing.plaf.basic.BasicTreeUI.MouseHandler.

TreeMouseListener is responsible for updating the selection based on mouse events.

BasicTreeUI.MouseHandler(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.MouseHandler

BasicTreeUI.MouseInputHandler - class javax.swing.plaf.basic.BasicTreeUI.MouseInputHandler.

MouseInputHandler handles passing all mouse events, including mouse motion events, until the mouse is released to the destination it is constructed with.

BasicTreeUI.MouseInputHandler(BasicTreeUI, Component, Component, MouseEvent) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.MouseInputHandler

BasicTreeUI.NodeDimensionsHandler - class javax.swing.plaf.basic.BasicTreeUI.NodeDimensionsHandler.

Class responsible for getting size of node, method is forwarded to BasicTreeUI method.

BasicTreeUI.NodeDimensionsHandler(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.NodeDimensionsHandler

BasicTreeUI.PropertyChangeListener - class javax.swing.plaf.basic.BasicTreeUI.PropertyChangeListener.

PropertyChangeListener for the tree.

BasicTreeUI.PropertyChangeListener(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.PropertyChangeListener

BasicTreeUI.SelectionModelPropertyChangeListener - class

javax.swing.plaf.basic.BasicTreeUI.SelectionModelPropertyChangeListener.

Listener on the TreeSelectionModel, resets the row selection if any of the properties of the model change.

BasicTreeUI.SelectionModelPropertyChangeListener(BasicTreeUI) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.SelectionModelPropertyChangeListener

BasicTreeUI.TreeCancelEditingAction - class javax.swing.plaf.basic.BasicTreeUI.TreeCancelEditingAction.

ActionListener that invokes cancelEditing when action performed.

BasicTreeUI.TreeCancelEditingAction(BasicTreeUI, String) - Constructor for class

javax.swing.plaf.basic.BasicTreeUI.TreeCancelEditingAction

BasicTreeUI.TreeExpansionHandler - class javax.swing.plaf.basic.BasicTreeUI.TreeExpansionHandler.

Updates the TreeState in response to nodes expanding/collapsing.

BasicTreeUI.TreeExpansionHandler(BasicTreeUI) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeExpansionHandler

BasicTreeUI.TreeHomeAction - class javax.swing.plaf.basic.BasicTreeUI.TreeHomeAction.
TreeHomeAction is used to handle end/home actions.

BasicTreeUI.TreeHomeAction(BasicTreeUI, int, String) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeHomeAction

BasicTreeUI.TreeIncrementAction - class javax.swing.plaf.basic.BasicTreeUI.TreeIncrementAction.
TreeIncrementAction is used to handle up/down actions.

BasicTreeUI.TreeIncrementAction(BasicTreeUI, int, String) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeIncrementAction

BasicTreeUI.TreeModelHandler - class javax.swing.plaf.basic.BasicTreeUI.TreeModelHandler.
Forwards all TreeModel events to the TreeState.

BasicTreeUI.TreeModelHandler(BasicTreeUI) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeModelHandler

BasicTreeUI.TreePageAction - class javax.swing.plaf.basic.BasicTreeUI.TreePageAction.
TreePageAction handles page up and page down events.

BasicTreeUI.TreePageAction(BasicTreeUI, int, String) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreePageAction

BasicTreeUI.TreeSelectionHandler - class javax.swing.plaf.basic.BasicTreeUI.TreeSelectionHandler.
Listens for changes in the selection model and updates the display accordingly.

BasicTreeUI.TreeSelectionHandler(BasicTreeUI) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeSelectionHandler

BasicTreeUI.TreeToggleAction - class javax.swing.plaf.basic.BasicTreeUI.TreeToggleAction.
For the first selected row expandedness will be toggled.

BasicTreeUI.TreeToggleAction(BasicTreeUI, String) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeToggleAction

BasicTreeUI.TreeTraverseAction - class javax.swing.plaf.basic.BasicTreeUI.TreeTraverseAction.
TreeTraverseAction is the action used for left/right keys.

BasicTreeUI.TreeTraverseAction(BasicTreeUI, int, String) - Constructor for class
javax.swing.plaf.basic.BasicTreeUI.TreeTraverseAction

BasicTreeUI() - Constructor for class javax.swing.plaf.basic.BasicTreeUI

BasicViewportUI - class javax.swing.plaf.basic.BasicViewportUI.
BasicViewport implementation

BasicViewportUI() - Constructor for class javax.swing.plaf.basic.BasicViewportUI

BATCHSIZE - Static variable in interface javax.naming.Context

Constant that holds the name of the environment property for specifying the batch size to use when
returning data via the service's protocol.

BatchUpdateException - exception java.sql.BatchUpdateException.

An exception thrown when an error occurs during a batch update operation.

BatchUpdateException() - Constructor for class java.sql.BatchUpdateException

Constructs a BatchUpdateException object with the reason, SQLState, and update count initialized to null and the vendor code initialized to 0.

BatchUpdateException(int[]) - Constructor for class java.sql.BatchUpdateException

Constructs a BatchUpdateException initialized to null for the reason and SQLState and 0 for the vendor code.

BatchUpdateException(String, int[]) - Constructor for class java.sql.BatchUpdateException

Constructs a BatchUpdateException initialized with reason, updateCounts and null for the SQLState and 0 for the vendorCode.

BatchUpdateException(String, String, int[]) - Constructor for class java.sql.BatchUpdateException

Constructs a BatchUpdateException initialized with the given arguments (reason, SQLState, and updateCounts) and 0 for the vendor code.

BatchUpdateException(String, String, int, int[]) - Constructor for class java.sql.BatchUpdateException

Constructs a fully-specified BatchUpdateException object, initializing it with the given values.

BC - Static variable in class java.util.GregorianCalendar

Value of the ERA field indicating the period before the common era (before Christ), also known as BCE.

bcmListeners - Variable in class java.beans.beancontext.BeanContextSupport

all accesses to the protected ArrayList bcmListeners field shall be synchronized on that object.

bcsChildren() - Method in class java.beans.beancontext.BeanContextSupport

Returns an iterator of all children of this BeanContext.

bcsListeners - Variable in class java.beans.beancontext.BeanContextServicesSupport

List of BeanContextServicesListener objects.

bcsPreDeserializationHook(ObjectInputStream) - Method in class java.beans.beancontext.BeanContextSupport

called by readObject after defaultReadObject() but prior to deserialization of any children.

bcsPreDeserializationHook(ObjectInputStream) - Method in class

java.beans.beancontext.BeanContextServicesSupport

called from BeanContextSupport readObject before it deserializes the children ...

bcsPreSerializationHook(ObjectOutputStream) - Method in class java.beans.beancontext.BeanContextSupport

called by writeObject after defaultWriteObject() but prior to serialization of currently serializable children.

bcsPreSerializationHook(ObjectOutputStream) - Method in class

java.beans.beancontext.BeanContextServicesSupport

called from BeanContextSupport writeObject before it serializes the children ...

beanContext - Variable in class java.beans.beancontext.BeanContextChildSupport

BeanContext - interface java.beans.beancontext.BeanContext.

The BeanContext acts a logical hierarchical container for JavaBeans.

BeanContextChild - interface java.beans.beancontext.BeanContextChild.

JavaBeans wishing to be nested within, and obtain a reference to their execution environment, or context, as defined by the BeanContext sub-interface shall implement this interface.

BeanContextChildComponentProxy - interface java.beans.beancontext.BeanContextChildComponentProxy.

This interface is implemented by BeanContextChildren that have an AWT Component associated with them.

beanContextChildPeer - Variable in class java.beans.beancontext.BeanContextChildSupport

The BeanContext in which this BeanContextChild is nested.

BeanContextChildSupport - class java.beans.beancontext.**BeanContextChildSupport**.

This is a general support class to provide support for implementing the BeanContextChild protocol.

BeanContextChildSupport() - Constructor for class java.beans.beancontext.**BeanContextChildSupport**

construct a BeanContextChildSupport where this class has been subclassed in order to implement the JavaBean component itself.

BeanContextChildSupport(BeanContextChild) - Constructor for class

java.beans.beancontext.**BeanContextChildSupport**

construct a BeanContextChildSupport where the JavaBean component itself implements BeanContextChild, and encapsulates this, delegating that interface to this implementation

BeanContextContainerProxy - interface java.beans.beancontext.**BeanContextContainerProxy**.

This interface is implemented by BeanContexts' that have an AWT Container associated with them.

BeanContextEvent - class java.beans.beancontext.**BeanContextEvent**.

BeanContextEvent is the abstract root event class for all events emitted from, and pertaining to the semantics of, a BeanContext.

BeanContextEvent(BeanContext) - Constructor for class java.beans.beancontext.**BeanContextEvent**

Construct a BeanContextEvent

BeanContextMembershipEvent - class java.beans.beancontext.**BeanContextMembershipEvent**.

A BeanContextMembershipEvent encapsulates the list of children added to, or removed from, the membership of a particular BeanContext.

BeanContextMembershipEvent(BeanContext, Collection) - Constructor for class

java.beans.beancontext.**BeanContextMembershipEvent**

Construct a BeanContextMembershipEvent

BeanContextMembershipEvent(BeanContext, Object[]) - Constructor for class

java.beans.beancontext.**BeanContextMembershipEvent**

Construct a BeanContextMembershipEvent

BeanContextMembershipListener - interface java.beans.beancontext.**BeanContextMembershipListener**.

Compliant BeanContexts fire events on this interface when the state of the membership of the BeanContext changes.

BeanContextProxy - interface java.beans.beancontext.**BeanContextProxy**.

This interface is implemented by a JavaBean that does not directly have a BeanContext(Child) associated with it (via implementing that interface or a subinterface thereof), but has a public BeanContext(Child) delegated from it.

BeanContextServiceAvailableEvent - class java.beans.beancontext.**BeanContextServiceAvailableEvent**.

This event type is used by the BeanContextServicesListener in order to identify the service being registered.

BeanContextServiceAvailableEvent(BeanContextServices, Class) - Constructor for class

java.beans.beancontext.**BeanContextServiceAvailableEvent**

Construct a BeanContextServiceAvailableEvent.

BeanContextServiceProvider - interface java.beans.beancontext.**BeanContextServiceProvider**.

One of the primary functions of a BeanContext is to act as a rendezvous between JavaBeans, and BeanContextServiceProviders.

BeanContextServiceProviderBeanInfo - interface

java.beans.beancontext.**BeanContextServiceProviderBeanInfo**.

A BeanContextServiceProvider implementor who wishes to provide explicit information about the services their bean may provide shall implement a BeanInfo class that implements this BeanInfo subinterface and provides explicit information about the methods, properties, events, etc, of their services.

BeanContextServiceRevokedEvent - class java.beans.beancontext.BeanContextServiceRevokedEvent.

This event type is used by the BeanContextServiceRevokedListener in order to identify the service being revoked.

BeanContextServiceRevokedEvent(BeanContextServices, Class, boolean) - Constructor for class java.beans.beancontext.BeanContextServiceRevokedEvent

Construct a BeanContextServiceEvent.

BeanContextServiceRevokedListener - interface java.beans.beancontext.BeanContextServiceRevokedListener.

The listener interface for receiving BeanContextServiceRevokedEvent objects.

BeanContextServices - interface java.beans.beancontext.BeanContextServices.

The BeanContextServices interface provides a mechanism for a BeanContext to expose generic "services" to the BeanContextChild objects within.

BeanContextServicesListener - interface java.beans.beancontext.BeanContextServicesListener.

The listener interface for receiving BeanContextServiceAvailableEvent objects.

BeanContextServicesSupport - class java.beans.beancontext.BeanContextServicesSupport.

This helper class provides a utility implementation of the java.beans.beancontext.BeanContextServices interface.

BeanContextServicesSupport.BCSSChild - class

java.beans.beancontext.BeanContextServicesSupport.BCSSChild.

BeanContextServicesSupport.BCSSProxyServiceProvider - class

java.beans.beancontext.BeanContextServicesSupport.BCSSProxyServiceProvider.

BeanContextServicesSupport.BCSSServiceProvider - class

java.beans.beancontext.BeanContextServicesSupport.BCSSServiceProvider.

subclasses may subclass this nested class to add behaviors for each BeanContextServicesProvider.

BeanContextServicesSupport() - Constructor for class java.beans.beancontext.BeanContextServicesSupport

Create an instance that is not a delegate of another object

BeanContextServicesSupport(BeanContextServices) - Constructor for class

java.beans.beancontext.BeanContextServicesSupport

Create an instance with a peer

BeanContextServicesSupport(BeanContextServices, Locale) - Constructor for class

java.beans.beancontext.BeanContextServicesSupport

Create an instance using the specified locale

BeanContextServicesSupport(BeanContextServices, Locale, boolean) - Constructor for class

java.beans.beancontext.BeanContextServicesSupport

Create an instance using the specified Locale and design mode.

BeanContextServicesSupport(BeanContextServices, Locale, boolean, boolean) - Constructor for class

java.beans.beancontext.BeanContextServicesSupport

Construct a BeanContextServicesSupport instance

BeanContextSupport - class java.beans.beancontext.BeanContextSupport.

This helper class provides a utility implementation of the java.beans.beancontext.BeanContext interface.

BeanContextSupport.BCSChild - class java.beans.beancontext.BeanContextSupport.BCSChild.

BeanContextSupport.BCSIterator - class java.beans.beancontext.BeanContextSupport.BCSIterator.

protected final subclass that encapsulates an iterator but implements a noop remove() method.

BeanContextSupport() - Constructor for class java.beans.beancontext.BeanContextSupport

Create an instance that is not a delegate of another object

BeanContextSupport(Bea nContext) - Constructor for class java.beans.bea ncontext.Bea nContextSupport

Create an instance using with a default locale

BeanContextSupport(Bea nContext, Locale) - Constructor for class

java.beans.bea ncontext.Bea nContextSupport

Create an instance using the specified locale

BeanContextSupport(Bea nContext, Locale, boolean) - Constructor for class

java.beans.bea ncontext.Bea nContextSupport

Create an instance using the specified Locale and design mode.

BeanContextSupport(Bea nContext, Locale, boolean, boolean) - Constructor for class

java.beans.bea ncontext.Bea nContextSupport

Construct a BeanContextSupport instance

BeanDescriptor - class java.beans.Bea nDescriptor.

A BeanDescriptor provides global information about a "bean", including its Java class, its displayName, etc.

BeanDescriptor(Class) - Constructor for class java.beans.Bea nDescriptor

Create a BeanDescriptor for a bean that doesn't have a customizer.

BeanDescriptor(Class, Class) - Constructor for class java.beans.Bea nDescriptor

Create a BeanDescriptor for a bean that has a customizer.

BeanInfo - interface java.beans.Bea nInfo.

A bean implementor who wishes to provide explicit information about their bean may provide a

BeanInfo class that implements this BeanInfo interface and provides explicit information about the methods, properties, events, etc, of their bean.

Beans - class java.beans.Bea ns.

This class provides some general purpose beans control methods.

Beans() - Constructor for class java.beans.Bea ns

beep() - Method in class java.awt.Tool kit

Emits an audio beep.

beepAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the action to create a beep.

BEFORE_FIRST_LINE - Static variable in class java.awt.BorderLayout

The component comes before the first line of the layout's content.

BEFORE_LINE_BEGINS - Static variable in class java.awt.BorderLayout

The component goes at the beginning of the line direction for the layout.

before(Date) - Method in class java.util.Date

Tests if this date is before the specified date.

before(Object) - Method in class java.util.Calendar

Compares the time field records.

before(Timestamp) - Method in class java.sql.Timestamp

Indicates whether this Timestamp object is earlier than the given Timestamp object.

beforeFirst() - Method in interface java.sql.ResultSet

Moves the cursor to the front of this ResultSet object, just before the first row.

beforeOffset(int) - Static method in class java.awt.font.TextHitInfo

Creates a TextHitInfo at the specified offset, associated with the character before the offset.

beginAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the Action for moving the caret to the beginning of the document.

beginDragDividerLocation - Variable in class javax.swing.plaf.basic.**BasicSplitPaneUI**

Location of the divider when the dragging session began.

beginDraggingFrame(JComponent) - Method in interface javax.swing.**DesktopManager**

This method is normally called when the user has indicated that they will begin dragging a component around.

beginDraggingFrame(JComponent) - Method in class javax.swing.**DefaultDesktopManager**

beginLineAction - Static variable in class javax.swing.text.**DefaultEditorKit**

Name of the Action for moving the caret to the beginning of a line.

beginParagraphAction - Static variable in class javax.swing.text.**DefaultEditorKit**

Name of the Action for moving the caret to the beginning of a paragraph.

beginResizingFrame(JComponent, int) - Method in interface javax.swing.**DesktopManager**

This methods is normally called when the user has indicated that they will begin resizing the frame.

beginResizingFrame(JComponent, int) - Method in class javax.swing.**DefaultDesktopManager**

beginUpdate() - Method in class javax.swing.undo.**UndoableEditSupport**

beginWordAction - Static variable in class javax.swing.text.**DefaultEditorKit**

Name of the Action for moving the caret to the beginning of a word.

BELOW_BOTTOM - Static variable in class javax.swing.border.**TitledBorder**

Position the title below the border's bottom line.

BELOW_TOP - Static variable in class javax.swing.border.**TitledBorder**

Position the title below the border's top line.

BENGALI - Static variable in class java.lang.**Character.UnicodeBlock**

Constant for the Unicode character block of the same name.

BEST_COMPRESSION - Static variable in class java.util.zip.**Deflater**

Compression level for best compression.

BEST_SPEED - Static variable in class java.util.zip.**Deflater**

Compression level for fastest compression.

bestRowNotPseudo - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the best row identifier is NOT a pseudo column.

bestRowPseudo - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the best row identifier is a pseudo column.

bestRowSession - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the scope of the best row identifier is the remainder of the current session.

bestRowTemporary - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the scope of the best row identifier is very temporary, lasting only while the row is being used.

bestRowTransaction - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the scope of the best row identifier is the remainder of the current transaction.

bestRowUnknown - Static variable in interface java.sql.**DatabaseMetaData**

Indicates that the best row identifier may or may not be a pseudo column.

BevelBorder - class javax.swing.border.**BevelBorder**.

A class which implements a simple 2 line bevel border.

BevelBorder(int) - Constructor for class javax.swing.border.**BevelBorder**

Creates a bevel border with the specified type and whose colors will be derived from the background color of the component passed into the paintBorder method.

BevelBorder(int, Color, Color) - Constructor for class javax.swing.border.BevelBorder

Creates a bevel border with the specified type, highlight and shadow colors.

BevelBorder(int, Color, Color, Color, Color) - Constructor for class javax.swing.border.BevelBorder

Creates a bevel border with the specified type, highlight shadow colors.

bevelType - Variable in class javax.swing.border.BevelBorder

BGColor - Static variable in class javax.swing.text.html.HTML.Attribute

BIDI_EMBEDDING - Static variable in class java.awt.font.TextAttribute

Attribute key for the embedding level for nested bidirectional runs.

BidiElementName - Static variable in class javax.swing.text.AbstractDocument

Name of elements used to hold a unidirectional run

BidiLevel - Static variable in class javax.swing.text.StyleConstants

Bidirectional level of a character as assigned by the Unicode bidi algorithm.

BidiLevel - Static variable in class javax.swing.text.StyleConstants.CharacterConstants

Bidirectional level of a character as assigned by the Unicode bidi algorithm.

BIG - Static variable in class javax.swing.text.html.HTML.Tag

BigDecimal - class java.math.BigDecimal.

Immutable, arbitrary-precision signed decimal numbers.

BigDecimal(BigInteger) - Constructor for class java.math.BigDecimal

Translates a BigInteger into a BigDecimal.

BigDecimal(BigInteger, int) - Constructor for class java.math.BigDecimal

Translates a BigInteger unscaled value and an int scale into a BigDecimal.

BigDecimal(double) - Constructor for class java.math.BigDecimal

Translates a double into a BigDecimal.

BigDecimal(String) - Constructor for class java.math.BigDecimal

Translates the String representation of a BigDecmal into a BigDecimal.

bigEndian - Variable in class javax.sound.sampled.AudioFormat

Indicates whether the audio data is stored in big-endian or little-endian order.

BIGINT - Static variable in class java.sql.Types

The constant in the Java programming language, sometimes referred to as a type code, that identifies the generic SQL type BIGINT.

BigInteger - class java.math.BigInteger.

Immutable arbitrary-precision integers.

BigInteger(byte[]) - Constructor for class java.math.BigInteger

Translates a byte array containing the two's-complement binary representation of a BigInteger into a BigInteger.

BigInteger(int, byte[]) - Constructor for class java.math.BigInteger

Translates the sign-magnitude representation of a BigInteger into a BigInteger.

BigInteger(int, int, Random) - Constructor for class java.math.BigInteger

Constructs a randomly generated positive BigInteger that is probably prime, with the specified bitLength.

BigInteger(int, Random) - Constructor for class java.math.BigInteger

Constructs a randomly generated BigInteger, uniformly distributed over the range 0 to ($2^{\text{numBits}} - 1$), inclusive.

BigInteger(String) - Constructor for class java.math.BigInteger

Translates the decimal String representation of a BigInteger into a BigInteger.

BigInteger(String, int) - Constructor for class java.math.BigInteger

Translates the String representation of a BigInteger in the specified radix into a BigInteger.

BINARY - Static variable in class java.sql.Types

The constant in the Java programming language, sometimes referred to as a type code, that identifies the generic SQL type BINARY.

BinaryRefAddr - class javax.naming.BinaryRefAddr.

This class represents the binary form of the address of a communications end-point.

BinaryRefAddr(String, byte[]) - Constructor for class javax.naming.BinaryRefAddr

Constructs a new instance of BinaryRefAddr using its address type and a byte array for contents.

BinaryRefAddr(String, byte[], int, int) - Constructor for class javax.naming.BinaryRefAddr

Constructs a new instance of BinaryRefAddr using its address type and a region of a byte array for contents.

binarySearch(byte[], byte) - Static method in class java.util.Arrays

Searches the specified array of bytes for the specified value using the binary search algorithm.

binarySearch(char[], char) - Static method in class java.util.Arrays

Searches the specified array of chars for the specified value using the binary search algorithm.

binarySearch(double[], double) - Static method in class java.util.Arrays

Searches the specified array of doubles for the specified value using the binary search algorithm.

binarySearch(float[], float) - Static method in class java.util.Arrays

Searches the specified array of floats for the specified value using the binary search algorithm.

binarySearch(int[], int) - Static method in class java.util.Arrays

Searches the specified array of ints for the specified value using the binary search algorithm.

binarySearch(List, Object) - Static method in class java.util.Collections

Searches the specified list for the specified object using the binary search algorithm.

binarySearch(List, Object, Comparator) - Static method in class java.util.Collections

Searches the specified list for the specified object using the binary search algorithm.

binarySearch(long[], long) - Static method in class java.util.Arrays

Searches the specified array of longs for the specified value using the binary search algorithm.

binarySearch(Object[], Object) - Static method in class java.util.Arrays

Searches the specified array for the specified object using the binary search algorithm.

binarySearch(Object[], Object, Comparator) - Static method in class java.util.Arrays

Searches the specified array for the specified object using the binary search algorithm.

binarySearch(short[], short) - Static method in class java.util.Arrays

Searches the specified array of shorts for the specified value using the binary search algorithm.

bind_context(NameComponent[], NamingContext) - Method in class org.omg.CosNaming.NamingContextStub

bind_context(NameComponent[], NamingContext) - Method in interface org.omg.CosNaming.NamingContextOperations

Names an object that is a naming context.

bind_new_context(NameComponent[]) - Method in class org.omg.CosNaming.NamingContextStub

bind_new_context(NameComponent[]) - Method in interface org.omg.CosNaming.NamingContextOperations

This operation creates a new context and binds it to the name supplied as an argument.

bind(InetAddress, int) - Method in class java.net.SocketImpl

Binds this socket to the specified port number on the specified host.

bind(int, InetAddress) - Method in class java.net.DatagramSocketImpl

Binds a datagram socket to a local port and address.

bind(NameComponent[], Object) - Method in class org.omg.CosNaming.NamingContextStub

bind(NameComponent[], Object) - Method in interface org.omg.CosNaming.NamingContextOperations

Creates a binding of a name and an object in the naming context.

bind(Name, Object) - Method in class javax.naming.InitialContext

bind(Name, Object) - Method in interface javax.naming.Context

Binds a name to an object.

bind(Name, Object, Attributes) - Method in interface javax.naming.directory.DirContext

Binds a name to an object, along with associated attributes.

bind(Name, Object, Attributes) - Method in class javax.naming.directory.InitialDirContext

bind(String, Object) - Method in class javax.naming.InitialContext

bind(String, Object) - Method in interface javax.naming.Context

Binds a name to an object.

bind(String, Object, Attributes) - Method in interface javax.naming.directory.DirContext

Binds a name to an object, along with associated attributes.

bind(String, Object, Attributes) - Method in class javax.naming.directory.InitialDirContext

bind(String, Remote) - Static method in class java.rmi.Naming

Binds the specified name to a remote object.

bind(String, Remote) - Method in interface java.rmi.registry.Registry

Binds the specified name to a remote object.

BindException - exception java.net.BindException.

Signals that an error occurred while attempting to bind a socket to a local address and port.

BindException() - Constructor for class java.net.BindException

Construct a new BindException with no detailed message.

BindException(String) - Constructor for class java.net.BindException

Constructs a new BindException with the specified detail message as to why the bind error occurred.

Binding - class javax.naming.Binding.

This class represents a name-to-object binding found in a context.

Binding - class org.omg.CosNaming.Binding.

binding_name - Variable in class org.omg.CosNaming.Binding

binding_type - Variable in class org.omg.CosNaming.Binding

Binding() - Constructor for class org.omg.CosNaming.Binding

Binding(NameComponent[], BindingType) - Constructor for class org.omg.CosNaming.Binding

Binding(String, Object) - Constructor for class javax.naming.Binding

Constructs an instance of a Binding given its name and object.

Binding(String, Object, boolean) - Constructor for class javax.naming.Binding

Constructs an instance of a Binding given its name, object, and whether the name is relative.

Binding(String, String, Object) - Constructor for class javax.naming.Binding

Constructs an instance of a Binding given its name, class name, and object.

Binding(String, String, Object, boolean) - Constructor for class javax.naming.Binding

Constructs an instance of a Binding given its name, class name, object, and whether the name is relative.

BindingHelper - class org.omg.CosNaming.BindingHelper.

BindingHolder - class org.omg.CosNaming.BindingHolder.

BindingHolder() - Constructor for class org.omg.CosNaming.BindingHolder

BindingHolder(Binding) - Constructor for class org.omg.CosNaming.BindingHolder

BindingIterator - interface org.omg.CosNaming.BindingIterator.

The BindingIterator interface allows a client to iterate through the bindings using the next_one or next_n operations.

BindingIteratorHelper - class org.omg.CosNaming.BindingIteratorHelper.

BindingIteratorHolder - class org.omg.CosNaming.BindingIteratorHolder.

BindingIteratorHolder() - Constructor for class org.omg.CosNaming.BindingIteratorHolder

BindingIteratorHolder(BindingIterator) - Constructor for class org.omg.CosNaming.BindingIteratorHolder

BindingIteratorOperations - interface org.omg.CosNaming.BindingIteratorOperations.

org.omg/CosNaming/BindingIteratorOperations.java Generated by the IDL-to-Java compiler (portable), version "3.0" from nameservice.idl Wednesday, January 26, 2000 3:34:52 PM PST

BindingListHelper - class org.omg.CosNaming.BindingListHelper.

BindingListHolder - class org.omg.CosNaming.BindingListHolder.

BindingListHolder() - Constructor for class org.omg.CosNaming.BindingListHolder

BindingListHolder(Binding[]) - Constructor for class org.omg.CosNaming.BindingListHolder

BindingType - class org.omg.CosNaming.BindingType.

BindingTypeHelper - class org.omg.CosNaming.BindingTypeHelper.

BindingTypeHolder - class org.omg.CosNaming.BindingTypeHolder.

BindingTypeHolder() - Constructor for class org.omg.CosNaming.BindingTypeHolder

BindingTypeHolder(BindingType) - Constructor for class org.omg.CosNaming.BindingTypeHolder

BIT - Static variable in class java.sql.Types

The constant in the Java programming language, sometimes referred to as a type code, that identifies the generic SQL type BIT.

bitCount() - Method in class java.math.BigInteger

Returns the number of bits in the two's complement representation of this BigInteger that differ from its sign bit.

bitLength() - Method in class java.math.BigInteger

Returns the number of bits in the minimal two's-complement representation of this BigInteger, *excluding* a sign bit.

BITMASK - Static variable in interface java.awt.Transparency

Represents image data that is guaranteed to be either completely opaque, with an alpha value of 1.0, or completely transparent, with an alpha value of 0.0.

BitSet - class java.util.BitSet

This class implements a vector of bits that grows as needed.

BitSet() - Constructor for class java.util.BitSet

Creates a new bit set.

BitSet(int) - Constructor for class java.util.BitSet

Creates a bit set whose initial size is large enough to explicitly represent bits with indices in the range 0 through `nbits-1`.

black - Static variable in class java.awt.Color

The color black.

BLIT_SCROLL_MODE - Static variable in class javax.swing.JViewport

Use `graphics.copyArea()` to implement scrolling.

Blob - interface java.sql.Blob

The representation (mapping) in the Java™ programming language of an SQL BLOB value.

BLOB - Static variable in class java.sql.Types

The constant in the Java programming language, sometimes referred to as a type code, that identifies the generic SQL type BLOB.

BLOCK_DECREMENT - Static variable in class java.awt.event.AdjustmentEvent

The block decrement adjustment type.

BLOCK_ELEMENTS - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

BLOCK_INCREMENT - Static variable in class java.awt.event.AdjustmentEvent

The block increment adjustment type.

blockClose(HTML.Tag) - Method in class javax.swing.text.html.HTMLDocument.HTMLReader

Adds an instruction to the parse buffer to close out a block element of the given type.

blockIncrement - Variable in class javax.swing.JScrollBar

blockOpen(HTML.Tag, MutableAttributeSet) - Method in class javax.swing.text.html.HTMLDocument.HTMLReader

Adds an instruction to the parse buffer to create a block element with the given attributes.

BLOCKQUOTE - Static variable in class javax.swing.text.html.HTML.Tag

BlockView - class javax.swing.text.html.BlockView

A view implementation to display a block (as a box) with CSS specifications.

BlockView(Element, int) - Constructor for class javax.swing.text.html.BlockView

Creates a new view that represents an html box.

blue - Static variable in class java.awt.Color

The color blue.

BLUECOMPONENT - Static variable in class java.awt.color.ICC_ProfileRGB

To request a gamma value or TRC for the blue component.

body - Variable in class javax.swing.text.html.parser.DTD

BODY - Static variable in class javax.swing.text.html.HTML.Tag

Bold - Static variable in class javax.swing.text.StyleConstants

Name of the bold attribute.

Bold - Static variable in class javax.swing.text.StyleConstants.CharacterConstants

Name of the bold attribute.

Bold - Static variable in class javax.swing.text.StyleConstants.FontConstants

Name of the bold attribute.

BOLD - Static variable in class java.awt.Font

The bold style constant.

BOLD ACTION - Static variable in class javax.swing.text.html.HTMLEditorKit

The bold action identifier

Book - class java.awt.print.Book.

The Book class provides a representation of a document in which pages may have different page formats and page painters.

Book() - Constructor for class java.awt.print.Book

Creates a new, empty Book.

Boolean - class java.lang.Boolean.

The Boolean class wraps a value of the primitive type boolean in an object.

Boolean(boolean) - Constructor for class java.lang.Boolean

Allocates a Boolean object representing the value argument.

Boolean(String) - Constructor for class java.lang.Boolean

Allocates a Boolean object representing the value true if the string argument is not null and is equal, ignoring case, to the string "true".

BooleanControl - class javax.sound.sampled.BooleanControl.

A BooleanControl provides the ability to switch between two possible settings that affect a line's audio.

BooleanControl.Type - class javax.sound.sampled.BooleanControl.Type.

An instance of the BooleanControl.Type class identifies one kind of boolean control.

BooleanControl.Type(String) - Constructor for class javax.sound.sampled.BooleanControl.Type

Constructs a new boolean control type.

BooleanControl(BooleanControl.Type, boolean) - Constructor for class javax.sound.sampled.BooleanControl

Constructs a new boolean control object with the given parameters.

BooleanControl(BooleanControl.Type, boolean, String, String) - Constructor for class javax.sound.sampled.BooleanControl

Constructs a new boolean control object with the given parameters.

BooleanHolder - class org.omg.CORBA.BooleanHolder.

A Holder class for a boolean that is used to store "out" and "inout" parameters in IDL methods.

BooleanHolder() - Constructor for class org.omg.CORBA.BooleanHolder

Constructs a new BooleanHolder object with its value field initialized to false.

BooleanHolder(boolean) - Constructor for class org.omg.CORBA.BooleanHolder

Constructs a new BooleanHolder object with its value field initialized with the given boolean.

BooleanSeqHelper - class org.omg.CORBA.BooleanSeqHelper.

org.omg.CORBA.BooleanSeqHelper.java Generated by the IDL-to-Java compiler (portable), version "3.0" from streams.idl 13 May 1999 22:41:36 o'clock GMT+00:00

BooleanSeqHelper() - Constructor for class org.omg.CORBA.BooleanSeqHelper

BooleanSeqHolder - class org.omg.CORBA.BooleanSeqHolder.

org.omg.CORBA.BooleanSeqHolder.java Generated by the IDL-to-Java compiler (portable), version "3.0" from streams.idl 13 May 1999 22:41:36 o'clock GMT+00:00

BooleanSeqHolder() - Constructor for class org.omg.CORBA.BooleanSeqHolder

BooleanSeqHolder(boolean[]) - Constructor for class org.omg.CORBA.BooleanSeqHolder

booleanValue() - Method in class java.lang.Boolean

Returns the value of this Boolean object as a boolean primitive.

BOPOMOFO - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

border - Variable in class javax.swing.border.TitledBorder

border - Variable in class javax.swing.tree.DefaultTreeCellEditor.DefaultTextField

Border to use.

Border - interface javax.swing.border.Border.

Interface describing an object capable of rendering a border around the edges of a swing component.

BORDER - Static variable in class javax.swing.text.html.HTML.Attribute

BORDER - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_BOTTOM - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_BOTTOM_WIDTH - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_COLOR - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_LEFT - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_LEFT_WIDTH - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_PAINTED_CHANGED_PROPERTY - Static variable in class javax.swing.AbstractButton

Identifies a change to having the border drawn, or having it not drawn.

BORDER_PAINTED_FLAT_CHANGED_PROPERTY - Static variable in class javax.swing.JCheckBox

Identifies a change to the flat property.

BORDER_RIGHT - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_RIGHT_WIDTH - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_STYLE - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_TOP - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_TOP_WIDTH - Static variable in class javax.swing.text.html.CSS.Attribute

BORDER_WIDTH - Static variable in class javax.swing.text.html.CSS.Attribute

BorderFactory - class javax.swing.BorderFactory.

Factory class for vending standard Border objects.

borderInsets - Static variable in class javax.swing.plaf.metal.MetalBorders.ButtonBorder

borderInsets - Static variable in class javax.swing.plaf.metal.MetalBorders.MenuBarBorder

borderInsets - Static variable in class javax.swing.plaf.metal.MetalBorders.MenuItemBorder

borderInsets - Static variable in class javax.swing.plaf.metal.MetalBorders.PopupMenuBorder

BorderLayout - class java.awt.BorderLayout.

A border layout lays out a container, arranging and resizing its components to fit in five regions: north, south, east, west, and center.

BorderLayout() - Constructor for class java.awt.BorderLayout

Constructs a new border layout with no gaps between components.

BorderLayout(int, int) - Constructor for class java.awt.BorderLayout

Constructs a border layout with the specified gaps between components.

borderListener - Variable in class javax.swing.plaf.basic.BasicInternalFrameUI

borderSelectionColor - Variable in class javax.swing.tree.DefaultTreeCellRenderer

Color to use for the background when the node isn't selected.

borderSelectionColor - Variable in class javax.swing.tree.DefaultTreeCellEditor

True if the border selection color should be drawn.

BorderUIResource - class javax.swing.plaf.BorderUIResource.

BorderUIResource.BevelBorderUIResource - class

javax.swing.plaf.BorderUIResource.BevelBorderUIResource.

BorderUIResource.BevelBorderUIResource(int) - Constructor for class

javax.swing.plaf.BorderUIResource.BevelBorderUIResource

BorderUIResource.BevelBorderUIResource(int, Color, Color) - Constructor for class

javax.swing.plaf.BorderUIResource.BevelBorderUIResource

BorderUIResource.BevelBorderUIResource(int, Color, Color, Color, Color) - Constructor for class

javax.swing.plaf.BorderUIResource.BevelBorderUIResource

BorderUIResource.CompoundBorderUIResource - class

javax.swing.plaf.BorderUIResource.CompoundBorderUIResource.

BorderUIResource.CompoundBorderUIResource(Border, Border) - Constructor for class

javax.swing.plaf.BorderUIResource.CompoundBorderUIResource

BorderUIResource.EmptyBorderUIResource - class
javax.swing.plaf.BorderUIResource.EmptyBorderUIResource.

BorderUIResource.EmptyBorderUIResource(Insets) - Constructor for class
javax.swing.plaf.BorderUIResource.EmptyBorderUIResource

BorderUIResource.EmptyBorderUIResource(int, int, int, int) - Constructor for class
javax.swing.plaf.BorderUIResource.EmptyBorderUIResource

BorderUIResource.EtchedBorderUIResource - class
javax.swing.plaf.BorderUIResource.EtchedBorderUIResource.

BorderUIResource.EtchedBorderUIResource() - Constructor for class
javax.swing.plaf.BorderUIResource.EtchedBorderUIResource

BorderUIResource.EtchedBorderUIResource(Color, Color) - Constructor for class
javax.swing.plaf.BorderUIResource.EtchedBorderUIResource

BorderUIResource.EtchedBorderUIResource(int) - Constructor for class
javax.swing.plaf.BorderUIResource.EtchedBorderUIResource

BorderUIResource.EtchedBorderUIResource(int, Color, Color) - Constructor for class
javax.swing.plaf.BorderUIResource.EtchedBorderUIResource

BorderUIResource.LineBorderUIResource - class javax.swing.plaf.BorderUIResource.LineBorderUIResource.

BorderUIResource.LineBorderUIResource(Color) - Constructor for class
javax.swing.plaf.BorderUIResource.LineBorderUIResource

BorderUIResource.LineBorderUIResource(Color, int) - Constructor for class
javax.swing.plaf.BorderUIResource.LineBorderUIResource

BorderUIResource.MatteBorderUIResource - class
javax.swing.plaf.BorderUIResource.MatteBorderUIResource.

BorderUIResource.MatteBorderUIResource(Icon) - Constructor for class
javax.swing.plaf.BorderUIResource.MatteBorderUIResource

BorderUIResource.MatteBorderUIResource(int, int, int, int, Color) - Constructor for class
javax.swing.plaf.BorderUIResource.MatteBorderUIResource

BorderUIResource.MatteBorderUIResource(int, int, int, int, Icon) - Constructor for class
javax.swing.plaf.BorderUIResource.MatteBorderUIResource

BorderUIResource.TitledBorderUIResource - class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource.

BorderUIResource.TitledBorderUIResource(Border) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource.TitledBorderUIResource(Border, String) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource.TitledBorderUIResource(Border, String, int, int) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource.TitledBorderUIResource(Border, String, int, int, Font) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource.TitledBorderUIResource(Border, String, int, int, Font, Color) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource.TitledBorderUIResource(String) - Constructor for class
javax.swing.plaf.BorderUIResource.TitledBorderUIResource

BorderUIResource(Border) - Constructor for class javax.swing.plaf.BorderUIResource
Creates a UIResource border object which wraps an existing Border instance.

BOTH - Static variable in class java.awt.GridBagConstraints
Resize the component both horizontally and vertically.

bottom - Variable in class java.awt.Insets
The inset from the bottom.

bottom - Variable in class javax.swing.border.EmptyBorder

BOTTOM - Static variable in interface javax.swing.SwingConstants
Box-orientation constant used to specify the bottom of a box.

BOTTOM - Static variable in class javax.swing.JSplitPane
Used to add a Component below the other Component.

BOTTOM - Static variable in class javax.swing.border.TitledBorder
Position the title in the middle of the border's bottom line.

BOTTOM_ALIGNMENT - Static variable in class java.awt.Component
Ease-of-use constant for getAlignmentY.

BOTTOM_ALIGNMENT - Static variable in class java.awt.font.GraphicAttribute
Aligns bottom of graphic to bottom of line.

BoundedRangeModel - interface javax.swing.BoundedRangeModel.
Defines the data model used by components like Sliders and ProgressBars.

bounds - Variable in class java.awt.Polygon
Bounds of the polygon.

Bounds - exception org.omg.CORBA.Bounds.

A user exception thrown when a parameter is not within the legal bounds for the object that a method is trying to access.

Bounds - exception org.omg.CORBA.TypeCodePackage.Bounds.
Provides the TypeCode operations member_name(), member_type(), and member_label.

bounds() - Method in class java.awt.Component
Deprecated. *As of JDK version 1.1, replaced by getBounds().*

Bounds() - Constructor for class org.omg.CORBA.Bounds

Constructs an Bounds with no specified detail message.

Bounds() - Constructor for class org.omg.CORBA.TypeCodePackage.Bounds

Constructs a Bounds exception with no reason message.

Bounds(String) - Constructor for class org.omg.CORBA.Bounds

Constructs an Bounds with the specified detail message.

Bounds(String) - Constructor for class org.omg.CORBA.TypeCodePackage.Bounds

Constructs a Bounds exception with the specified reason message.

Box - class javax.swing.Box.

A lightweight container that uses a BoxLayout object as its layout manager.

BOX_DRAWING - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

Box.AccessibleBox - class javax.swing.Box.AccessibleBox.

This class implements accessibility support for the Box class.

Box.AccessibleBox(Box) - Constructor for class javax.swing.Box.AccessibleBox

Box.Filler - class javax.swing.Box.Filler.

An implementation of a lightweight component that participates in layout but has no view.

Box.Filler.AccessibleBoxFiller - class javax.swing.Box.Filler.AccessibleBoxFiller.

This class implements accessibility support for the Box.Filler class.

Box.Filler.AccessibleBoxFiller(Box.Filler) - Constructor for class javax.swing.Box.Filler.AccessibleBoxFiller

Box.Filler(Dimension, Dimension, Dimension) - Constructor for class javax.swing.Box.Filler

Constructor to create shape with the given size ranges.

Box(int) - Constructor for class javax.swing.Box

Creates a Box that displays its components along the the specified axis.

BoxedValueHelper - interface org.omg.CORBA.portable.BoxedValueHelper.

BoxLayout - class javax.swing.BoxLayout.

A layout manager that allows multiple components to be layed out either vertically or horizontally.

BoxLayout(Container, int) - Constructor for class javax.swing.BoxLayout

Creates a layout manager that will lay out components either left to right or top to bottom, as specified in the axis parameter.

BoxView - class javax.swing.text.BoxView.

A view that arranges its children into a box shape by tiling it's children along an axis.

BoxView(Element, int) - Constructor for class javax.swing.text.BoxView

Constructs a BoxView.

BR - Static variable in class javax.swing.text.html.HTML.Tag

breadthFirstEnumeration() - Method in class javax.swing.tree.DefaultMutableTreeNode

Creates and returns an enumeration that traverses the subtree rooted at this node in breadth-first order.

BreakIterator - class java.text.BreakIterator.

The BreakIterator class implements methods for finding the location of boundaries in text.

BreakIterator() - Constructor for class java.text.BreakIterator

Constructor.

breaksFlow() - Method in class javax.swing.text.html.HTML.Tag

If the tag causes a line break, to the flow of data, then this method will return true.

breaksFlow() - Method in class javax.swing.text.html.parser.TagElement

breakView(int, float, Shape) - Method in class javax.swing.text.ParagraphView

Breaks this view on the given axis at the given length.

breakView(int, int, float, float) - Method in class javax.swing.text.View

Tries to break this view on the given axis.

breakView(int, int, float, float) - Method in class javax.swing.text.GlyphView

Breaks this view on the given axis at the given length.

BRIEF - Static variable in class java.rmi.server.LogStream

Deprecated. log level constant (brief logging).

brighter() - Method in class java.awt.Color

Creates a new Color that is a brighter version of this Color.

buf - Variable in class java.io.PushbackInputStream

The pushback buffer.

buf - Variable in class java.io.BufferedInputStream

The internal buffer array where the data is stored.

buf - Variable in class java.io.BufferedOutputStream

The internal buffer where data is stored.

buf - Variable in class java.io.ByteArrayInputStream

An array of bytes that was provided by the creator of the stream.

buf - Variable in class java.io.CharArrayReader

The character buffer.

buf - Variable in class java.io.CharArrayWriter

The buffer where data is stored.

buf - Variable in class java.io.ByteArrayOutputStream

The buffer where data is stored.

buf - Variable in class java.util.zip.InflaterInputStream

Input buffer for decompression.

buf - Variable in class java.util.zip.DeflaterOutputStream

Output buffer for writing compressed data.

buffer - Variable in class java.io.PipedInputStream

The circular buffer into which incoming data is placed.

buffer - Variable in class java.io.StringBufferInputStream

Deprecated. The string from which bytes are read.

buffer - Variable in class javax.swing.text.DefaultStyledDocument

BUFFER_SIZE_DEFAULT - Static variable in class javax.swing.text.DefaultStyledDocument

The default size of the initial content buffer.

BUFFERED_OPTION - Static variable in class javax.swing.DebugGraphics

Show buffered operations in a separate Frame.

BufferedImage - class java.awt.image.BufferedImage.

The BufferedImage subclass describes an Image with an accessible buffer of image data.

BufferedImage(ColorModel, WritableRaster, boolean, Hashtable) - Constructor for class java.awt.image.BufferedImage

Constructs a new BufferedImage with a specified ColorModel and Raster.

BufferedImage(int, int, int) - Constructor for class java.awt.image.BufferedImage

Constructs a BufferedImage of one of the predefined image types.

BufferedImage(int, int, int, IndexColorModel) - Constructor for class java.awt.image.BufferedImage
Constructs a BufferedImage of one of the predefined image types: TYPE_BYTE_BINARY or TYPE_BYTE_INDEXED

BufferedImageFilter - class java.awt.image.BufferedImageFilter.

The BufferedImageFilter class subclasses an ImageFilter to provide a simple means of using a single-source/single-destination image operator (BufferedImageOp) to filter a BufferedImage in the Image Producer/Consumer/Observer paradigm.

BufferedImageFilter(BufferedImageOp) - Constructor for class java.awt.image.BufferedImageFilter

Constructs a BufferedImageFilter with the specified single-source/single-destination operator.

BufferedImageOp - interface java.awt.image.BufferedImageOp.

This interface describes single-input/single-output operations performed on BufferedImage objects.

BufferedInputStream - class java.io.BufferedInputStream.

A BufferedInputStream adds functionality to another input stream-namely, the ability to buffer the input and to support the mark and reset methods.

BufferedInputStream(InputStream) - Constructor for class java.io.BufferedInputStream

Creates a BufferedInputStream and saves its argument, the input stream *in*, for later use.

BufferedInputStream(InputStream, int) - Constructor for class java.io.BufferedInputStream

Creates a BufferedInputStream with the specified buffer size, and saves its argument, the input stream *in*, for later use.

BufferedOutputStream - class java.io.BufferedOutputStream.

The class implements a buffered output stream.

BufferedOutputStream(OutputStream) - Constructor for class java.io.BufferedOutputStream

Creates a new buffered output stream to write data to the specified underlying output stream with a default 512-byte buffer size.

BufferedOutputStream(OutputStream, int) - Constructor for class java.io.BufferedOutputStream

Creates a new buffered output stream to write data to the specified underlying output stream with the specified buffer size.

BufferedReader - class java.io.BufferedReader.

Read text from a character-input stream, buffering characters so as to provide for the efficient reading of characters, arrays, and lines.

BufferedReader(Reader) - Constructor for class java.io.BufferedReader

Create a buffering character-input stream that uses a default-sized input buffer.

BufferedReader(Reader, int) - Constructor for class java.io.BufferedReader

Create a buffering character-input stream that uses an input buffer of the specified size.

BufferedWriter - class java.io.BufferedWriter.

Write text to a character-output stream, buffering characters so as to provide for the efficient writing of single characters, arrays, and strings.

BufferedWriter(Writer) - Constructor for class java.io.BufferedWriter

Create a buffered character-output stream that uses a default-sized output buffer.

BufferedWriter(Writer, int) - Constructor for class java.io.BufferedWriter

Create a new buffered character-output stream that uses an output buffer of the given size.

buildChooser() - Method in class javax.swing.colorchooser.AbstractColorChooserPanel

Builds a new chooser panel.

bumps - Variable in class javax.swing.plaf.metal.MetalScrollBarUI

bumps - Variable in class javax.swing.plaf.metal.MetalBorders.ToolBarBorder

burstStringInto(Container, String, int) - Method in class javax.swing.plaf.basic.BasicOptionPaneUI

Recursively creates new JLabel instances to represent d.

BUSY - Static variable in class javax.accessibility.AccessibleState

Indicates the current object is busy.

Button - class java.awt.Button.

This class creates a labeled button.

Button.AccessibleAWTButton - class java.awt.Button.AccessibleAWTButton.

This class implements accessibility support for the Button class.

Button.AccessibleAWTButton(Button) - Constructor for class java.awt.Button.AccessibleAWTButton

Button() - Constructor for class java.awt.Button

Constructs a Button with no label.

Button(String) - Constructor for class java.awt.Button

Constructs a Button with the specified label.

BUTTON1_MASK - Static variable in class java.awt.event.InputEvent

The mouse button1 modifier constant.

BUTTON2_MASK - Static variable in class java.awt.event.InputEvent

The mouse button2 modifier constant.

BUTTON3_MASK - Static variable in class java.awt.event.InputEvent

The mouse button3 modifier constant.

ButtonGroup - class javax.swing.ButtonGroup.

This class is used to create a multiple-exclusion scope for a set of buttons.

ButtonGroup() - Constructor for class javax.swing.ButtonGroup

Creates a new ButtonGroup.

buttonIndex - Variable in class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonActionListener

buttonListener - Variable in class javax.swing.plaf.basic.BasicScrollBarUI

ButtonModel - interface javax.swing.ButtonModel.

State Model for buttons.

buttons - Variable in class javax.swing.ButtonGroup

ButtonUI - class javax.swing.plaf.ButtonUI.

Pluggable look and feel interface for JButton.

ButtonUI() - Constructor for class javax.swing.plaf.ButtonUI

Byte - class java.lang.Byte.

The Byte class is the standard wrapper for byte values.

Byte(byte) - Constructor for class java.lang.Byte

Constructs a Byte object initialized to the specified byte value.

Byte(String) - Constructor for class java.lang.Byte

Constructs a Byte object initialized to the value specified by the String parameter.

ByteArrayInputStream - class java.io.ByteArrayInputStream.

A ByteArrayInputStream contains an internal buffer that contains bytes that may be read from the stream.

ByteArrayInputStream(byte[]) - Constructor for class java.io.ByteArrayInputStream

Creates a ByteArrayInputStream so that it uses buf as its buffer array.

Java™ 2 Platform, Standard Edition, v 1.3.1

API Specification

This document is the API specification for the Java 2 Platform, Standard Edition, version 1.3.1.

See:

[Description](#)

Java 2 Platform Packages	
java.applet	Provides the classes necessary to create an applet and the classes an applet uses to communicate with its applet context.
java.awt	Contains all of the classes for creating user interfaces and for painting graphics and images.
java.awt.color	Provides classes for color spaces.
java.awt.datatransfer	Provides interfaces and classes for transferring data between and within applications.
java.awt.dnd	Drag and Drop is a direct manipulation gesture found in many Graphical User Interface systems that provides a mechanism to transfer information between two entities logically associated with presentation elements in the GUI.
java.awt.event	Provides interfaces and classes for dealing with different types of events fired by AWT components.
java.awt.font	Provides classes and interface relating to fonts.
java.awt.geom	Provides the Java 2D classes for defining and performing operations on objects related to two-dimensional geometry.
java.awt.im	Provides classes and interfaces for the input method framework.
java.awt.im.spi	Provides interfaces that enable the development of input methods that can be used with any Java runtime environment.
java.awt.image	Provides classes for creating and modifying images.
java.awt.image.renderable	Provides classes and interfaces for producing rendering-independent images.
java.awt.print	Provides classes and interfaces for a general printing API.
java.beans	Contains classes related to Java Beans development.

<u>java.beans.beancontext</u>	Provides classes and interfaces relating to bean context.
<u>java.io</u>	Provides for system input and output through data streams, serialization and the file system.
<u>java.lang</u>	Provides classes that are fundamental to the design of the Java programming language.
<u>java.lang.ref</u>	Provides reference-object classes, which support a limited degree of interaction with the garbage collector.
<u>java.lang.reflect</u>	Provides classes and interfaces for obtaining reflective information about classes and objects.
<u>java.math</u>	Provides classes for performing arbitrary-precision integer arithmetic (BigInteger) and arbitrary-precision decimal arithmetic (BigDecimal).
<u>java.net</u>	Provides the classes for implementing networking applications.
<u>java.rmi</u>	Provides the RMI package.
<u>java.rmi.activation</u>	Provides support for RMI Object Activation.
<u>java.rmi.dgc</u>	Provides classes and interface for RMI distributed garbage-collection (DGC).
<u>java.rmi.registry</u>	Provides a class and two interfaces for the RMI registry.
<u>java.rmi.server</u>	Provides classes and interfaces for supporting the server side of RMI.
<u>java.security</u>	Provides the classes and interfaces for the security framework.
<u>java.security.acl</u>	The classes and interfaces in this package have been superseded by classes in the java.security package.
<u>java.security.cert</u>	Provides classes and interfaces for parsing and managing certificates.
<u>java.security.interfaces</u>	Provides interfaces for generating RSA (Rivest, Shamir and Adleman AsymmetricCipher algorithm) keys as defined in the RSA Laboratory Technical Note PKCS#1, and DSA (Digital Signature Algorithm) keys as defined in NIST's FIPS-186.
<u>java.security.spec</u>	Provides classes and interfaces for key specifications and algorithm parameter specifications.
<u>java.sql</u>	Provides the API for accessing and processing data in a data source using the Java™ programming language.
<u>java.text</u>	Provides classes and interfaces for handling text, dates, numbers, and messages in a manner independent of natural languages.

<u>java.util</u>	Contains the collections framework, legacy collection classes, event model, date and time facilities, internationalization, and miscellaneous utility classes (a string tokenizer, a random-number generator, and a bit array).
<u>java.util.jar</u>	Provides classes for reading and writing the JAR (Java ARchive) file format, which is based on the standard ZIP file format with an optional manifest file.
<u>java.util.zip</u>	Provides classes for reading and writing the standard ZIP and GZIP file formats.
<u>javax.accessibility</u>	Defines a contract between user-interface components and an assistive technology that provides access to those components.
<u>javax.naming</u>	Provides the classes and interfaces for accessing naming services.
<u>javax.naming.directory</u>	Extends the <code>javax.naming</code> package to provide functionality for accessing directory services.
<u>javax.naming.event</u>	Provides support for event notification when accessing naming and directory services.
<u>javax.naming.ldap</u>	Provides support for LDAPv3 extended operations and controls.
<u>javax.naming.spi</u>	Provides the means for dynamically plugging in support for accessing naming and directory services through the <code>javax.naming</code> and related packages.
<u>javax.rmi</u>	Contains user APIs for RMI-IIOP.
<u>javax.rmi.CORBA</u>	Contains portability APIs for RMI-IIOP.
<u>javax.sound.midi</u>	Provides interfaces and classes for I/O, sequencing, and synthesis of MIDI (Musical Instrument Digital Interface) data.
<u>javax.sound.midi.spi</u>	Supplies interfaces for service providers to implement when offering new MIDI devices, MIDI file readers and writers, or sound bank readers.
<u>javax.sound.sampled</u>	Provides interfaces and classes for capture, processing, and playback of sampled audio data.
<u>javax.sound.sampled.spi</u>	Supplies abstract classes for service providers to subclass when offering new audio devices, sound file readers and writers, or audio format converters.
<u>javax.swing</u>	Provides a set of "lightweight" (all-Java language) components that, to the maximum degree possible, work the same on all platforms.
	Provides classes and interface for drawing specialized borders

<u>javax.swing.border</u>	around a Swing component.
<u>javax.swing.colorchooser</u>	Contains classes and interfaces used by the JColorChooser component.
<u>javax.swing.event</u>	Provides for events fired by Swing components.
<u>javax.swing.filechooser</u>	Contains classes and interfaces used by the JFileChooser component.
<u>javax.swing.plaf</u>	Provides one interface and many abstract classes that Swing uses to provide its pluggable look-and-feel capabilities.
<u>javax.swing.plaf.basic</u>	Provides user interface objects built according to the Basic look-and-feel.
<u>javax.swing.plaf.metal</u>	Provides user interface objects built according to the "metal" look-and-feel.
<u>javax.swing.plaf.multi</u>	The multiplexing look and feel allows users to combine auxiliary look and feels with the default look and feel.
<u>javax.swing.table</u>	Provides classes and interfaces for dealing with javax.swing.JTable.
<u>javax.swing.text</u>	Provides classes and interfaces that deal with editable and noneditable text components.
<u>javax.swing.text.html</u>	Provides the class HTMLEditorKit and supporting classes for creating HTML text editors.
<u>javax.swing.text.html.parser</u>	Provides the default HTML parser, along with support classes.
<u>javax.swing.text.rtf</u>	Provides a class (RTFEditorKit) for creating Rich-Text-Format text editors.
<u>javax.swing.tree</u>	Provides classes and interfaces for dealing with javax.swing.JTree.
<u>javax.swing.undo</u>	Provides support for undo/redo capabilities in an application such as a text editor.
<u>javax.transaction</u>	Contains three exceptions thrown by the ORB machinery during unmarshalling.
<u>org.omg.CORBA</u>	Provides the mapping of the OMG CORBA APIs to the Java™ programming language, including the class ORB, which is implemented so that a programmer can use it as a fully-functional Object Request Broker (ORB).
<u>org.omg.CORBA_2_3</u>	The CORBA_2_3 package defines additions to existing CORBA interfaces in the Java 2 Standard Edition. These changes occurred in recent revisions to the CORBA API defined by the OMG. The new methods were added to interfaces derived from the corresponding interfaces in the

	CORBA package. This provides backward compatibility and avoids breaking the JCK tests.
<u>org.omg.CORBA_2_3.portable</u>	Provides methods for the input and output of value types, and contains other updates to the <code>org.omg.CORBA.portable</code> package.
<u>org.omg.CORBA.DynAnyPackage</u>	Provides the exceptions used with the <code>DynAny</code> interface (<code>InvalidValue</code> , <code>Invalid</code> , <code>InvalidSeq</code> , and <code>TypeMismatch</code>).
<u>org.omg.CORBA.ORBPackage</u>	Provides the exception <code>InvalidName</code> , which is thrown by the method <code>ORB.resolve_initial_references</code> and the exception <code>InconsistentTypeCode</code> , which is thrown by the <code>Dynamic Any</code> creation methods in the <code>ORB</code> class.
<u>org.omg.CORBA.portable</u>	Provides a portability layer, that is, a set of ORB APIs that makes it possible for code generated by one vendor to run on another vendor's ORB.
<u>org.omg.CORBA.TypeCodePackage</u>	Provides the user-defined exceptions <code>BadKind</code> and <code>Bounds</code> , which are thrown by methods in the class <code>TypeCode</code> .
<u>org.omg.CosNaming</u>	Provides the naming service for Java IDL.
<u>org.omg.CosNaming.NamingContextPackage</u>	Provides the exceptions used in the package <code>org.omg.CosNaming</code> (<code>AlreadyBound</code> , <code>CannotProceed</code> , <code>InvalidName</code> , <code>NotEmpty</code> , and <code>NotFound</code>) and also the <code>Helper</code> and <code>Holder</code> classes for those exceptions.
<u>org.omg.SendingContext</u>	Provides support for the marshalling of value types.
<u>org.omg.stub.java.rmi</u>	Contains RMI-IIOP Stubs for the Remote types that occur in the <code>java.rmi</code> package.

This document is the API specification for the Java 2 Platform, Standard Edition, version 1.3.1.

Overview Package Class Use Tree Deprecated Index Help

*Java™ 2 Platform
Std. Ed. v1.3.1*

[PREV](#) [NEXT](#)

[FRAMES](#) [NO FRAMES](#)

[Submit a bug or feature](#)

For further API reference and developer documentation, see [Java 2 SDK SE Developer Documentation](#). That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Java, Java 2D, and JDBC are trademarks or registered trademarks of Sun Microsystems, Inc. in the US and other countries.
Copyright 1993-2001 Sun Microsystems, Inc. 901 San Antonio Road
Palo Alto, California, 94303, U.S.A. All Rights Reserved.

B

[b](#) - Variable in class [java.awt.AWTEventMulticaster](#)

[B](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
The MediaType instance for Engineering B, 11 x 17 in.

[B](#) - Static variable in class [javax.swing.text.html.HTML.Tag](#)

[B0](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B0.

[B1](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B1.

[B10](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B10.

[B2](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B2.

[B3](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B3.

[B4](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B4.

[B5](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B5.

[B6](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B6.

[B7](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B7.

[B8](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B8.

[B9](#) - Static variable in class [java.awt.PageAttributes.MediaType](#)
An alias for ISO_B9.

[BACK_SPACE](#) - Static variable in class [java.awt.Event](#)
The BackSpace key.

[Background](#) - Static variable in class [javax.swing.text.StyleConstants](#)
Name of the background color attribute.

[Background](#) - Static variable in class [javax.swing.text.StyleConstants.CharacterConstants](#)
Name of the background color attribute.

[Background](#) - Static variable in class [javax.swing.text.StyleConstants.ColorConstants](#)
Name of the background color attribute.

[BACKGROUND](#) - Static variable in class [java.awt.font.TextAttribute](#)
Attribute key for the background Paint adornment.

[BACKGROUND](#) - Static variable in class [javax.swing.text.html.HTML.Attribute](#)

BACKGROUND - Static variable in class javax.swing.text.html.CSS.Attribute

BACKGROUND_ATTACHMENT - Static variable in class javax.swing.text.html.CSS.Attribute

BACKGROUND_COLOR - Static variable in class javax.swing.text.html.CSS.Attribute

BACKGROUND_IMAGE - Static variable in class javax.swing.text.html.CSS.Attribute

BACKGROUND_POSITION - Static variable in class javax.swing.text.html.CSS.Attribute

BACKGROUND_REPEAT - Static variable in class javax.swing.text.html.CSS.Attribute

backgroundNonSelectionColor - Variable in class javax.swing.tree.DefaultTreeCellRenderer

Color to use for the background when the node isn't selected.

backgroundSelectionColor - Variable in class javax.swing.tree.DefaultTreeCellRenderer

Color to use for the background when a node is selected.

backingStore - Variable in class javax.swing.JViewport

Deprecated. *As of Java 2 platform v1.3*

BACKINGSTORE_SCROLL_MODE - Static variable in class javax.swing.JViewport

Draws viewport contents into an offscreen image.

backingStoreImage - Variable in class javax.swing.JViewport

The view image used for a backing store.

Backward - Static variable in class javax.swing.text.Position.Bias

Indicates a bias toward the previous character in the model.

backwardAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the Action for moving the caret logically backward one position.

BAD_CONTEXT - exception org.omg.CORBA.BAD_CONTEXT.

The CORBA BAD_CONTEXT exception, which is thrown when there is an error processing a context object.

BAD_CONTEXT() - Constructor for class org.omg.CORBA.BAD_CONTEXT

Constructs a BAD_CONTEXT exception with a default minor code of 0 and a completion state of COMPLETED_NO.

BAD_CONTEXT(int, CompletionStatus) - Constructor for class org.omg.CORBA.BAD_CONTEXT

Constructs a BAD_CONTEXT exception with the specified minor code and completion status.

BAD_CONTEXT(String) - Constructor for class org.omg.CORBA.BAD_CONTEXT

Constructs a BAD_CONTEXT exception with the specified detail message, a minor code of 0 and a completion state of COMPLETED_NO.

BAD_CONTEXT(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.BAD_CONTEXT

Constructs a BAD_CONTEXT exception with the specified detail message, minor code, and completion status.

BAD_INV_ORDER - exception org.omg.CORBA.BAD_INV_ORDER.

The CORBA BAD_INV_ORDER exception, which is thrown when methods are called out of order.

BAD_INV_ORDER() - Constructor for class org.omg.CORBA.BAD_INV_ORDER

Constructs a BAD_INV_ORDER exception with a default minor code of 0 and a completion state of COMPLETED_NO.

BAD_INV_ORDER(int, CompletionStatus) - Constructor for class org.omg.CORBA.BAD_INV_ORDER

Constructs a `BAD_INV_ORDER` exception `BAD_INV_ORDER` with the specified minor code and completion status.

BAD_INV_ORDER(String) - Constructor for class `org.omg.CORBA.BAD_INV_ORDER`

Constructs a `BAD_INV_ORDER` exception with the specified detail message, a minor code of 0, and a completion state of `COMPLETED_NO`.

BAD_INV_ORDER(String, int, CompletionStatus) - Constructor for class `org.omg.CORBA.BAD_INV_ORDER`

Constructs a `BAD_INV_ORDER` exception with the specified detail message, minor code, and completion status.

BAD_LOCATION - Static variable in class `javax.swing.text.AbstractDocument`

Error message to indicate a bad location.

BAD_OPERATION - exception `org.omg.CORBA.BAD_OPERATION`.

The CORBA `BAD_OPERATION` exception, which is thrown when a method is invalid.

BAD_OPERATION() - Constructor for class `org.omg.CORBA.BAD_OPERATION`

Constructs a `BAD_OPERATION` exception with a default minor code of 0 and a completion state of `COMPLETED_NO`.

BAD_OPERATION(int, CompletionStatus) - Constructor for class `org.omg.CORBA.BAD_OPERATION`

Constructs a `BAD_OPERATION` exception with the specified minor code and completion status.

BAD_OPERATION(String) - Constructor for class `org.omg.CORBA.BAD_OPERATION`

Constructs a `BAD_OPERATION` exception with the specified detail message, a minor code of 0, and a completion state of `COMPLETED_NO`.

BAD_OPERATION(String, int, CompletionStatus) - Constructor for class `org.omg.CORBA.BAD_OPERATION`

Constructs a `BAD_OPERATION` exception with the specified detail message, minor code, and completion status.

BAD_PARAM - exception `org.omg.CORBA.BAD_PARAM`.

The CORBA `BAD_PARAM` exception, which is thrown when an invalid parameter is passed to a method.

BAD_PARAM() - Constructor for class `org.omg.CORBA.BAD_PARAM`

Constructs a `BAD_PARAM` exception with a default minor code of 0 and a completion state of `COMPLETED_NO`.

BAD_PARAM(int, CompletionStatus) - Constructor for class `org.omg.CORBA.BAD_PARAM`

Constructs a `BAD_PARAM` exception with the specified minor code and completion status.

BAD_PARAM(String) - Constructor for class `org.omg.CORBA.BAD_PARAM`

Constructs a `BAD_PARAM` exception with the specified detail message, a minor code of 0, and a completion state of `COMPLETED_NO`.

BAD_PARAM(String, int, CompletionStatus) - Constructor for class `org.omg.CORBA.BAD_PARAM`

Constructs a `BAD_PARAM` exception with the specified detail message, minor code, and completion status.

BAD_POLICY - interface `org.omg.CORBA.BAD_POLICY`.

`BAD_POLICY` is one of the `PolicyErrorCodes` which would be filled in the `PolicyError` exception.

BAD_POLICY_TYPE - interface `org.omg.CORBA.BAD_POLICY_TYPE`.

`BAD_POLICY_TYPE` is one of the `PolicyErrorCodes` which would be filled in the `PolicyError` exception.

BAD_POLICY_VALUE - interface `org.omg.CORBA.BAD_POLICY_VALUE`.

Contains the value used to indicate a policy value that is incorrect for a valid policy type in a call to the `create_policy` method defined in the `ORB` class.

BAD_TYPECODE - exception `org.omg.CORBA.BAD_TYPECODE`.

The CORBA `BAD_TYPECODE` exception, which is thrown when the specified typecode is invalid.

BAD_TYPECODE() - Constructor for class org.omg.CORBA.BAD_TYPECODE

Constructs a BAD_TYPECODE exception with a default minor code of 0 and a completion state of COMPLETED_NO.

BAD_TYPECODE(int, CompletionStatus) - Constructor for class org.omg.CORBA.BAD_TYPECODE

Constructs a BAD_TYPECODE exception with the specified minor code and completion status.

BAD_TYPECODE(String) - Constructor for class org.omg.CORBA.BAD_TYPECODE

Constructs a BAD_TYPECODE exception with the specified detail, a minor code of 0, and a completion state of COMPLETED_NO.

BAD_TYPECODE(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.BAD_TYPECODE

Constructs a BAD_TYPECODE exception with the specified detail message, minor code, and completion status.

BadBreakWeight - Static variable in class javax.swing.text.View

The weight to indicate a view is a bad break opportunity for the purpose of formatting.

BadKind - exception org.omg.CORBA.TypeCodePackage.BadKind.

The exception BadKind is thrown when an inappropriate operation is invoked on a TypeCode object.

BadKind() - Constructor for class org.omg.CORBA.TypeCodePackage.BadKind

Constructs a BadKind exception with no reason message.

BadKind(String) - Constructor for class org.omg.CORBA.TypeCodePackage.BadKind

Constructs a BadKind exception with the specified reason message.

BadLocationException - exception javax.swing.text.BadLocationException.

This exception is to report bad locations within a document model (that is, attempts to reference a location that doesn't exist).

BadLocationException(String, int) - Constructor for class javax.swing.text.BadLocationException

Creates a new BadLocationException object.

BALANCE - Static variable in class javax.sound.sampled.FloatControl.Type

Represents a control for the relative balance of a stereo signal between two stereo speakers.

BandCombineOp - class java.awt.image.BandCombineOp.

This class performs an arbitrary linear combination of the bands in a Raster, using a specified matrix.

BandCombineOp(float[[[], RenderingHints) - Constructor for class java.awt.image.BandCombineOp

Constructs a BandCombineOp with the specified matrix.

BandedSampleModel - class java.awt.image.BandedSampleModel.

This class represents image data which is stored in a band interleaved fashion and for which each sample of a pixel occupies one data element of the DataBuffer.

BandedSampleModel(int, int, int, int) - Constructor for class java.awt.image.BandedSampleModel

Constructs a BandedSampleModel with the specified parameters.

BandedSampleModel(int, int, int, int, int[], int[]) - Constructor for class java.awt.image.BandedSampleModel

Constructs a BandedSampleModel with the specified parameters.

bandOffsets - Variable in class java.awt.image.ComponentSampleModel

Offsets for all bands in data array elements.

bank - Variable in class javax.sound.midi.VoiceStatus

The bank number of the instrument that this voice is currently using.

bankIndices - Variable in class java.awt.image.ComponentSampleModel

Index for each bank storing a band of image data.

banks - Variable in class java.awt.image.DataBuffer

The number of banks in this DataBuffer.

base - Variable in class javax.swing.text.html.parser.DTD

BASE - Static variable in class javax.swing.text.html.HTML.Tag

BASEFONT - Static variable in class javax.swing.text.html.HTML.Tag

baselineLayout(int, int, int[], int[]) - Method in class javax.swing.text.BoxView

baselineRequirements(int, SizeRequirements) - Method in class javax.swing.text.BoxView

baseWireHandle - Static variable in interface java.io.ObjectStreamConstants

First wire handle to be assigned.

BASIC_LATIN - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

BasicArrowButton - class javax.swing.plaf.basic.BasicArrowButton.

JButton object that draws a scaled Arrow in one of the cardinal directions.

BasicArrowButton(int) - Constructor for class javax.swing.plaf.basic.BasicArrowButton

BasicAttribute - class javax.naming.directory.BasicAttribute.

This class provides a basic implementation of the Attribute interface.

BasicAttribute(String) - Constructor for class javax.naming.directory.BasicAttribute

Constructs a new instance of an unordered attribute with no value.

BasicAttribute(String, boolean) - Constructor for class javax.naming.directory.BasicAttribute

Constructs a new instance of a possibly ordered attribute with no value.

BasicAttribute(String, Object) - Constructor for class javax.naming.directory.BasicAttribute

Constructs a new instance of an unordered attribute with a single value.

BasicAttribute(String, Object, boolean) - Constructor for class javax.naming.directory.BasicAttribute

Constructs a new instance of a possibly ordered attribute with a single value.

BasicAttributes - class javax.naming.directory.BasicAttributes.

This class provides a basic implementation of the Attributes interface.

BasicAttributes() - Constructor for class javax.naming.directory.BasicAttributes

Constructs a new instance of Attributes.

BasicAttributes(boolean) - Constructor for class javax.naming.directory.BasicAttributes

Constructs a new instance of Attributes.

BasicAttributes(String, Object) - Constructor for class javax.naming.directory.BasicAttributes

Constructs a new instance of Attributes with one attribute.

BasicAttributes(String, Object, boolean) - Constructor for class javax.naming.directory.BasicAttributes

Constructs a new instance of Attributes with one attribute.

BasicBorders - class javax.swing.plaf.basic.BasicBorders.

Factory object that can vend Borders appropriate for the basic L & F.

BasicBorders.ButtonBorder - class javax.swing.plaf.basic.BasicBorders.ButtonBorder.

BasicBorders.ButtonBorder(Color, Color, Color, Color) - Constructor for class javax.swing.plaf.basic.BasicBorders.ButtonBorder

BasicBorders.FieldBorder - class javax.swing.plaf.basic.BasicBorders.FieldBorder.

BasicBorders.FieldBorder(Color, Color, Color, Color) - Constructor for class

javax.swing.plaf.basic.BasicBorders.FieldBorder

BasicBorders.MarginBorder - class javax.swing.plaf.basic.BasicBorders.MarginBorder.

BasicBorders.MarginBorder() - Constructor for class javax.swing.plaf.basic.BasicBorders.MarginBorder

BasicBorders.MenuBarBorder - class javax.swing.plaf.basic.BasicBorders.MenuBarBorder.

BasicBorders.MenuBarBorder(Color, Color) - Constructor for class
javax.swing.plaf.basic.BasicBorders.MenuBarBorder

BasicBorders.RadioButtonBorder - class javax.swing.plaf.basic.BasicBorders.RadioButtonBorder.

BasicBorders.RadioButtonBorder(Color, Color, Color, Color) - Constructor for class
javax.swing.plaf.basic.BasicBorders.RadioButtonBorder

BasicBorders.SplitPaneBorder - class javax.swing.plaf.basic.BasicBorders.SplitPaneBorder.
Draws the border around the splitpane.

BasicBorders.SplitPaneBorder(Color, Color) - Constructor for class
javax.swing.plaf.basic.BasicBorders.SplitPaneBorder

BasicBorders.ToggleButtonBorder - class javax.swing.plaf.basic.BasicBorders.ToggleButtonBorder.

BasicBorders.ToggleButtonBorder(Color, Color, Color, Color) - Constructor for class
javax.swing.plaf.basic.BasicBorders.ToggleButtonBorder

BasicBorders() - Constructor for class javax.swing.plaf.basic.BasicBorders

BasicButtonListener - class javax.swing.plaf.basic.BasicButtonListener.
Button Listener

BasicButtonListener(AbstractButton) - Constructor for class javax.swing.plaf.basic.BasicButtonListener

BasicButtonUI - class javax.swing.plaf.basic.BasicButtonUI.
BasicButton implementation

BasicButtonUI() - Constructor for class javax.swing.plaf.basic.BasicButtonUI

BasicCheckBoxMenuItemUI - class javax.swing.plaf.basic.BasicCheckBoxMenuItemUI.
BasicCheckboxMenuItem implementation

BasicCheckBoxMenuItemUI() - Constructor for class javax.swing.plaf.basic.BasicCheckBoxMenuItemUI

BasicCheckBoxUI - class javax.swing.plaf.basic.BasicCheckBoxUI.
CheckboxUI implementation for BasicCheckboxUI

BasicCheckBoxUI() - Constructor for class javax.swing.plaf.basic.BasicCheckBoxUI

BasicColorChooserUI - class javax.swing.plaf.basic.BasicColorChooserUI.
Provides the basic look and feel for a JColorChooser.

BasicColorChooserUI.PropertyHandler - class javax.swing.plaf.basic.BasicColorChooserUI.PropertyHandler.

This inner class is marked "public" due to a compiler bug.

BasicColorChooserUI.PropertyHandler(BasicColorChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicColorChooserUI.PropertyHandler

BasicColorChooserUI() - Constructor for class javax.swing.plaf.basic.BasicColorChooserUI

BasicComboBoxEditor - class javax.swing.plaf.basic.BasicComboBoxEditor.

The default editor for editable combo boxes

BasicComboBoxEditor.UIResource - class javax.swing.plaf.basic.BasicComboBoxEditor.UIResource.

A subclass of BasicComboBoxEditor that implements UIResource.

BasicComboBoxEditor.UIResource() - Constructor for class
javax.swing.plaf.basic.BasicComboBoxEditor.UIResource

BasicComboBoxEditor() - Constructor for class javax.swing.plaf.basic.BasicComboBoxEditor

BasicComboBoxRenderer - class javax.swing.plaf.basic.BasicComboBoxRenderer.

ComboBox renderer

BasicComboBoxRenderer.UIResource - class javax.swing.plaf.basic.BasicComboBoxRenderer.UIResource.

A subclass of BasicComboBoxRenderer that implements UIResource.

BasicComboBoxRenderer.UIResource() - Constructor for class
javax.swing.plaf.basic.BasicComboBoxRenderer.UIResource

BasicComboBoxRenderer() - Constructor for class javax.swing.plaf.basic.BasicComboBoxRenderer

BasicComboBoxUI - class javax.swing.plaf.basic.BasicComboBoxUI.

Basic UI for JComboBox.

BasicComboBoxUI.ComboBoxLayoutManager - class

javax.swing.plaf.basic.BasicComboBoxUI.ComboBoxLayoutManager.

This layout manager handles the 'standard' layout of combo boxes.

BasicComboBoxUI.ComboBoxLayoutManager(BasicComboBoxUI) - Constructor for class
javax.swing.plaf.basic.BasicComboBoxUI.ComboBoxLayoutManager

BasicComboBoxUI.FocusHandler - class javax.swing.plaf.basic.BasicComboBoxUI.FocusHandler.

This listener hides the popup when the focus is lost.

BasicComboBoxUI.FocusHandler(BasicComboBoxUI) - Constructor for class
javax.swing.plaf.basic.BasicComboBoxUI.FocusHandler

BasicComboBoxUI.ItemHandler - class javax.swing.plaf.basic.BasicComboBoxUI.ItemHandler.

This listener watches for changes to the selection in the combo box and updates the display of the currently selected item.

BasicComboBoxUI.ItemHandler(BasicComboBoxUI) - Constructor for class
javax.swing.plaf.basic.BasicComboBoxUI.ItemHandler

BasicComboBoxUI.KeyHandler - class javax.swing.plaf.basic.BasicComboBoxUI.KeyHandler.

This listener checks to see if the key event isn't a navigation key.

BasicComboBoxUI.KeyHandler(BasicComboBoxUI) - Constructor for class
javax.swing.plaf.basic.BasicComboBoxUI.KeyHandler

BasicComboBoxUI.ListDataHandler - class javax.swing.plaf.basic.BasicComboBoxUI.ListDataHandler.

This listener watches for changes in the data and revalidates.

BasicComboBoxUI.ListDataHandler(BasicComboBoxUI) - Constructor for class javax.swing.plaf.basic.BasicComboBoxUI.ListDataHandler

BasicComboBoxUI.PropertyChangeHandler - class

javax.swing.plaf.basic.BasicComboBoxUI.PropertyChangeHandler.

This listener watches for bound properties that have changed in the JComboBox.

BasicComboBoxUI.PropertyChangeHandler(BasicComboBoxUI) - Constructor for class javax.swing.plaf.basic.BasicComboBoxUI.PropertyChangeHandler

BasicComboBoxUI() - Constructor for class javax.swing.plaf.basic.BasicComboBoxUI

BasicComboPopup - class javax.swing.plaf.basic.BasicComboPopup.

This is an implementation of the ComboPopup interface.

BasicComboPopup.InvocationKeyHandler - class

javax.swing.plaf.basic.BasicComboPopup.InvocationKeyHandler.

This listener watches for the spacebar being pressed and shows/hides the popup accordingly.

BasicComboPopup.InvocationKeyHandler(BasicComboPopup) - Constructor for class javax.swing.plaf.basic.BasicComboPopup.InvocationKeyHandler

BasicComboPopup.InvocationMouseHandler - class

javax.swing.plaf.basic.BasicComboPopup.InvocationMouseHandler.

This listener knows how and when to invoke this popup menu.

BasicComboPopup.InvocationMouseHandler(BasicComboPopup) - Constructor for class javax.swing.plaf.basic.BasicComboPopup.InvocationMouseHandler

BasicComboPopup.InvocationMouseMotionHandler - class

javax.swing.plaf.basic.BasicComboPopup.InvocationMouseMotionHandler.

This listener watches for dragging and updates the current selection in the list if it is dragging over the list.

BasicComboPopup.InvocationMouseMotionHandler(BasicComboPopup) - Constructor for class javax.swing.plaf.basic.BasicComboPopup.InvocationMouseMotionHandler

BasicComboPopup.ItemHandler - class javax.swing.plaf.basic.BasicComboPopup.ItemHandler.

This listener watches for changes in the JComboBox's selection.

BasicComboPopup.ItemHandler(BasicComboPopup) - Constructor for class javax.swing.plaf.basic.BasicComboPopup.ItemHandler

BasicComboPopup.ListDataHandler - class javax.swing.plaf.basic.BasicComboPopup.ListDataHandler.

Keeps the selected index in the list in-sync with the combo box's selection.

BasicComboPopup.ListDataHandler(BasicComboPopup) - Constructor for class javax.swing.plaf.basic.BasicComboPopup.ListDataHandler

BasicComboPopup.ListMouseHandler - class javax.swing.plaf.basic.BasicComboPopup.ListMouseHandler.

This listener hides the popup when the mouse is released in the list.

BasicComboPopup.ListMouseHandler(BasicComboPopup) - Constructor for class
javax.swing.plaf.basic.BasicComboPopup.ListMouseHandler

BasicComboPopup.ListMouseMotionHandler - class
javax.swing.plaf.basic.BasicComboPopup.ListMouseMotionHandler.

This listener changes the selected item as you move the mouse over the list.

BasicComboPopup.ListMouseMotionHandler(BasicComboPopup) - Constructor for class
javax.swing.plaf.basic.BasicComboPopup.ListMouseMotionHandler

BasicComboPopup.ListSelectionHandler - class
javax.swing.plaf.basic.BasicComboPopup.ListSelectionHandler.

This listener watches for changes in the list's selection and reports them to the combo box.

BasicComboPopup.ListSelectionHandler(BasicComboPopup) - Constructor for class
javax.swing.plaf.basic.BasicComboPopup.ListSelectionHandler

BasicComboPopup.PropertyChangeHandler - class
javax.swing.plaf.basic.BasicComboPopup.PropertyChangeHandler.

This listener watches for bound property changes in JComboBox.

BasicComboPopup.PropertyChangeHandler(BasicComboPopup) - Constructor for class
javax.swing.plaf.basic.BasicComboPopup.PropertyChangeHandler

BasicComboPopup(JComboBox) - Constructor for class javax.swing.plaf.basic.BasicComboPopup

BasicDesktopIconUI - class javax.swing.plaf.basic.BasicDesktopIconUI.

Basic L&F for a minimized window on a desktop.

BasicDesktopIconUI.MouseInputHandler - class
javax.swing.plaf.basic.BasicDesktopIconUI.MouseInputHandler.

Listens for mouse movements and acts on them.

BasicDesktopIconUI.MouseInputHandler(BasicDesktopIconUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopIconUI.MouseInputHandler

BasicDesktopIconUIQ - Constructor for class javax.swing.plaf.basic.BasicDesktopIconUI

BasicDesktopPaneUI - class javax.swing.plaf.basic.BasicDesktopPaneUI.

Basic L&F for a desktop.

BasicDesktopPaneUI.CloseAction - class javax.swing.plaf.basic.BasicDesktopPaneUI.CloseAction.

BasicDesktopPaneUI.CloseAction(BasicDesktopPaneUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopPaneUI.CloseAction

BasicDesktopPaneUI.MaximizeAction - class javax.swing.plaf.basic.BasicDesktopPaneUI.MaximizeAction.

BasicDesktopPaneUI.MaximizeAction(BasicDesktopPaneUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopPaneUI.MaximizeAction

BasicDesktopPaneUI.MinimizeAction - class javax.swing.plaf.basic.BasicDesktopPaneUI.MinimizeAction.

BasicDesktopPaneUI.MinimizeAction(BasicDesktopPaneUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopPaneUI.MinimizeAction

BasicDesktopPaneUI.NavigateAction - class javax.swing.plaf.basic.BasicDesktopPaneUI.NavigateAction.

BasicDesktopPaneUI.NavigateAction(BasicDesktopPaneUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopPaneUI.NavigateAction

BasicDesktopPaneUI.OpenAction - class javax.swing.plaf.basic.BasicDesktopPaneUI.OpenAction.

BasicDesktopPaneUI.OpenAction(BasicDesktopPaneUI) - Constructor for class
javax.swing.plaf.basic.BasicDesktopPaneUI.OpenAction

BasicDesktopPaneUI() - Constructor for class javax.swing.plaf.basic.BasicDesktopPaneUI

BasicDirectoryModel - class javax.swing.plaf.basic.BasicDirectoryModel.

Basic implementation of a file list.

BasicDirectoryModel(JFileChooser) - Constructor for class javax.swing.plaf.basic.BasicDirectoryModel

BasicEditorPaneUI - class javax.swing.plaf.basic.BasicEditorPaneUI.

Provides the look and feel for a JEditorPane.

BasicEditorPaneUI() - Constructor for class javax.swing.plaf.basic.BasicEditorPaneUI

Creates a new BasicEditorPaneUI.

BasicFileChooserUI - class javax.swing.plaf.basic.BasicFileChooserUI.

Basic L&F implementation of a FileChooser.

BasicFileChooserUI.AcceptAllFileFilter - class

javax.swing.plaf.basic.BasicFileChooserUI.AcceptAllFileFilter.

BasicFileChooserUI.AcceptAllFileFilter(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.AcceptAllFileFilter

BasicFileChooserUI.ApproveSelectionAction - class

javax.swing.plaf.basic.BasicFileChooserUI.ApproveSelectionAction.

Responds to an Open or Save request

BasicFileChooserUI.ApproveSelectionAction(BasicFileChooserUI) - Constructor for class

javax.swing.plaf.basic.BasicFileChooserUI.ApproveSelectionAction

BasicFileChooserUI.BasicFileView - class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView.

BasicFileChooserUI.BasicFileView(BasicFileChooserUI) - Constructor for class

javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

BasicFileChooserUI.CancelSelectionAction - class

javax.swing.plaf.basic.BasicFileChooserUI.CancelSelectionAction.

Responds to a cancel request.

BasicFileChooserUI.CancelSelectionAction(BasicFileChooserUI) - Constructor for class

javax.swing.plaf.basic.BasicFileChooserUI.CancelSelectionAction

BasicFileChooserUI.ChangeToParentDirectoryAction - class
javax.swing.plaf.basic.BasicFileChooserUI.ChangeToParentDirectoryAction.

BasicFileChooserUI.ChangeToParentDirectoryAction(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.ChangeToParentDirectoryAction

BasicFileChooserUI.DoubleClickListener - class
javax.swing.plaf.basic.BasicFileChooserUI.DoubleClickListener.

BasicFileChooserUI.DoubleClickListener(BasicFileChooserUI, JList) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.DoubleClickListener

BasicFileChooserUI.GoHomeAction - class javax.swing.plaf.basic.BasicFileChooserUI.GoHomeAction.
Acts on the "home" key event or equivalent event.

BasicFileChooserUI.GoHomeAction(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.GoHomeAction

BasicFileChooserUI.NewFolderAction - class javax.swing.plaf.basic.BasicFileChooserUI.NewFolderAction.
Creates a new folder.

BasicFileChooserUI.NewFolderAction(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.NewFolderAction

BasicFileChooserUI.SelectionListener - class javax.swing.plaf.basic.BasicFileChooserUI.SelectionListener.

BasicFileChooserUI.SelectionListener(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.SelectionListener

BasicFileChooserUI.UpdateAction - class javax.swing.plaf.basic.BasicFileChooserUI.UpdateAction.
Rescans the files in the current directory

BasicFileChooserUI.UpdateAction(BasicFileChooserUI) - Constructor for class
javax.swing.plaf.basic.BasicFileChooserUI.UpdateAction

BasicFileChooserUI(JFileChooser) - Constructor for class javax.swing.plaf.basic.BasicFileChooserUI

BasicGraphicsUtils - class javax.swing.plaf.basic.BasicGraphicsUtils.

BasicGraphicsUtils() - Constructor for class javax.swing.plaf.basic.BasicGraphicsUtils

BasicHTML - class javax.swing.plaf.basic.BasicHTML.
Support for providing html views for the swing components.

BasicHTML() - Constructor for class javax.swing.plaf.basic.BasicHTML

BasicIconFactory - class javax.swing.plaf.basic.BasicIconFactory.
Factory object that can vend Icons appropriate for the basic L & F.

BasicIconFactory() - Constructor for class javax.swing.plaf.basic.BasicIconFactory

BasicInternalFrameTitlePane - class javax.swing.plaf.basic.BasicInternalFrameTitlePane.

The class that manages a basic title bar

BasicInternalFrameTitlePane.CloseAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.CloseAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.CloseAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.CloseAction

BasicInternalFrameTitlePane.IconifyAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.IconifyAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.IconifyAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.IconifyAction

BasicInternalFrameTitlePane.MaximizeAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.MaximizeAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.MaximizeAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.MaximizeAction

BasicInternalFrameTitlePane.MoveAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.MoveAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.MoveAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.MoveAction

BasicInternalFrameTitlePane.PropertyChangeHandler - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.PropertyChangeHandler.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.PropertyChangeHandler(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.PropertyChangeHandler

BasicInternalFrameTitlePane.RestoreAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.RestoreAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.RestoreAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.RestoreAction

BasicInternalFrameTitlePane.SizeAction - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.SizeAction.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.SizeAction(BasicInternalFrameTitlePane) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.SizeAction

BasicInternalFrameTitlePane.SystemMenuBar - class

javax.swing.plaf.basic.BasicInternalFrameTitlePane.SystemMenuBar.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.SystemMenuBar(BasicInternalFrameTitlePane) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameTitlePane.SystemMenuBar

BasicInternalFrameTitlePane.TitlePaneLayout - class
javax.swing.plaf.basic.BasicInternalFrameTitlePane.TitlePaneLayout.

This inner class is marked "public" due to a compiler bug.

BasicInternalFrameTitlePane.TitlePaneLayout(BasicInternalFrameTitlePane) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameTitlePane.TitlePaneLayout

BasicInternalFrameTitlePane(JInternalFrame) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameTitlePane

BasicInternalFrameUI - class javax.swing.plaf.basic.BasicInternalFrameUI.

A basic L&F implementation of JInternalFrame.

BasicInternalFrameUI.BasicInternalFrameListener - class
javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener.

BasicInternalFrameUI.BasicInternalFrameListener(BasicInternalFrameUI) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

BasicInternalFrameUI.BorderListener - class javax.swing.plaf.basic.BasicInternalFrameUI.BorderListener.
Listens for border adjustments.

BasicInternalFrameUI.BorderListener(BasicInternalFrameUI) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameUI.BorderListener

BasicInternalFrameUI.ComponentHandler - class
javax.swing.plaf.basic.BasicInternalFrameUI.ComponentHandler.

BasicInternalFrameUI.ComponentHandler(BasicInternalFrameUI) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameUI.ComponentHandler

BasicInternalFrameUI.GlassPaneDispatcher - class
javax.swing.plaf.basic.BasicInternalFrameUI.GlassPaneDispatcher.

BasicInternalFrameUI.GlassPaneDispatcher(BasicInternalFrameUI) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameUI.GlassPaneDispatcher

BasicInternalFrameUI.InternalFrameLayout - class
javax.swing.plaf.basic.BasicInternalFrameUI.InternalFrameLayout.

BasicInternalFrameUI.InternalFrameLayout(BasicInternalFrameUI) - Constructor for class
javax.swing.plaf.basic.BasicInternalFrameUI.InternalFrameLayout

BasicInternalFrameUI.InternalFramePropertyChangeListener - class
javax.swing.plaf.basic.BasicInternalFrameUI.InternalFramePropertyChangeListener.

BasicInternalFrameUI.InternalFramePropertyChangeListener(BasicInternalFrameUI) - Constructor for class

javax.swing.plaf.basic.BasicInternalFrameUI.InternalFramePropertyChangeListener

BasicInternalFrameUI(JInternalFrame) - Constructor for class javax.swing.plaf.basic.BasicInternalFrameUI

BasicLabelUI - class javax.swing.plaf.basic.BasicLabelUI.

A Windows L&F implementation of LabelUI.

BasicLabelUI() - Constructor for class javax.swing.plaf.basic.BasicLabelUI

BasicListUI - class javax.swing.plaf.basic.BasicListUI.

A Windows L&F implementation of ListUI.

BasicListUI.FocusHandler - class javax.swing.plaf.basic.BasicListUI.FocusHandler.

This inner class is marked "public" due to a compiler bug.

BasicListUI.FocusHandler(BasicListUI) - Constructor for class
javax.swing.plaf.basic.BasicListUI.FocusHandler

BasicListUI.ListDataHandler - class javax.swing.plaf.basic.BasicListUI.ListDataHandler.

The ListDataListener that's added to the JLists model at installUI time, and whenever the JList.model property changes.

BasicListUI.ListDataHandler(BasicListUI) - Constructor for class
javax.swing.plaf.basic.BasicListUI.ListDataHandler

BasicListUI.ListSelectionHandler - class javax.swing.plaf.basic.BasicListUI.ListSelectionHandler.

The ListSelectionListener that's added to the JLists selection model at installUI time, and whenever the JList.selectionModel property changes.

BasicListUI.ListSelectionHandler(BasicListUI) - Constructor for class
javax.swing.plaf.basic.BasicListUI.ListSelectionHandler

BasicListUI.MouseInputHandler - class javax.swing.plaf.basic.BasicListUI.MouseInputHandler.

Mouse input, and focus handling for JList.

BasicListUI.MouseInputHandler(BasicListUI) - Constructor for class
javax.swing.plaf.basic.BasicListUI.MouseInputHandler

BasicListUI.PropertyChangeHandler - class javax.swing.plaf.basic.BasicListUI.PropertyChangeHandler.

The PropertyChangeListener that's added to the JList at installUI time.

BasicListUI.PropertyChangeHandler(BasicListUI) - Constructor for class
javax.swing.plaf.basic.BasicListUI.PropertyChangeHandler

BasicListUI() - Constructor for class javax.swing.plaf.basic.BasicListUI

BasicLookAndFeel - class javax.swing.plaf.basic.BasicLookAndFeel.

Implements the a standard base LookAndFeel class from which standard desktop LookAndFeel classes (JL&F, Mac, Windows, etc.) can be derived.

BasicLookAndFeel() - Constructor for class javax.swing.plaf.basic.BasicLookAndFeel

BasicMenuBarUI - class javax.swing.plaf.basic.BasicMenuBarUI.

A default L&F implementation of MenuBarUI.

BasicMenuBarUI() - Constructor for class javax.swing.plaf.basic.BasicMenuBarUI

BasicMenuItemUI - class javax.swing.plaf.basic.BasicMenuItemUI.

BasicMenuItem implementation

BasicMenuItemUI.MouseInputHandler - class javax.swing.plaf.basic.BasicMenuItemUI.MouseInputHandler.

BasicMenuItemUI.MouseInputHandler(BasicMenuItemUI) - Constructor for class javax.swing.plaf.basic.BasicMenuItemUI.MouseInputHandler

BasicMenuItemUI() - Constructor for class javax.swing.plaf.basic.BasicMenuItemUI

BasicMenuUI - class javax.swing.plaf.basic.BasicMenuUI.

A default L&F implementation of MenuUI.

BasicMenuUI.ChangeHandler - class javax.swing.plaf.basic.BasicMenuUI.ChangeHandler.

BasicMenuUI.ChangeHandler(BasicMenuUI, JMenu, BasicMenuUI) - Constructor for class javax.swing.plaf.basic.BasicMenuUI.ChangeHandler

BasicMenuUI() - Constructor for class javax.swing.plaf.basic.BasicMenuUI

BasicOptionPaneUI - class javax.swing.plaf.basic.BasicOptionPaneUI.

Provides the basic look and feel for a JOptionPane.

BasicOptionPaneUI.ButtonActionListener - class

javax.swing.plaf.basic.BasicOptionPaneUI.ButtonActionListener.

This inner class is marked "public" due to a compiler bug.

BasicOptionPaneUI.ButtonActionListener(BasicOptionPaneUI, int) - Constructor for class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonActionListener

BasicOptionPaneUI.ButtonAreaLayout - class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonAreaLayout.

ButtonAreaLayout acts similar to FlowLayout.

BasicOptionPaneUI.ButtonAreaLayout(boolean, int) - Constructor for class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonAreaLayout

BasicOptionPaneUI.PropertyChangeListener - class

javax.swing.plaf.basic.BasicOptionPaneUI.PropertyChangeListener.

This inner class is marked "public" due to a compiler bug.

BasicOptionPaneUI.PropertyChangeListener(BasicOptionPaneUI) - Constructor for class javax.swing.plaf.basic.BasicOptionPaneUI.PropertyChangeListener

BasicOptionPaneUI() - Constructor for class javax.swing.plaf.basic.BasicOptionPaneUI

BasicPanelUI - class javax.swing.plaf.basic.BasicPanelUI.

BasicPanel implementation

BasicPanelUI() - Constructor for class javax.swing.plaf.basic.BasicPanelUI

BasicPasswordFieldUI - class javax.swing.plaf.basic.BasicPasswordFieldUI.

Provides the Windows look and feel for a password field.

BasicPasswordFieldUI() - Constructor for class javax.swing.plaf.basic.BasicPasswordFieldUI

BasicPermission - class java.security.BasicPermission.

The BasicPermission class extends the Permission class, and can be used as the base class for permissions that want to follow the same naming convention as BasicPermission.

BasicPermission(String) - Constructor for class java.security.BasicPermission

Creates a new BasicPermission with the specified name.

BasicPermission(String, String) - Constructor for class java.security.BasicPermission

Creates a new BasicPermission object with the specified name.

BasicPopupMenuSeparatorUI - class javax.swing.plaf.basic.BasicPopupMenuSeparatorUI.

A Basic L&F implementation of PopupMenuSeparatorUI.

BasicPopupMenuSeparatorUI() - Constructor for class javax.swing.plaf.basic.BasicPopupMenuSeparatorUI

BasicPopupMenuUI - class javax.swing.plaf.basic.BasicPopupMenuUI.

A Windows L&F implementation of PopupMenuUI.

BasicPopupMenuUI() - Constructor for class javax.swing.plaf.basic.BasicPopupMenuUI

BasicProgressBarUI - class javax.swing.plaf.basic.BasicProgressBarUI.

A Basic L&F implementation of ProgressBarUI.

BasicProgressBarUI.ChangeHandler - class javax.swing.plaf.basic.BasicProgressBarUI.ChangeHandler.

This inner class is marked "public" due to a compiler bug.

BasicProgressBarUI.ChangeHandler(BasicProgressBarUI) - Constructor for class javax.swing.plaf.basic.BasicProgressBarUI.ChangeHandler

BasicProgressBarUI() - Constructor for class javax.swing.plaf.basic.BasicProgressBarUI

BasicRadioButtonMenuItemUI - class javax.swing.plaf.basic.BasicRadioButtonMenuItemUI.

BasicRadioButtonMenuItem implementation

BasicRadioButtonMenuItemUI() - Constructor for class javax.swing.plaf.basic.BasicRadioButtonMenuItemUI

BasicRadioButtonUI - class javax.swing.plaf.basic.BasicRadioButtonUI.

RadioButtonUI implementation for BasicRadioButtonUI

BasicRadioButtonUI() - Constructor for class javax.swing.plaf.basic.BasicRadioButtonUI

BasicRootPaneUI - class javax.swing.plaf.basic.BasicRootPaneUI.

Basic implementation of RootPaneUI, there is one shared between all JRootPane instances.

BasicRootPaneUI() - Constructor for class javax.swing.plaf.basic.BasicRootPaneUI

BasicScrollBarUI - class javax.swing.plaf.basic.BasicScrollBarUI.

Implementation of ScrollBarUI for the Basic Look and Feel

BasicScrollBarUI.ArrowButtonListener - class javax.swing.plaf.basic.BasicScrollBarUI.ArrowButtonListener.

Listener for cursor keys.

BasicScrollBarUI.ArrowButtonListener(BasicScrollBarUI) - Constructor for class javax.swing.plaf.basic.BasicScrollBarUI.ArrowButtonListener

BasicScrollBarUI.ModelListener - class javax.swing.plaf.basic.BasicScrollBarUI.ModelListener.

A listener to listen for model changes.

BasicScrollBarUI.ModelListener(BasicScrollBarUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollBarUI.ModelListener

BasicScrollBarUI.PropertyChangeHandler - class

javax.swing.plaf.basic.BasicScrollBarUI.PropertyChangeHandler.

BasicScrollBarUI.PropertyChangeHandler(BasicScrollBarUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollBarUI.PropertyChangeHandler

BasicScrollBarUI.ScrollListener - class javax.swing.plaf.basic.BasicScrollBarUI.ScrollListener.

Listener for scrolling events initiated in the ScrollPane.

BasicScrollBarUI.ScrollListener(BasicScrollBarUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollBarUI.ScrollListener

BasicScrollBarUI.ScrollListener(BasicScrollBarUI, int, boolean) - Constructor for class

javax.swing.plaf.basic.BasicScrollBarUI.ScrollListener

BasicScrollBarUI.TrackListener - class javax.swing.plaf.basic.BasicScrollBarUI.TrackListener.

Track mouse drags.

BasicScrollBarUI.TrackListener(BasicScrollBarUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollBarUI.TrackListener

BasicScrollBarUI() - Constructor for class javax.swing.plaf.basic.BasicScrollBarUI

BasicScrollPaneUI - class javax.swing.plaf.basic.BasicScrollPaneUI.

A default L&F implementation of ScrollPaneUI.

BasicScrollPaneUI.HSBChangeListener - class

javax.swing.plaf.basic.BasicScrollPaneUI.HSBChangeListener.

Horizontal scrollbar listener.

BasicScrollPaneUI.HSBChangeListener(BasicScrollPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollPaneUI.HSBChangeListener

BasicScrollPaneUI.PropertyChangeHandler - class

javax.swing.plaf.basic.BasicScrollPaneUI.PropertyChangeHandler.

BasicScrollPaneUI.PropertyChangeHandler(BasicScrollPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollPaneUI.PropertyChangeHandler

BasicScrollPaneUI.ViewportChangeListener - class

javax.swing.plaf.basic.BasicScrollPaneUI.ViewportChangeListener.

Listener for viewport events.

BasicScrollPaneUI.ViewportChangeListener(BasicScrollPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollPaneUI.ViewportChangeListener

BasicScrollPaneUI.VSBChangeListener - class

javax.swing.plaf.basic.BasicScrollPaneUI.VSBChangeListener.

Vertical scrollbar listener.

BasicScrollPaneUI.VSBChangeListener(BasicScrollPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicScrollPaneUI.VSBChangeListener

BasicScrollPaneUI() - Constructor for class javax.swing.plaf.basic.BasicScrollPaneUI

BasicSeparatorUI - class javax.swing.plaf.basic.BasicSeparatorUI.

A Basic L&F implementation of SeparatorUI.

BasicSeparatorUI() - Constructor for class javax.swing.plaf.basic.BasicSeparatorUI

BasicSliderUI - class javax.swing.plaf.basic.BasicSliderUI.

A Basic L&F implementation of SliderUI.

BasicSliderUI.ActionScroller - class javax.swing.plaf.basic.BasicSliderUI.ActionScroller.

As of Java 2 platform v1.3 this undocumented class is no longer used.

BasicSliderUI.ActionScroller(BasicSliderUI, JSlider, int, boolean) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.ActionScroller

BasicSliderUI.ChangeHandler - class javax.swing.plaf.basic.BasicSliderUI.ChangeHandler.

Data model listener.

BasicSliderUI.ChangeHandler(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.ChangeHandler

BasicSliderUI.ComponentHandler - class javax.swing.plaf.basic.BasicSliderUI.ComponentHandler.

Listener for resizing events.

BasicSliderUI.ComponentHandler(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.ComponentHandler

BasicSliderUI.FocusHandler - class javax.swing.plaf.basic.BasicSliderUI.FocusHandler.

Focus-change listener.

BasicSliderUI.FocusHandler(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.FocusHandler

BasicSliderUI.PropertyChangeHandler - class javax.swing.plaf.basic.BasicSliderUI.PropertyChangeHandler.

BasicSliderUI.PropertyChangeHandler(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.PropertyChangeHandler

BasicSliderUI.ScrollListener - class javax.swing.plaf.basic.BasicSliderUI.ScrollListener.

Scroll-event listener.

BasicSliderUI.ScrollListener(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.ScrollListener

BasicSliderUI.ScrollListener(BasicSliderUI, int, boolean) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.ScrollListener

BasicSliderUI.TrackListener - class javax.swing.plaf.basic.BasicSliderUI.TrackListener.

Track mouse movements.

BasicSliderUI.TrackListener(BasicSliderUI) - Constructor for class javax.swing.plaf.basic.BasicSliderUI.TrackListener

BasicSliderUI(JSlider) - Constructor for class javax.swing.plaf.basic.BasicSliderUI

BasicSplitPaneDivider - class javax.swing.plaf.basic.BasicSplitPaneDivider.

Divider used by BasicSplitPaneUI.

BasicSplitPaneDivider.DividerLayout - class javax.swing.plaf.basic.BasicSplitPaneDivider.DividerLayout.

Used to layout a BasicSplitPaneDivider.

BasicSplitPaneDivider.DividerLayout(BasicSplitPaneDivider) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneDivider.DividerLayout

BasicSplitPaneDivider.DragController - class javax.swing.plaf.basic.BasicSplitPaneDivider.DragController.

Handles the events during a dragging session for a HORIZONTAL_SPLIT orientated split pane.

BasicSplitPaneDivider.DragController(BasicSplitPaneDivider, MouseEvent) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneDivider.DragController

BasicSplitPaneDivider.MouseHandler - class javax.swing.plaf.basic.BasicSplitPaneDivider.MouseHandler.

MouseHandler is responsible for converting mouse events (released, dragged...) into the appropriate DragController methods.

BasicSplitPaneDivider.MouseHandler(BasicSplitPaneDivider) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneDivider.MouseHandler

BasicSplitPaneDivider.VerticalDragController - class javax.swing.plaf.basic.BasicSplitPaneDivider.VerticalDragController.

Handles the events during a dragging session for a VERTICAL_SPLIT orientated split pane.

BasicSplitPaneDivider.VerticalDragController(BasicSplitPaneDivider, MouseEvent) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneDivider.VerticalDragController

BasicSplitPaneDivider(BasicSplitPaneUI) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneDivider

Creates an instance of BasicSplitPaneDivider.

BasicSplitPaneUI - class javax.swing.plaf.basic.BasicSplitPaneUI.

A Basic L&F implementation of the SplitPaneUI.

BasicSplitPaneUI.BasicHorizontalLayoutManager - class javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager.

LayoutManager for JSplitPanes that have an orientation of HORIZONTAL_SPLIT.

BasicSplitPaneUI.BasicVerticalLayoutManager - class javax.swing.plaf.basic.BasicSplitPaneUI.BasicVerticalLayoutManager.

LayoutManager used for JSplitPanes with an orientation of VERTICAL_SPLIT.

BasicSplitPaneUI.BasicVerticalLayoutManager(BasicSplitPaneUI) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneUI.BasicVerticalLayoutManager

BasicSplitPaneUI.FocusHandler - class javax.swing.plaf.basic.BasicSplitPaneUI.FocusHandler.

Implementation of the FocusListener that the JSplitPane UI uses.

BasicSplitPaneUI.FocusHandler(BasicSplitPaneUI) - Constructor for class javax.swing.plaf.basic.BasicSplitPaneUI.FocusHandler

BasicSplitPaneUI.KeyboardDownRightHandler - class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardDownRightHandler.

Implementation of an ActionListener that the JSplitPane UI uses for handling specific key presses.

BasicSplitPaneUI.KeyboardDownRightHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardDownRightHandler

BasicSplitPaneUI.KeyboardEndHandler - class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardEndHandler.

Implementation of an ActionListener that the JSplitPane UI uses for handling specific key presses.

BasicSplitPaneUI.KeyboardEndHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardEndHandler

BasicSplitPaneUI.KeyboardHomeHandler - class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardHomeHandler.

Implementation of an ActionListener that the JSplitPane UI uses for handling specific key presses.

BasicSplitPaneUI.KeyboardHomeHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardHomeHandler

BasicSplitPaneUI.KeyboardResizeToggleHandler - class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardResizeToggleHandler.

Implementation of an ActionListener that the JSplitPane UI uses for handling specific key presses.

BasicSplitPaneUI.KeyboardResizeToggleHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardResizeToggleHandler

BasicSplitPaneUI.KeyboardUpLeftHandler - class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardUpLeftHandler.

Implementation of an ActionListener that the JSplitPane UI uses for handling specific key presses.

BasicSplitPaneUI.KeyboardUpLeftHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.KeyboardUpLeftHandler

BasicSplitPaneUI.PropertyHandler - class javax.swing.plaf.basic.BasicSplitPaneUI.PropertyHandler.

Implementation of the PropertyChangeListener that the JSplitPane UI uses.

BasicSplitPaneUI.PropertyHandler(BasicSplitPaneUI) - Constructor for class

javax.swing.plaf.basic.BasicSplitPaneUI.PropertyHandler

BasicSplitPaneUI() - Constructor for class javax.swing.plaf.basic.BasicSplitPaneUI

BasicStroke - class java.awt.BasicStroke.

The BasicStroke class defines a basic set of rendering attributes for the outlines of graphics primitives, which are rendered with a Graphics2D object that has its Stroke attribute set to this BasicStroke.

BasicStroke() - Constructor for class java.awt.BasicStroke

Constructs a new BasicStroke with defaults for all attributes.

BasicStroke(float) - Constructor for class java.awt.BasicStroke

Constructs a solid BasicStroke with the specified line width and with default values for the cap and join styles.

BasicStroke(float, int, int) - Constructor for class java.awt.BasicStroke

Constructs a solid BasicStroke with the specified attributes.

BasicStroke(float, int, int, float) - Constructor for class java.awt.BasicStroke

Constructs a solid `BasicStroke` with the specified attributes.

`BasicStroke(float, int, int, float, float[], float)` - Constructor for class `java.awt.BasicStroke`

Constructs a new `BasicStroke` with the specified attributes.

`BasicTabbedPaneUI` - class `javax.swing.plaf.basic.BasicTabbedPaneUI`.

A Basic L&F implementation of `TabbedPaneUI`.

`BasicTabbedPaneUI.FocusHandler` - class `javax.swing.plaf.basic.BasicTabbedPaneUI.FocusHandler`.

This inner class is marked "public" due to a compiler bug.

`BasicTabbedPaneUI.FocusHandler(BasicTabbedPaneUI)` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI.FocusHandler`

`BasicTabbedPaneUI.MouseHandler` - class `javax.swing.plaf.basic.BasicTabbedPaneUI.MouseHandler`.

This inner class is marked "public" due to a compiler bug.

`BasicTabbedPaneUI.MouseHandler(BasicTabbedPaneUI)` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI.MouseHandler`

`BasicTabbedPaneUI.PropertyChangeHandler` - class `javax.swing.plaf.basic.BasicTabbedPaneUI.PropertyChangeHandler`.

This inner class is marked "public" due to a compiler bug.

`BasicTabbedPaneUI.PropertyChangeHandler(BasicTabbedPaneUI)` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI.PropertyChangeHandler`

`BasicTabbedPaneUI.TabbedPaneLayout` - class `javax.swing.plaf.basic.BasicTabbedPaneUI.TabbedPaneLayout`.

This inner class is marked "public" due to a compiler bug.

`BasicTabbedPaneUI.TabbedPaneLayout(BasicTabbedPaneUI)` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI.TabbedPaneLayout`

`BasicTabbedPaneUI.TabSelectionHandler` - class `javax.swing.plaf.basic.BasicTabbedPaneUI.TabSelectionHandler`.

This inner class is marked "public" due to a compiler bug.

`BasicTabbedPaneUI.TabSelectionHandler(BasicTabbedPaneUI)` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI.TabSelectionHandler`

`BasicTabbedPaneUI()` - Constructor for class `javax.swing.plaf.basic.BasicTabbedPaneUI`

`BasicTableHeaderUI` - class `javax.swing.plaf.basic.BasicTableHeaderUI`.

`BasicTableHeaderUI` implementation

`BasicTableHeaderUI.MouseInputHandler` - class `javax.swing.plaf.basic.BasicTableHeaderUI.MouseInputHandler`.

This inner class is marked "public" due to a compiler bug.

`BasicTableHeaderUI.MouseInputHandler(BasicTableHeaderUI)` - Constructor for class `javax.swing.plaf.basic.BasicTableHeaderUI.MouseInputHandler`

`BasicTableHeaderUI()` - Constructor for class `javax.swing.plaf.basic.BasicTableHeaderUI`

`BasicTableUI` - class `javax.swing.plaf.basic.BasicTableUI`.

`BasicTableUI` implementation

BasicTableUI.FocusHandler - class javax.swing.plaf.basic.BasicTableUI.FocusHandler.

This inner class is marked "public" due to a compiler bug.

BasicTableUI.FocusHandler(BasicTableUI) - Constructor for class
javax.swing.plaf.basic.BasicTableUI.FocusHandler

BasicTableUI.KeyHandler - class javax.swing.plaf.basic.BasicTableUI.KeyHandler.

This inner class is marked "public" due to a compiler bug.

BasicTableUI.KeyHandler(BasicTableUI) - Constructor for class
javax.swing.plaf.basic.BasicTableUI.KeyHandler

BasicTableUI.MouseInputHandler - class javax.swing.plaf.basic.BasicTableUI.MouseInputHandler.

This inner class is marked "public" due to a compiler bug.

BasicTableUI.MouseInputHandler(BasicTableUI) - Constructor for class
javax.swing.plaf.basic.BasicTableUI.MouseInputHandler

BasicTableUI() - Constructor for class javax.swing.plaf.basic.BasicTableUI

BasicTextAreaUI - class javax.swing.plaf.basic.BasicTextAreaUI.

Provides the look and feel for a plain text editor.

BasicTextAreaUI() - Constructor for class javax.swing.plaf.basic.BasicTextAreaUI

Constructs a new BasicTextAreaUI object.

BasicTextFieldUI - class javax.swing.plaf.basic.BasicTextFieldUI.

Basis of a look and feel for a JTextField.

BasicTextFieldUI() - Constructor for class javax.swing.plaf.basic.BasicTextFieldUI

Creates a new BasicTextFieldUI.

BasicTextPaneUI - class javax.swing.plaf.basic.BasicTextPaneUI.

Provides the look and feel for a styled text editor.

BasicTextPaneUI() - Constructor for class javax.swing.plaf.basic.BasicTextPaneUI

Creates a new BasicTextPaneUI.

BasicTextUI - class javax.swing.plaf.basic.BasicTextUI.

Basis of a text components look-and-feel.

BasicTextUI.BasicCaret - class javax.swing.plaf.basic.BasicTextUI.BasicCaret.

BasicTextUI.BasicCaret() - Constructor for class javax.swing.plaf.basic.BasicTextUI.BasicCaret

BasicTextUI.BasicHighlighter - class javax.swing.plaf.basic.BasicTextUI.BasicHighlighter.

BasicTextUI.BasicHighlighter() - Constructor for class javax.swing.plaf.basic.BasicTextUI.BasicHighlighter

BasicTextUI() - Constructor for class javax.swing.plaf.basic.BasicTextUI

Creates a new UI.

BasicToggleButtonUI - class javax.swing.plaf.basic.BasicToggleButtonUI.

BasicToggleButton implementation

BasicToggleButtonUI() - Constructor for class javax.swing.plaf.basic.BasicToggleButtonUI

BasicToolBarSeparatorUI - class javax.swing.plaf.basic.BasicToolBarSeparatorUI.

A Basic L&F implementation of ToolBarSeparatorUI.

The bitmask that indicates that a point lies to the left of this `Rectangle2D`.

`OUT_RIGHT` - Static variable in class `java.awt.geom.Rectangle2D`

The bitmask that indicates that a point lies to the right of this `Rectangle2D`.

`OUT_TOP` - Static variable in class `java.awt.geom.Rectangle2D`

The bitmask that indicates that a point lies above this `Rectangle2D`.

`outcode(double, double)` - Method in class `java.awt.Rectangle`

Determines where the specified coordinates lie with respect to this `Rectangle`.

`outcode(double, double)` - Method in class `java.awt.geom.Rectangle2D`

Determines where the specified coordinates lie with respect to this `Rectangle2D`.

`outcode(double, double)` - Method in class `java.awt.geom.Rectangle2D.Float`

Determines where the specified float coordinates lie with respect to this `Rectangle2D`.

`outcode(double, double)` - Method in class `java.awt.geom.Rectangle2D.Double`

Determines where the specified double coordinates lie with respect to this `Rectangle2D`.

`outcode(Point2D)` - Method in class `java.awt.geom.Rectangle2D`

Determines where the specified `Point2D` lies with respect to this `Rectangle2D`.

`OUTLINE_DRAG_MODE` - Static variable in class `javax.swing.JDesktopPane`

Used to indicate you wish to see only an outline of the item being dragged inside the desktop pane.

`OutOfMemoryError` - error `java.lang.OutOfMemoryError`.

Thrown when the Java Virtual Machine cannot allocate an object because it is out of memory, and no more memory could be made available by the garbage collector.

`OutOfMemoryError()` - Constructor for class `java.lang.OutOfMemoryError`

Constructs an `OutOfMemoryError` with no detail message.

`OutOfMemoryError(String)` - Constructor for class `java.lang.OutOfMemoryError`

Constructs an `OutOfMemoryError` with the specified detail message.

`outpixmap` - Variable in class `java.awt.image.ReplicateScaleFilter`

A byte array initialized with a size of `ReplicateScaleFilter.destWidth` and used to deliver a row of pixel data to the `ImageConsumer`.

`output(char[], int, int)` - Method in class `javax.swing.text.AbstractWriter`

The last stop in writing out content.

`output(char[], int, int)` - Method in class `javax.swing.text.html.HTMLWriter`

This method is overridden to map any character entities, such as `<` to `<`.

`OutputStream` - class `java.io.OutputStream`.

This abstract class is the superclass of all classes representing an output stream of bytes.

`OutputStream` - class `org.omg.CORBA.portable.OutputStream`.

`OutputStream` is the Java API for writing IDL types to CDR marshal streams.

`OutputStream` - class `org.omg.CORBA_2_3.portable.OutputStream`.

`OutputStream` provides interface for writing of all of the mapped IDL type to the stream.

`OutputStream()` - Constructor for class `java.io.OutputStream`

`OutputStream()` - Constructor for class `org.omg.CORBA.portable.OutputStream`

`OutputStream()` - Constructor for class `org.omg.CORBA_2_3.portable.OutputStream`

`OutputStreamWriter` - class `java.io.OutputStreamWriter`.

An `OutputStreamWriter` is a bridge from character streams to byte streams: Characters written to it are translated into bytes according to a specified character encoding.

`OutputStreamWriter(OutputStream)` - Constructor for class `java.io.OutputStreamWriter`

Create an `OutputStreamWriter` that uses the default character encoding.
[`OutputStreamWriter\(OutputStream, String\)`](#) - Constructor for class `java.io.OutputStreamWriter`
Create an `OutputStreamWriter` that uses the named character encoding.
[`outsideBorder`](#) - Variable in class `javax.swing.border.CompoundBorder`

[`OVER`](#) - Static variable in class `java.awt.dnd.DragSourceContext`
An `int` used by `updateCurrentCursor()` indicating that the `Cursor` is over a `DropTarget`.
[`OverlayLayout`](#) - class `javax.swing.OverlayLayout`.
A layout manager to arrange components over the top of each other.
[`OverlayLayout\(Container\)`](#) - Constructor for class `javax.swing.OverlayLayout`
Constructs a layout manager that performs overlay arrangement of the children.
[`ownDeletesAreVisible\(int\)`](#) - Method in interface `java.sql.DatabaseMetaData`
Indicates whether a result set's own deletes are visible.
[`owner`](#) - Variable in class `java.awt.datatransfer.Clipboard`

[`Owner`](#) - interface `java.security.acl.Owner`.
Interface for managing owners of Access Control Lists (ACLs) or ACL configurations.
[`ownInsertsAreVisible\(int\)`](#) - Method in interface `java.sql.DatabaseMetaData`
Indicates whether a result set's own inserts are visible.
[`ownUpdatesAreVisible\(int\)`](#) - Method in interface `java.sql.DatabaseMetaData`
Indicates whether a result set's own updates are visible.

[Overview](#) [Package](#) [Class](#) [Use](#) [Tree](#) [Deprecated](#) [Index](#) [Help](#)

*Java™ 2 Platform
Std. Ed. v1.3.1*

[PREV LETTER](#) [NEXT LETTER](#)

[FRAMES](#) [NO FRAMES](#)

[A](#) [B](#) [C](#) [D](#) [E](#) [F](#) [G](#) [H](#) [I](#) [J](#) [K](#) [L](#) [M](#) [N](#) [O](#) [P](#) [Q](#) [R](#) [S](#) [T](#) [U](#) [V](#) [W](#) [X](#) [Y](#) [Z](#) [_](#)

[Submit a bug or feature](#)

For further API reference and developer documentation, see [Java 2 SDK SE Developer Documentation](#). That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Java, Java 2D, and JDBC are trademarks or registered trademarks of Sun Microsystems, Inc. in the US and other countries.
Copyright 1993-2001 Sun Microsystems, Inc. 901 San Antonio Road
Palo Alto, California, 94303, U.S.A. All Rights Reserved.

G

GapContent - class javax.swing.text.GapContent.

An implementation of the AbstractDocument.Content interface implemented using a gapped buffer similar to that used by emacs.

GapContent() - Constructor for class javax.swing.text.GapContent

Creates a new GapContent object.

GapContent(int) - Constructor for class javax.swing.text.GapContent

Creates a new GapContent object, with the initial size specified.

gc() - Static method in class java.lang.System

Runs the garbage collector.

gc() - Method in class java.lang.Runtime

Runs the garbage collector.

gcd(BigInteger) - Method in class java.math.BigInteger

Returns a BigInteger whose value is the greatest common divisor of `abs(this)` and `abs(val)`.

GENERAL - Static variable in interface javax.swing.text.html.parser.DTDConstants

GENERAL_PUNCTUATION - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

GeneralPath - class java.awt.geom.GeneralPath.

The GeneralPath class represents a geometric path constructed from straight lines, and quadratic and cubic (Bézier) curves.

GeneralPath() - Constructor for class java.awt.geom.GeneralPath

Constructs a new GeneralPath object.

GeneralPath(int) - Constructor for class java.awt.geom.GeneralPath

Constructs a new GeneralPath object with the specified winding rule to control operations that require the interior of the path to be defined.

GeneralPath(int, int) - Constructor for class java.awt.geom.GeneralPath

Constructs a new GeneralPath object with the specified winding rule and the specified initial capacity to store path coordinates.

GeneralPath(Shape) - Constructor for class java.awt.geom.GeneralPath

Constructs a new GeneralPath object from an arbitrary Shape object.

GeneralSecurityException - exception java.security.GeneralSecurityException.

This is the general security exception class, which serves to group all the exception classes of the `java.security` package that extend from it.

GeneralSecurityException() - Constructor for class java.security.GeneralSecurityException

Constructs a GeneralSecurityException with no detail message.

GeneralSecurityException(String) - Constructor for class java.security.GeneralSecurityException

Constructs a GeneralSecurityException with the specified detail message.

generateCertificate(InputStream) - Method in class java.security.cert.CertificateFactory

Generates a certificate object and initializes it with the data read from the input stream `inStream`.

generateCertificates(InputStream) - Method in class java.security.cert.CertificateFactory

Returns a (possibly empty) collection view of the certificates read from the given input stream
inStream.

generateCRL(InputStream) - Method in class java.security.cert.CertificateFactory

Generates a certificate revocation list (CRL) object and initializes it with the data read from the input
stream inStream.

generateCRLs(InputStream) - Method in class java.security.cert.CertificateFactory

Returns a (possibly empty) collection view of the CRLs read from the given input stream inStream.

generateKeyPair() - Method in class java.security.KeyPairGeneratorSpi

Generates a key pair.

generateKeyPair() - Method in class java.security.KeyPairGenerator

Generates a key pair.

generateParameters() - Method in class java.security.AlgorithmParameterGenerator

Generates the parameters.

generatePrivate(KeySpec) - Method in class java.security.KeyFactory

Generates a private key object from the provided key specification (key material).

generatePublic(KeySpec) - Method in class java.security.KeyFactory

Generates a public key object from the provided key specification (key material).

generateSeed(int) - Method in class java.security.SecureRandom

Returns the given number of seed bytes, computed using the seed generation algorithm that this class
uses to seed itself.

genKeyPair() - Method in class java.security.KeyPairGenerator

Generates a key pair.

GEOMETRIC_SHAPES - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

GEORGIAN - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

GERMAN - Static variable in class java.util.Locale

Useful constant for language.

GERMANY - Static variable in class java.util.Locale

Useful constant for country.

get_any() - Method in interface org.omg.CORBA.DynAny

Retrieves the org.omg.CORBA.Any contained in this DynAny object.

get_boolean() - Method in interface org.omg.CORBA.DynAny

Retrieves the boolean contained in this DynAny object.

get_char() - Method in interface org.omg.CORBA.DynAny

Retrieves the char contained in this DynAny object.

get_codebase(Object) - Method in class org.omg.CORBA_2_3.portable.Delegate

Returns the codebase for object reference provided.

get_compact_typecode() - Method in class org.omg.CORBA.TypeCode

Strips out all optional name and member name fields, but leaves all alias typecodes intact.

get_current() - Method in class org.omg.CORBA.ORB

Deprecated. *use resolve_initial_references.*

get_default_context() - Method in class org.omg.CORBA.ORB

Gets the default Context object.

get_domain_managers(Object) - Method in class org.omg.CORBA.portable.Delegate

Retrieves the DomainManagers of this object.

get_domain_policy(int) - Method in interface org.omg.CORBA.DomainManagerOperations

This returns the policy of the specified type for objects in this domain.

get_double() - Method in interface org.omg.CORBA.DynAny

Retrieves the double contained in this DynAny object.

get_elements() - Method in interface org.omg.CORBA.DynArray

Returns the value of all the elements of this array.

get_elements() - Method in interface org.omg.CORBA.DynSequence

Returns the value of every element in this sequence.

get_float() - Method in interface org.omg.CORBA.DynAny

Retrieves the float contained in this DynAny object.

get_id() - Method in class org.omg.CORBA.StringValueHelper

get_id() - Method in class org.omg.CORBA.WStringValueHelper

get_id() - Method in interface org.omg.CORBA.portable.BoxedValueHelper

get_interface_def(Object) - Method in class org.omg.CORBA.portable.Delegate

Return an InterfaceDef for the object reference provided.

get_long() - Method in interface org.omg.CORBA.DynAny

Retrieves the int contained in this DynAny object.

get_longlong() - Method in interface org.omg.CORBA.DynAny

Retrieves the long contained in this DynAny object.

get_members() - Method in interface org.omg.CORBA.DynStruct

Returns an array containing all the members of the stored struct.

get_members() - Method in interface org.omg.CORBA.DynValue

Returns an array containing all the members of the value object stored in this DynValue.

get_next_response() - Method in class org.omg.CORBA.ORB

Gets the next Request instance for which a response has been received.

get_octet() - Method in interface org.omg.CORBA.DynAny

Retrieves the byte contained in this DynAny object.

get_policy(Object, int) - Method in class org.omg.CORBA.portable.Delegate

Returns the Policy object of the specified type which applies to this object.

get_primitive_tc(TCKind) - Method in class org.omg.CORBA.ORB

Retrieves the TypeCode object that represents the given primitive IDL type.

get_reference() - Method in interface org.omg.CORBA.DynAny

Retrieves the org.omg.CORBA.Other contained in this DynAny object.

get_response() - Method in class org.omg.CORBA.Request

Allows the user to access the response for the invocation triggered earlier with the send_deferred method.

get_service_information(short, ServiceInformationHolder) - Method in class org.omg.CORBA.ORB

See package comments regarding unimplemented features.

get_short() - Method in interface org.omg.CORBA.DynAny

Retrieves the short contained in this DynAny object.

get_string() - Method in interface org.omg.CORBA.DynAny

Retrieves the String contained in this DynAny object.

get_typecode() - Method in interface org.omg.CORBA.DynAny

Retrieves the org.omg.CORBA.TypeCode contained in this DynAny object.

get_ulong() - Method in interface org.omg.CORBA.DynAny

Retrieves the int contained in this DynAny object.

get_ulonglong() - Method in interface org.omg.CORBA.DynAny

Retrieves the long contained in this DynAny object.

get_ushort() - Method in interface org.omg.CORBA.DynAny

Retrieves the short contained in this DynAny object.

get_val() - Method in interface org.omg.CORBA.DynAny

Retrieves the java.io.Serializable object contained in this DynAny object.

get_value_def(String) - Method in class org.omg.CORBA_2_3.ORB

get_value() - Method in interface org.omg.CORBA.DynFixed

Returns the value of the fixed type represented in this DynFixed object.

get_values(String, int, String) - Method in class org.omg.CORBA.Context

Retrieves the NamedValue objects whose name field matches the given name or name pattern.

get_wchar() - Method in interface org.omg.CORBA.DynAny

Retrieves the char contained in this DynAny object.

get_wstring() - Method in interface org.omg.CORBA.DynAny

Retrieves the String contained in this DynAny object.

get() - Method in class java.lang.ThreadLocal

Returns the value in the calling thread's copy of this ThreadLocal variable.

get() - Method in class java.lang.InheritableThreadLocal

Returns the value in the calling thread's copy of this ThreadLocal variable.

get() - Method in class java.lang.ref.Reference

Returns this reference object's referent.

get() - Method in class java.lang.ref.PhantomReference

Returns this reference object's referent.

get() - Method in class java.lang.ref.SoftReference

Returns this reference object's referent.

get() - Method in class java.rmi.MarshalledObject

Returns a new copy of the contained marshalledobject.

get() - Method in class javax.naming.directory.BasicAttribute

Retrieves one of this attribute's values.

get() - Method in interface javax.naming.directory.Attribute

Retrieves one of this attribute's values.

get(int) - Method in class java.util.BitSet

Returns the value of the bit with the specified index.

get(int) - Method in class java.util.AbstractList

Returns the element at the specified position in this list.

get(int) - Method in class java.util.Vector

Returns the element at the specified position in this Vector.

get(int) - Method in class java.util.AbstractSequentialList

Returns the element at the specified position in this list.

get(int) - Method in class java.util.Calendar

Gets the value for a given time field.

get(int) - Method in class java.util.LinkedList

Returns the element at the specified position in this list.

get(int) - Method in interface java.util.List

Returns the element at the specified position in this list.
get(int) - Method in class java.util.ArrayList
Returns the element at the specified position in this list.
get(int) - Method in class javax.sound.midi.Track
Obtains the event at the specified index.
get(int) - Method in class javax.naming.Reference
Retrieves the address at index posn.
get(int) - Method in interface javax.naming.Name
Retrieves a component of this name.
get(int) - Method in class javax.naming.CompoundName
Retrieves a component of this compound name.
get(int) - Method in class javax.naming.CompositeName
Retrieves a component of this composite name.
get(int) - Method in class javax.naming.directory.BasicAttribute

get(int) - Method in interface javax.naming.directory.Attribute
Retrieves the attribute value from the ordered list of attribute values.
get(int) - Method in class javax.swing.DefaultListModel
Returns the element at the specified position in this list.
get(KeyStroke) - Method in class javax.swing.InputMap
Returns the binding for keyStroke, messaging the parent InputMap if the binding is not locally defined.
get(Object) - Method in class java.awt.RenderingHints
Returns the value to which the specified key is mapped.
get(Object) - Method in class java.lang.reflect.Field
Returns the value of the field represented by this Field, on the specified object.
get(Object) - Method in class java.util.Dictionary
Returns the value to which the key is mapped in this dictionary.
get(Object) - Method in class java.util.Hashtable
Returns the value to which the specified key is mapped in this hashtable.
get(Object) - Method in class java.util.AbstractMap
Returns the value to which this map maps the specified key.
get(Object) - Method in class java.util.WeakHashMap
Returns the value to which this map maps the specified key.
get(Object) - Method in class java.util.TreeMap
Returns the value to which this map maps the specified key.
get(Object) - Method in class java.util.HashMap
Returns the value to which this map maps the specified key.
get(Object) - Method in interface java.util.Map
Returns the value to which this map maps the specified key.
get(Object) - Method in class java.util.jar.Attributes
Returns the value of the specified attribute name, or null if the attribute name was not found.
get(Object) - Method in class javax.swing.ActionMap
Returns the binding for key, messaging the parent ActionMap if the binding is not locally defined.
get(Object) - Method in class javax.swing.UIDefaults
Returns the value for key.
get(Object) - Static method in class javax.swing.UIManager
Returns an object from the defaults table.

get(Object, int) - Static method in class java.lang.reflect.Array

Returns the value of the indexed component in the specified array object.

get(String) - Method in class javax.accessibility.AccessibleRelationSet

Returns the relation that matches the specified key.

get(String) - Method in class javax.naming.Reference

Retrieves the first address that has the address type 'addrType'.

get(String) - Method in interface javax.naming.directory.Attributes

Retrieves the attribute with the given attribute id from the attribute set.

get(String) - Method in class javax.naming.directory.BasicAttributes

get(String, boolean) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named boolean field from the persistent field.

get(String, byte) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named byte field from the persistent fields.

get(String, char) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named char field from the persistent fields.

get(String, double) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named double field from the persistent field.

get(String, float) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named float field from the persistent fields.

get(String, int) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named int field from the persistent fields.

get(String, long) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named long field from the persistent fields.

get(String, Object) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named Object field from the persistent field.

get(String, short) - Method in class java.io.ObjectInputStream.GetField

Get the value of the named short field from the persistent fields.

get2DigitYearStart() - Method in class java.text.SimpleDateFormat

Returns the beginning date of the 100-year period 2-digit years are interpreted as being within.

getAbsolutePath() - Method in class java.io.File

Returns the absolute form of this abstract pathname.

getAbsolutePath() - Method in class java.io.File

Returns the absolute pathname string of this abstract pathname.

getAccelerator() - Method in class javax.swing.JMenuItem

Returns the KeyStroke which serves as an accelerator for the menu item.

getAcceleratorForeground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getAcceleratorForeground() - Method in class javax.swing.plaf.metal.MetalTheme

getAcceleratorSelectedForeground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getAcceleratorSelectedForeground() - Method in class javax.swing.plaf.metal.MetalTheme

getAcceleratorString() - Method in class javax.swing.plaf.metal.MetalToolTipUI

getAcceptAllFileFilter() - Method in class javax.swing.JFileChooser

Returns the AcceptAll file filter.

[getAcceptAllFileFilter\(JFileChooser\)](#) - Method in class javax.swing.plaf.[FileChooserUI](#)

[getAcceptAllFileFilter\(JFileChooser\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

Returns the default accept all file filter

[getAcceptAllFileFilter\(JFileChooser\)](#) - Method in class javax.swing.plaf.multi.[MultiFileChooserUI](#)

Call getAcceptAllFileFilter on each UI handled by this MultiUI.

[getAccessibleAction\(\)](#) - Method in class java.awt.MenuItem.[AccessibleAWTMenuItem](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class java.awt.Checkbox.[AccessibleAWTCheckbox](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class java.awt.Choice.[AccessibleAWTChoice](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class java.awt.Button.[AccessibleAWTButton](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class java.awt.CheckboxMenuItem.[AccessibleAWTCheckboxMenuItem](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class javax.accessibility.[AccessibleContext](#)

Gets the AccessibleAction associated with this object that supports one or more actions.

[getAccessibleAction\(\)](#) - Method in class javax.swing.AbstractButton.[AccessibleAbstractButton](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class javax.swing.JComboBox.[AccessibleJComboBox](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class javax.swing.JList.[AccessibleJList](#).[AccessibleJListChild](#)

[getAccessibleAction\(\)](#) - Method in class javax.swing.JTree.[AccessibleJTree](#).[AccessibleJTreeNode](#)

Get the AccessibleAction associated with this object.

[getAccessibleAction\(\)](#) - Method in class javax.swing.JTable.[AccessibleJTable](#).[AccessibleJTableCell](#)

Gets the AccessibleAction associated with this object if one exists.

[getAccessibleAction\(\)](#) - Method in class

javax.swing.table.JTableHeader.[AccessibleJTableHeader](#).[AccessibleJTableHeaderEntry](#)

[getAccessibleActionAnchor\(int\)](#) - Method in class javax.accessibility.[AccessibleHyperlink](#)

Returns an object that represents the link anchor, as appropriate for that link.

[getAccessibleActionAnchor\(int\)](#) - Method in class

javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.[HTMLLink](#)

Return an object that represents the link anchor, as appropriate for that link.

[getAccessibleActionCount\(\)](#) - Method in class java.awt.MenuItem.[AccessibleAWTMenuItem](#)

Returns the number of Actions available in this object.

[getAccessibleActionCount\(\)](#) - Method in class java.awt.Checkbox.[AccessibleAWTCheckbox](#)

Returns the number of Actions available in this object.

[getAccessibleActionCount\(\)](#) - Method in class java.awt.Choice.[AccessibleAWTChoice](#)

Returns the number of accessible actions available in this object If there are more than one, the first one is considered the "default" action of the object.

[getAccessibleActionCount\(\)](#) - Method in class java.awt.Button.[AccessibleAWTButton](#)

Returns the number of Actions available in this object.

[getAccessibleActionCount\(\)](#) - Method in class

java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem

Returns the number of Actions available in this object.

getAccessibleActionCount() - Method in class javax.accessibility.AccessibleHyperlink

Returns the number of accessible actions available in this Link If there are more than one, the first one is NOT considered the "default" action of this LINK object (e.g.

getAccessibleActionCount() - Method in interface javax.accessibility.AccessibleAction

Returns the number of accessible actions available in this object If there are more than one, the first one is considered the "default" action of the object.

getAccessibleActionCount() - Method in class javax.swing.AbstractButton.AccessibleAbstractButton

Returns the number of Actions available in this object.

getAccessibleActionCount() - Method in class

javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.HTMLLink

Returns the number of accessible actions available in this Link If there are more than one, the first one is NOT considered the "default" action of this LINK object (e.g.

getAccessibleActionCount() - Method in class javax.swing.JComboBox.AccessibleJComboBox

Returns the number of Actions available in this object.

getAccessibleActionCount() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Returns the number of accessible actions available in this tree node.

getAccessibleActionDescription(int) - Method in class java.awt.MenuItem.AccessibleAWTMenuItem

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class java.awt.Checkbox.AccessibleAWTCheckbox

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class java.awt.Choice.AccessibleAWTChoice

Returns a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class java.awt.Button.AccessibleAWTButton

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class

java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class javax.accessibility.AccessibleHyperlink

Returns a String description of this particular link action.

getAccessibleActionDescription(int) - Method in interface javax.accessibility.AccessibleAction

Returns a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class

javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.HTMLLink

Return a String description of this particular link action.

getAccessibleActionDescription(int) - Method in class javax.swing.JComboBox.AccessibleJComboBox

Return a description of the specified action of the object.

getAccessibleActionDescription(int) - Method in class

javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Return a description of the specified action of the tree node.

getAccessibleActionObject(int) - Method in class javax.accessibility.AccessibleHyperlink

Returns an object that represents the link action, as appropriate for that link.

getAccessibleActionObject(int) - Method in class

javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.HTMLLink

Returns a URL object that represents the link.

[getAccessibleAt\(Component, Point\)](#) - Static method in class [javax.swing.SwingUtilities](#)

Returns the Accessible child contained at the local coordinate Point, if one exists.

[getAccessibleAt\(int, int\)](#) - Method in interface [javax.accessibility.AccessibleTable](#)

Returns the Accessible at a specified row and column in the table.

[getAccessibleAt\(int, int\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)

[getAccessibleAt\(Point\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [java.awt.Container.AccessibleAWTContainer](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [java.awt.List.AccessibleAWTList](#)

Returns the Accessible child contained at the local coordinate Point, if one exists.

[getAccessibleAt\(Point\)](#) - Method in class [java.awt.List.AccessibleAWTList.AccessibleAWTListChild](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in interface [javax.accessibility.AccessibleComponent](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JTabbedPane.AccessibleJTabbedPane](#)

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JList.AccessibleJList](#)

Returns the Accessible child contained at the local coordinate Point, if one exists.

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JTree.AccessibleJTree](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)

[getAccessibleAt\(Point\)](#) - Method in class [javax.swing.table.JTableHeader.AccessibleJTableHeader](#)

Returns the Accessible child, if one exists, contained at the local coordinate Point.

[getAccessibleAt\(Point\)](#) - Method in class

[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleCaption\(\)](#) - Method in interface [javax.accessibility.AccessibleTable](#)

Returns the caption for the table.

[getAccessibleCaption\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)

Returns the caption for the table.

[getAccessibleChild\(Component, int\)](#) - Static method in class [javax.swing.SwingUtilities](#)

Return the nth Accessible child of the object.

[getAccessibleChild\(int\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)

Return the nth Accessible child of the object.

[getAccessibleChild\(int\)](#) - Method in class [java.awt.Container.AccessibleAWTContainer](#)

Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class java.awt.[MenuComponent.AccessibleAWTMenuComponent](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class java.awt.[List.AccessibleAWTList](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class java.awt.[List.AccessibleAWTList.AccessibleAWTListChild](#)
 Return the specified Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.accessibility.[AccessibleContext](#)
 Returns the specified Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JComponent.AccessibleJComponent](#)
 Returns the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JTabbedPane.AccessibleJTabbedPane](#)
 Return the specified Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JMenu.AccessibleJMenu](#)
 Returns the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JComboBox.AccessibleJComboBox](#)
 Returns the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JList.AccessibleJList](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JList.AccessibleJList.AccessibleJListChild](#)

[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JTree.AccessibleJTree](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JTree.AccessibleJTree.AccessibleJTreeNode](#)
 Return the specified Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[JTable.AccessibleJTable.AccessibleJTableCell](#)
 Return the specified Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.[ImageIcon.AccessibleImageIcon](#)
 Returns the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class javax.swing.table.[JTableHeader.AccessibleJTableHeader](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(int\)](#) - Method in class
 javax.swing.table.[JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.[ComponentUI](#)
 Return the nth Accessible child of the object.
[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.multi.[MultiListUI](#)
 Call [getAccessibleChild](#) on each UI handled by this MultiUI.
[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.multi.[MultiSeparatorUI](#)
 Call [getAccessibleChild](#) on each UI handled by this MultiUI.
[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.multi.[MultiLabelUI](#)
 Call [getAccessibleChild](#) on each UI handled by this MultiUI.
[getAccessibleChild\(JComponent, int\)](#) - Method in class javax.swing.plaf.multi.[MultiPopupMenuUI](#)

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiPanelUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiScrollBarUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiTextUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiComboBoxUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiTableHeaderUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiFileChooserUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiColorChooserUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiTreeUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiViewportUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiTabbedPaneUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiProgressBarUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiScrollPaneUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiOptionPaneUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiSplitPaneUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiButtonUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiToolBarUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiSliderUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiDesktopPaneUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiTableUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiDesktopIconUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiMenuItemUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiInternalFrameUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.
`getAccessibleChild(JComponent, int)` - Method in class `javax.swing.plaf.multi.MultiToolTipUI`

Call `getAccessibleChild` on each UI handled by this `MultiUI`.

getAccessibleChild(JComponent, int) - Method in class javax.swing.plaf.multi.MultiMenuBarUI
 Call getAccessibleChild on each UI handled by this MultiUI.

getAccessibleChildrenCount() - Method in class java.awt.Component.AccessibleAWTComponent
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class java.awt.Container.AccessibleAWTContainer
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class java.awt.List.AccessibleAWTList
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild
 Returns the number of accessible children of the object.

getAccessibleChildrenCount() - Method in class javax.accessibility.AccessibleContext
 Returns the number of accessible children of the object.

getAccessibleChildrenCount() - Method in class javax.swing.JComponent.AccessibleJComponent
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JTabbedPane.AccessibleJTabbedPane
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JMenu.AccessibleJMenu
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JComboBox.AccessibleJComboBox
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JList.AccessibleJList
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getAccessibleChildrenCount() - Method in class javax.swing.JTree.AccessibleJTree
 Returns the number of top-level children nodes of this JTree.

getAccessibleChildrenCount() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JTable.AccessibleJTable
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.ImageIcon.AccessibleImageIcon
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class javax.swing.table.JTableHeader.AccessibleJTableHeader
 Returns the number of accessible children in the object.

getAccessibleChildrenCount() - Method in class
 javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getAccessibleChildrenCount(Component) - Static method in class javax.swing.SwingUtilities
 Returns the number of accessible children in the object.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.ComponentUI
 Returns the number of accessible children in the object.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiListUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiSeparatorUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiLabelUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiPopupMenuUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiPanelUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollBarUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiTextUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiComboBoxUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiTableHeaderUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiFileChooserUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiColorChooserUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiTreeUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiViewportUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiTabbedPaneUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiProgressBarUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollPaneUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiOptionPaneUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiSplitPaneUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiButtonUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiToolBarUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiSliderUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiDesktopPaneUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiTableUI
 Call getAccessibleChildrenCount on each UI handled by this MultiUI.

getAccessibleChildrenCount(JComponent) - Method in class javax.swing.plaf.multi.MultiDesktopIconUI

Call `getAccessibleChildrenCount` on each UI handled by this `MultiUI`.
`getAccessibleChildrenCount(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuItemUI`
 Call `getAccessibleChildrenCount` on each UI handled by this `MultiUI`.
`getAccessibleChildrenCount(JComponent)` - Method in class `javax.swing.plaf.multi.MultiInternalFrameUI`
 Call `getAccessibleChildrenCount` on each UI handled by this `MultiUI`.
`getAccessibleChildrenCount(JComponent)` - Method in class `javax.swing.plaf.multi.MultiToolTipUI`
 Call `getAccessibleChildrenCount` on each UI handled by this `MultiUI`.
`getAccessibleChildrenCount(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuBarUI`
 Call `getAccessibleChildrenCount` on each UI handled by this `MultiUI`.
`getAccessibleColumnAt(int)` - Method in class `javax.swing.JTable.AccessibleJTable`

`getAccessibleColumnCount()` - Method in interface `javax.accessibility.AccessibleTable`
 Returns the number of columns in the table.
`getAccessibleColumnCount()` - Method in class `javax.swing.JTable.AccessibleJTable`

`getAccessibleColumnDescription(int)` - Method in interface `javax.accessibility.AccessibleTable`
 Returns the description text of the specified column in the table.
`getAccessibleColumnDescription(int)` - Method in class `javax.swing.JTable.AccessibleJTable`
 Return the description of the specified column in the table.
`getAccessibleColumnExtentAt(int, int)` - Method in interface `javax.accessibility.AccessibleTable`
 Returns the number of columns occupied by the Accessible at a specified row and column in the table.
`getAccessibleColumnExtentAt(int, int)` - Method in class `javax.swing.JTable.AccessibleJTable`
 Returns the number of columns occupied by the Accessible at a given (row, column)
`getAccessibleColumnHeader()` - Method in interface `javax.accessibility.AccessibleTable`
 Returns the column headers as an `AccessibleTable`.
`getAccessibleColumnHeader()` - Method in class `javax.swing.JTable.AccessibleJTable`
 Return the column headers as an `AccessibleTable`.
`getAccessibleComponent()` - Method in class `java.awt.Component.AccessibleAWTComponent`
 Get the `AccessibleComponent` associated with this object if one exists.
`getAccessibleComponent()` - Method in class `java.awt.MenuComponent.AccessibleAWTMenuComponent`
 Get the `AccessibleComponent` associated with this object if one exists.
`getAccessibleComponent()` - Method in class `javax.accessibility.AccessibleContext`
 Gets the `AccessibleComponent` associated with this object that has a graphical representation.
`getAccessibleComponent()` - Method in class `javax.swing.JList.AccessibleJList.AccessibleJListChild`
 Get the `AccessibleComponent` associated with this object.
`getAccessibleComponent()` - Method in class `javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode`
 Get the `AccessibleComponent` associated with this object.
`getAccessibleComponent()` - Method in class `javax.swing.JTable.AccessibleJTable.AccessibleJTableCell`
 Gets the `AccessibleComponent` associated with this object if one exists.
`getAccessibleComponent()` - Method in class
`javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry`
 Get the `AccessibleComponent` associated with this object.
`getAccessibleContext()` - Method in class `java.applet.Applet`
 Gets the `AccessibleContext` associated with this `Applet`.
`getAccessibleContext()` - Method in class `java.awt.Component`
 Get the `AccessibleContext` associated with this `Component`
`getAccessibleContext()` - Method in class `java.awt.Panel`

Gets the AccessibleContext associated with this Panel.
getAccessibleContext() - Method in class java.awt.ScrollPane

Gets the AccessibleContext associated with this ScrollPane.
getAccessibleContext() - Method in class java.awt.Scrollbar

Gets the AccessibleContext associated with this Scrollbar.
getAccessibleContext() - Method in class java.awt.Canvas

Gets the AccessibleContext associated with this Canvas.
getAccessibleContext() - Method in class java.awt.MenuComponent

Get the AccessibleContext associated with this MenuComponent
getAccessibleContext() - Method in class java.awt.MenuItem

Gets the AccessibleContext associated with this MenuItem.
getAccessibleContext() - Method in class java.awt.Menu

Gets the AccessibleContext associated with this Menu.
getAccessibleContext() - Method in class java.awt.Checkbox

Gets the AccessibleContext associated with this Checkbox.
getAccessibleContext() - Method in class java.awt.Window

Gets the AccessibleContext associated with this Window.
getAccessibleContext() - Method in class java.awt.Dialog

Gets the AccessibleContext associated with this Dialog.
getAccessibleContext() - Method in class java.awt.MenuBar

Gets the AccessibleContext associated with this MenuBar.
getAccessibleContext() - Method in class java.awt.List

Gets the AccessibleContext associated with this List.
getAccessibleContext() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Gets the AccessibleContext for this object.
getAccessibleContext() - Method in class java.awt.TextComponent

Gets the AccessibleContext associated with this TextComponent.
getAccessibleContext() - Method in class java.awt.PopupMenu

Gets the AccessibleContext associated with this PopupMenu.
getAccessibleContext() - Method in class java.awt.Choice

Gets the AccessibleContext associated with this Choice.
getAccessibleContext() - Method in class java.awt.Frame

Gets the AccessibleContext associated with this Frame.
getAccessibleContext() - Method in class java.awt.Label

Gets the AccessibleContext associated with this Label.
getAccessibleContext() - Method in class java.awt.TextField

Gets the AccessibleContext associated with this TextField.
getAccessibleContext() - Method in class java.awt.Button

Gets the AccessibleContext associated with this Button.
getAccessibleContext() - Method in class java.awt.CheckboxMenuItem

Gets the AccessibleContext associated with this CheckboxMenuItem.
getAccessibleContext() - Method in class java.awt.TextArea

Gets the AccessibleContext associated with this TextArea.
getAccessibleContext() - Method in interface javax.accessibility.Accessible

Returns the AccessibleContext associated with this object.
getAccessibleContext() - Method in class javax.swing.JComponent

Gets the AccessibleContext associated with this JComponent.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JEditorPane
Gets the AccessibleContext associated with this JEditorPane.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JViewport
Gets the AccessibleContext associated with this JViewport.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JTabbedPane
Gets the AccessibleContext associated with this JTabbedPane.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JMenuItem
Gets the AccessibleContext associated with this JMenuItem.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JCheckBoxMenuItem
Gets the AccessibleContext associated with this JCheckBoxMenuItem.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JLayeredPane
Gets the AccessibleContext associated with this JLayeredPane.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JToggleButton
Gets the AccessibleContext associated with this JToggleButton.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JCheckBox
Gets the AccessibleContext associated with this JCheckBox.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JTextField
Gets the AccessibleContext associated with this JTextField.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JPasswordField
Gets the AccessibleContext associated with this JPasswordField.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JOptionPane
Gets the AccessibleContext associated with this JOptionPane.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JMenu
Gets the AccessibleContext associated with this JMenu.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JColorChooser
Gets the AccessibleContext associated with this JColorChooser.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JButton
Gets the AccessibleContext associated with this JButton.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JPopupMenu
Gets the AccessibleContext associated with this JPopupMenu.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JSeparator
Gets the AccessibleContext associated with this JSeparator.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JWindow
Gets the AccessibleContext associated with this JWindow.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JApplet
Gets the AccessibleContext associated with this JApplet.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JComboBox
Gets the AccessibleContext associated with this JComboBox.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JList
Gets the AccessibleContext associated with this JList.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild
Get the AccessibleContext for this object.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JToolTip
Gets the AccessibleContext associated with this JToolTip.

[getAccessibleContext\(\)](#) - Method in class javax.swing.CellRendererPane
Gets the AccessibleContext associated with this CellRendererPane.

[getAccessibleContext\(\)](#) - Method in class javax.swing.JInternalFrame

Gets the AccessibleContext associated with this JInternalFrame.
getAccessibleContext() - Method in class javax.swing.JInternalFrame.JDesktopIcon

Gets the AccessibleContext associated with this JDesktopIcon.
getAccessibleContext() - Method in class javax.swing.JPanel

Gets the AccessibleContext associated with this JPanel.
getAccessibleContext() - Method in class javax.swing.JFrame

Gets the AccessibleContext associated with this JFrame.
getAccessibleContext() - Method in class javax.swing.JSplitPane

Gets the AccessibleContext associated with this JSplitPane.
getAccessibleContext() - Method in class javax.swing.JTree

Gets the AccessibleContext associated with this JTree.
getAccessibleContext() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Get the AccessibleContext associated with this tree node.
getAccessibleContext() - Method in class javax.swing.JTable

Gets the AccessibleContext associated with this JTable.
getAccessibleContext() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Gets the AccessibleContext associated with this component.
getAccessibleContext() - Method in class javax.swing.JLabel

Get the AccessibleContext of this object
getAccessibleContext() - Method in class javax.swing.JFileChooser

Gets the AccessibleContext associated with this JFileChooser.
getAccessibleContext() - Method in class javax.swing.JDesktopPane

Gets the AccessibleContext associated with this JDesktopPane.
getAccessibleContext() - Method in class javax.swing.JRadioButton

Gets the AccessibleContext associated with this JRadioButton.
getAccessibleContext() - Method in class javax.swing.JToolBar

Gets the AccessibleContext associated with this JToolBar.
getAccessibleContext() - Method in class javax.swing.JMenuBar

Gets the AccessibleContext associated with this JMenuBar.
getAccessibleContext() - Method in class javax.swing.ImageIcon

Gets the AccessibleContext associated with this ImageIcon.
getAccessibleContext() - Method in class javax.swing.JRadioButtonMenuItem

Gets the AccessibleContext associated with this JRadioButtonMenuItem.
getAccessibleContext() - Method in class javax.swing.JTextArea

Gets the AccessibleContext associated with this JTextArea.
getAccessibleContext() - Method in class javax.swing.Box

Gets the AccessibleContext associated with this Box.
getAccessibleContext() - Method in class javax.swing.Box.Filler

Gets the AccessibleContext associated with this Box.Filler.
getAccessibleContext() - Method in class javax.swing.JScrollPane

Gets the AccessibleContext associated with this JScrollPane.
getAccessibleContext() - Method in class javax.swing.JScrollBar

Gets the AccessibleContext associated with this JScrollBar.
getAccessibleContext() - Method in class javax.swing.JProgressBar

Gets the AccessibleContext associated with this JProgressBar.
getAccessibleContext() - Method in class javax.swing.JRootPane

Gets the AccessibleContext associated with this JRootPane.

[getAccessibleContext\(\)](#) - Method in class [javax.swing.JDialog](#)

Gets the AccessibleContext associated with this JDialog.

[getAccessibleContext\(\)](#) - Method in class [javax.swing.JSlider](#)

Gets the AccessibleContext associated with this JSlider.

[getAccessibleContext\(\)](#) - Method in class [javax.swing.table.JTableHeader](#)

Gets the AccessibleContext associated with this JTableHeader.

[getAccessibleContext\(\)](#) - Method in class

[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

Get the AccessibleContext associated with this object.

[getAccessibleContext\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)

Gets the AccessibleContext associated with this JTextComponent.

[getAccessibleDescription\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)

Get the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)

Get the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the accessibleDescription property of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JComponent.AccessibleJComponent](#)

Gets the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JEditorPane.AccessibleJEditorPane](#)

Gets the accessibleDescription property of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JToolTip.AccessibleJToolTip](#)

Get the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

Get the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)

Gets the accessible description of this object.

[getAccessibleDescription\(\)](#) - Method in class

[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleIcon\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the AccessibleIcons associated with an object that has one or more associated icons

[getAccessibleIcon\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)

Get the AccessibleIcons associated with this object if one or more exist.

[getAccessibleIcon\(\)](#) - Method in class [javax.swing.JLabel.AccessibleJLabel](#)

Get the AccessibleIcons associated with this object if one or more exist.

[getAccessibleIconDescription\(\)](#) - Method in interface [javax.accessibility.AccessibleIcon](#)

Gets the description of the icon.

[getAccessibleIconDescription\(\)](#) - Method in class [javax.swing.ImageIcon.AccessibleImageIcon](#)

Gets the description of the icon.

[getAccessibleIconHeight\(\)](#) - Method in interface [javax.accessibility.AccessibleIcon](#)

Gets the height of the icon

[getAccessibleIconHeight\(\)](#) - Method in class [javax.swing.ImageIcon.AccessibleImageIcon](#)

Gets the height of the icon.

[getAccessibleIconWidth\(\)](#) - Method in interface [javax.accessibility.AccessibleIcon](#)

Gets the width of the icon
[getAccessibleIconWidth\(\)](#) - Method in class javax.swing.ImageIcon.AccessibleImageIcon
 Gets the width of the icon.

[getAccessibleIndexAt\(int, int\)](#) - Method in class javax.swing.JTable.AccessibleJTable
 Returns the index at a given (row, column) in the table

[getAccessibleIndexInParent\(\)](#) - Method in class java.awt.Component.AccessibleAWTComponent
 Get the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
 Get the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild
 Get the 0-based index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.accessibility.AccessibleContext
 Gets the 0-based index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.JTree.AccessibleJTree
 Get the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode
 Get the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
 Gets the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.ImageIcon.AccessibleImageIcon
 Gets the index of this object in its accessible parent.

[getAccessibleIndexInParent\(\)](#) - Method in class javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

[getAccessibleIndexInParent\(Component\)](#) - Static method in class javax.swing.SwingUtilities
 Get the index of this object in its accessible parent.

[getAccessibleName\(\)](#) - Method in class java.awt.Component.AccessibleAWTComponent
 Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
 Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class java.awt.MenuItem.AccessibleAWTMenuItem
 Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class java.awt.Label.AccessibleAWTLabel
 Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class java.awt.Button.AccessibleAWTButton
 Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class javax.accessibility.AccessibleContext
 Gets the accessibleName property of this object.

[getAccessibleName\(\)](#) - Method in class javax.swing.JComponent.AccessibleJComponent
 Gets the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton
 Returns the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

[getAccessibleName\(\)](#) - Method in class javax.swing.JInternalFrame.AccessibleJInternalFrame

Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.JFrame.AccessibleJFrame](#)

Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)

Gets the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.JLabel.AccessibleJLabel](#)

Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.JDialog.AccessibleJDialog](#)

Get the accessible name of this object.

[getAccessibleName\(\)](#) - Method in class [javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleParent\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)

Get the Accessible parent of this object.

[getAccessibleParent\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)

Get the Accessible parent of this object.

[getAccessibleParent\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the Accessible parent of this object.

[getAccessibleParent\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

Get the Accessible parent of this object.

[getAccessibleParent\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)

Gets the Accessible parent of this object.

[getAccessibleParent\(\)](#) - Method in class [javax.swing.ImageIcon.AccessibleImageIcon](#)

Gets the Accessible parent of this object.

[getAccessibleRelationSet\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the AccessibleRelationSet associated with an object

[getAccessibleRelationSet\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)

Get the AccessibleRelationSet associated with this object if one exists.

[getAccessibleRelationSet\(\)](#) - Method in class [javax.swing.JLabel.AccessibleJLabel](#)

Get the AccessibleRelationSet associated with this object if one exists.

[getAccessibleRole\(\)](#) - Method in class [java.applet.Applet.AccessibleApplet](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.Panel.AccessibleAWTPanel](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.ScrollPane.AccessibleAWTScrollPane](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.Scrollbar.AccessibleAWTScrollBar](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.Canvas.AccessibleAWTCanvas](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)

Get the role of this object.

[getAccessibleRole\(\)](#) - Method in class [java.awt.MenuItem.AccessibleAWTMenuItem](#)

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Menu.AccessibleAWTMenu

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Checkbox.AccessibleAWTCheckbox

Get the role of this object.
getAccessibleRole() - Method in class java.awt.MenuBar.AccessibleAWTMenuBar

Get the role of this object.
getAccessibleRole() - Method in class java.awt.List.AccessibleAWTList

Get the role of this object.
getAccessibleRole() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Get the role of this object.
getAccessibleRole() - Method in class java.awt.TextComponent.AccessibleAWTTextComponent

Gets the role of this object.
getAccessibleRole() - Method in class java.awt.PopupMenu.AccessibleAWTPopupMenu

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Window.AccessibleAWTWindow

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Dialog.AccessibleAWTDialog

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Choice.AccessibleAWTChoice

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Frame.AccessibleAWTFrame

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Label.AccessibleAWTLabel

Get the role of this object.
getAccessibleRole() - Method in class java.awt.Button.AccessibleAWTButton

Get the role of this object.
getAccessibleRole() - Method in class java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem

Get the role of this object.
getAccessibleRole() - Method in class javax.accessibility.AccessibleContext

Gets the role of this object.
getAccessibleRole() - Method in class javax.swing.JComponent.AccessibleJComponent

Gets the role of this object.
getAccessibleRole() - Method in class javax.swing.JViewport.AccessibleJViewport

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JTabbedPane.AccessibleJTabbedPane

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JMenuItem.AccessibleJMenuItem

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JCheckBoxMenuItem.AccessibleJCheckBoxMenuItem

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JLayeredPane.AccessibleJLayeredPane

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JToggleButton.AccessibleJToggleButton

Get the role of this object.
getAccessibleRole() - Method in class javax.swing.JCheckBox.AccessibleJCheckBox

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JPasswordField.AccessibleJPasswordField

Gets the role of this object.

getAccessibleRole() - Method in class javax.swing.JOptionPane.AccessibleJOptionPane

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JMenu.AccessibleJMenu

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JColorChooser.AccessibleJColorChooser

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JButton.AccessibleJButton

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JPopupMenu.AccessibleJPopupMenu

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JComboBox.AccessibleJComboBox

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JList.AccessibleJList

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getAccessibleRole() - Method in class javax.swing.JToolTip.AccessibleJToolTip

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JSeparator.AccessibleJSeparator

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.CellRendererPane.AccessibleCellRendererPane

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JInternalFrame.AccessibleJInternalFrame

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JInternalFrame.JDesktopIcon.AccessibleJDesktopIcon

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JPanel.AccessibleJPanel

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JSplitPane.AccessibleJSplitPane

Gets the role of this object.

getAccessibleRole() - Method in class javax.swing.JTree.AccessibleJTree

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JTable.AccessibleJTable

Gets the role of this object.

getAccessibleRole() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Gets the role of this object.

getAccessibleRole() - Method in class javax.swing.JFileChooser.AccessibleJFileChooser

Gets the role of this object.

getAccessibleRole() - Method in class javax.swing.JDesktopPane.AccessibleJDesktopPane

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JRadioButton.AccessibleJRadioButton

Get the role of this object.

getAccessibleRole() - Method in class javax.swing.JLabel.AccessibleJLabel

Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JToolBar.AccessibleJToolBar](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JMenuBar.AccessibleJMenuBar](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[ImageIcon.AccessibleImageIcon](#)
 Gets the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JRadioButtonMenuItem.AccessibleJRadioButtonMenuItem](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[Box.Filler.AccessibleBoxFiller](#)
 Gets the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[Box.AccessibleBox](#)
 Gets the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JScrollPane.AccessibleJScrollPane](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JScrollBar.AccessibleJScrollBar](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JProgressBar.AccessibleJProgressBar](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JRootPane.AccessibleJRootPane](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.[JSlider.AccessibleJSlider](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class javax.swing.table.[JTableHeader.AccessibleJTableHeader](#)
 Get the role of this object.
[getAccessibleRole\(\)](#) - Method in class
 javax.swing.table.[JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleRole\(\)](#) - Method in class javax.swing.text.[JTextComponent.AccessibleJTextComponent](#)
 Gets the role of this object.
[getAccessibleRowAtIndex\(int\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)

[getAccessibleRowCount\(\)](#) - Method in interface javax.accessibility.[AccessibleTable](#)
 Returns the number of rows in the table.
[getAccessibleRowCount\(\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)

[getAccessibleRowDescription\(int\)](#) - Method in interface javax.accessibility.[AccessibleTable](#)
 Returns the description of the specified row in the table.
[getAccessibleRowDescription\(int\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)
 Return the description of the specified row in the table.
[getAccessibleRowExtentAt\(int, int\)](#) - Method in interface javax.accessibility.[AccessibleTable](#)
 Returns the number of rows occupied by the Accessible at a specified row and column in the table.
[getAccessibleRowExtentAt\(int, int\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)
 Returns the number of rows occupied by the Accessible at a specified row and column in the table.
[getAccessibleRowHeader\(\)](#) - Method in interface javax.accessibility.[AccessibleTable](#)
 Returns the row headers as an AccessibleTable.
[getAccessibleRowHeader\(\)](#) - Method in class javax.swing.[JTable.AccessibleJTable](#)

Return the row headers as an AccessibleTable.

[getAccessibleSelection\(\)](#) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
Get the AccessibleSelection associated with this object which allows its Accessible children to be selected.

[getAccessibleSelection\(\)](#) - Method in class java.awt.List.AccessibleAWTList
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.accessibility.AccessibleContext
Gets the AccessibleSelection associated with this object which allows its Accessible children to be selected.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JTabbedPane.AccessibleJTabbedPane
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JMenu.AccessibleJMenu
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JComboBox.AccessibleJComboBox
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JList.AccessibleJList
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JTree.AccessibleJTree
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode
Get the AccessibleSelection associated with this object if one exists.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JTable.AccessibleJTable
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
Gets the AccessibleSelection associated with this object if one exists.

[getAccessibleSelection\(\)](#) - Method in class javax.swing.JMenuBar.AccessibleJMenuBar
Get the AccessibleSelection associated with this object.

[getAccessibleSelection\(\)](#) - Method in class
javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

[getAccessibleSelection\(int\)](#) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent.
Returns an Accessible representing the specified selected child in the object.

[getAccessibleSelection\(int\)](#) - Method in class java.awt.List.AccessibleAWTList
Returns an Accessible representing the specified selected item in the object.

[getAccessibleSelection\(int\)](#) - Method in interface javax.accessibility.AccessibleSelection
Returns an Accessible representing the specified selected child of the object.

[getAccessibleSelection\(int\)](#) - Method in class javax.swing.JTabbedPane.AccessibleJTabbedPane

[getAccessibleSelection\(int\)](#) - Method in class javax.swing.JMenu.AccessibleJMenu
Returns the currently selected sub-menu if one is selected, otherwise null (there can only be one selection, and it can only be a sub-menu, as otherwise menu items don't remain selected).

[getAccessibleSelection\(int\)](#) - Method in class javax.swing.JComboBox.AccessibleJComboBox
Returns an Accessible representing the specified selected child in the popup.

[getAccessibleSelection\(int\)](#) - Method in class javax.swing.JList.AccessibleJList
Returns an Accessible representing the specified selected item in the object.

[getAccessibleSelection\(int\)](#) - Method in class [javax.swing.JTree.AccessibleJTree](#)
Returns an Accessible representing the specified selected item in the object.

[getAccessibleSelection\(int\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)
Returns an Accessible representing the specified selected item in the object.

[getAccessibleSelection\(int\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)
Returns an Accessible representing the specified selected child in the object.

[getAccessibleSelection\(int\)](#) - Method in class [javax.swing.JMenuBar.AccessibleJMenuBar](#)
Returns the currently selected menu if one is selected, otherwise null.

[getAccessibleSelectionCount\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)
Returns the number of Accessible children currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [java.awt.List.AccessibleAWTList](#)
Returns the number of items currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in interface [javax.accessibility.AccessibleSelection](#)
Returns the number of Accessible children currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JTabbedPane.AccessibleJTabbedPane](#)

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JMenu.AccessibleJMenu](#)
Returns 1 if a sub-menu is currently selected in this menu.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JComboBox.AccessibleJComboBox](#)
Returns the number of Accessible children currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JList.AccessibleJList](#)
Returns the number of items currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree](#)
Returns the number of items currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)
Returns the number of items currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)
Returns the number of Accessible children currently selected.

[getAccessibleSelectionCount\(\)](#) - Method in class [javax.swing.JMenuBar.AccessibleJMenuBar](#)
Returns 1 if a menu is currently selected in this menu bar.

[getAccessibleStateSet\(\)](#) - Method in class [java.applet.Applet.AccessibleApplet](#)
Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)
Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.Scrollbar.AccessibleAWTScrollBar](#)
Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)
Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.Checkbox.AccessibleAWTCheckbox](#)
Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.List.AccessibleAWTList](#)
Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.List.AccessibleAWTList.AccessibleAWTListChild](#)
Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.TextComponent.AccessibleAWTTextComponent](#)
Gets the state set of the TextComponent.

[getAccessibleStateSet\(\)](#) - Method in class [java.awt.Window.AccessibleAWTWindow](#)

INVALID_TRANSACTION(String, int, CompletionStatus) - Constructor for class
org.omg.CORBA.INVALID_TRANSACTION

Constructs an INVALID_TRANSACTION exception with the specified detail message, minor code, and completion status.

Invalid() - Constructor for class org.omg.CORBA.DynAnyPackage.Invalid
Constructs an Invalid object.

Invalid(String) - Constructor for class org.omg.CORBA.DynAnyPackage.Invalid
Constructs an Invalid object.

InvalidAlgorithmParameterException - exception java.security.InvalidAlgorithmParameterException.
This is the exception for invalid or inappropriate algorithm parameters.

InvalidAlgorithmParameterException() - Constructor for class
java.security.InvalidAlgorithmParameterException

Constructs an InvalidAlgorithmParameterException with no detail message.

InvalidAlgorithmParameterException(String) - Constructor for class
java.security.InvalidAlgorithmParameterException

Constructs an InvalidAlgorithmParameterException with the specified detail message.

invalidate() - Method in class java.awt.Component
Invalidates this component.

invalidate() - Method in class java.awt.Container
Invalidates the container.

invalidate() - Method in class javax.swing.CellRendererPane

Overridden to avoid propagating an invalidate up the tree when the cell renderer child is configured.

invalidateFileCache() - Method in class javax.swing.plaf.basic.BasicDirectoryModel

invalidateLayout(Container) - Method in interface java.awt.LayoutManager2

Invalidates the layout, indicating that if the layout manager has cached information it should be discarded.

invalidateLayout(Container) - Method in class java.awt.CardLayout

Invalidates the layout, indicating that if the layout manager has cached information it should be discarded.

invalidateLayout(Container) - Method in class java.awt.BorderLayout

Invalidates the layout, indicating that if the layout manager has cached information it should be discarded.

invalidateLayout(Container) - Method in class java.awt.GridBagLayout

Invalidates the layout, indicating that if the layout manager has cached information it should be discarded.

invalidateLayout(Container) - Method in class javax.swing.BoxLayout

Indicates that a child has changed its layout related information, and thus any cached calculations should be flushed.

invalidateLayout(Container) - Method in class javax.swing.OverlayLayout

Indicates a child has changed its layout related information, which causes any cached calculations to be flushed.

invalidateLayout(Container) - Method in class javax.swing.JRootPane.RootLayout

invalidateLayout(Container) - Method in class

javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager

Does nothing.

[invalidatePathBounds\(TreePath\)](#) - Method in class javax.swing.tree.[AbstractLayoutCache](#)

Instructs the LayoutCache that the bounds for path are invalid, and need to be updated.

[invalidatePathBounds\(TreePath\)](#) - Method in class javax.swing.tree.[VariableHeightLayoutCache](#)

Instructs the LayoutCache that the bounds for path are invalid, and need to be updated.

[invalidatePathBounds\(TreePath\)](#) - Method in class javax.swing.tree.[FixedHeightLayoutCache](#)

Does nothing, FixedHeightLayoutCache doesn't cache width, and that is all that could change.

[invalidateSizes\(\)](#) - Method in class javax.swing.tree.[AbstractLayoutCache](#)

Informs the TreeState that it needs to recalculate all the sizes it is referencing.

[invalidateSizes\(\)](#) - Method in class javax.swing.tree.[VariableHeightLayoutCache](#)

Informs the TreeState that it needs to recalculate all the sizes it is referencing.

[invalidateSizes\(\)](#) - Method in class javax.swing.tree.[FixedHeightLayoutCache](#)

Informs the TreeState that it needs to recalculate all the sizes it is referencing.

[InvalidAttributeIdentifierException](#) - exception javax.naming.directory.[InvalidAttributeIdentifierException](#).

This exception is thrown when an attempt is made to add to create an attribute with an invalid attribute identifier.

[InvalidAttributeIdentifierException\(\)](#) - Constructor for class

javax.naming.directory.[InvalidAttributeIdentifierException](#)

Constructs a new instance of InvalidAttributeIdentifierException.

[InvalidAttributeIdentifierException\(String\)](#) - Constructor for class

javax.naming.directory.[InvalidAttributeIdentifierException](#)

Constructs a new instance of InvalidAttributeIdentifierException using the explanation supplied.

[InvalidAttributesException](#) - exception javax.naming.directory.[InvalidAttributesException](#).

This exception is thrown when an attempt is made to add or modify an attribute set that has been specified incompletely or incorrectly.

[InvalidAttributesException\(\)](#) - Constructor for class javax.naming.directory.[InvalidAttributesException](#)

Constructs a new instance of InvalidAttributesException.

[InvalidAttributesException\(String\)](#) - Constructor for class javax.naming.directory.[InvalidAttributesException](#)

Constructs a new instance of InvalidAttributesException using an explanation.

[InvalidAttributeValueException](#) - exception javax.naming.directory.[InvalidAttributeValueException](#).

This class is thrown when an attempt is made to add to an attribute a value that conflicts with the attribute's schema definition.

[InvalidAttributeValueException\(\)](#) - Constructor for class

javax.naming.directory.[InvalidAttributeValueException](#)

Constructs a new instance of InvalidAttributeValueException.

[InvalidAttributeValueException\(String\)](#) - Constructor for class

javax.naming.directory.[InvalidAttributeValueException](#)

Constructs a new instance of InvalidAttributeValueException using an explanation.

[InvalidClassException](#) - exception java.io.[InvalidClassException](#).

Thrown when the Serialization runtime detects one of the following problems with a Class.

[InvalidClassException\(String\)](#) - Constructor for class java.io.[InvalidClassException](#)

Report a InvalidClassException for the reason specified.

[InvalidClassException\(String, String\)](#) - Constructor for class java.io.[InvalidClassException](#)

Constructs an InvalidClassException object.

[InvalidDnDOperationException](#) - exception java.awt.dnd.[InvalidDnDOperationException](#).

This exception is thrown by various methods in the java.awt.dnd package.

[InvalidDnDOperationException\(\)](#) - Constructor for class java.awt.dnd.[InvalidDnDOperationException](#)

Create a default Exception

[InvalidDnOperationException\(String\)](#) - Constructor for class java.awt.dnd.[InvalidDnOperationException](#)

Create an Exception with its own descriptive message

[InvalidKeyException](#) - exception java.security.[InvalidKeyException](#).

This is the exception for invalid Keys (invalid encoding, wrong length, uninitialized, etc).

[InvalidKeyException\(\)](#) - Constructor for class java.security.[InvalidKeyException](#)

Constructs an InvalidKeyException with no detail message.

[InvalidKeyException\(String\)](#) - Constructor for class java.security.[InvalidKeyException](#)

Constructs an InvalidKeyException with the specified detail message.

[InvalidKeySpecException](#) - exception java.security.spec.[InvalidKeySpecException](#).

This is the exception for invalid key specifications.

[InvalidKeySpecException\(\)](#) - Constructor for class java.security.spec.[InvalidKeySpecException](#)

Constructs an InvalidKeySpecException with no detail message.

[InvalidKeySpecException\(String\)](#) - Constructor for class java.security.spec.[InvalidKeySpecException](#)

Constructs an InvalidKeySpecException with the specified detail message.

[InvalidMidiDataException](#) - exception javax.sound.midi.[InvalidMidiDataException](#).

An InvalidMidiDataException indicates that inappropriate MIDI data was encountered.

[InvalidMidiDataException\(\)](#) - Constructor for class javax.sound.midi.[InvalidMidiDataException](#)

Constructs an InvalidMidiDataException with null for its error detail message.

[InvalidMidiDataException\(String\)](#) - Constructor for class javax.sound.midi.[InvalidMidiDataException](#)

Constructs an InvalidMidiDataException with the specified detail message.

[InvalidName](#) - exception org.omg.CORBA.ORBPackage.[InvalidName](#).

The InvalidName exception is raised when ORB.resolve_initial_references is passed a name for which there is no initial reference.

[InvalidName](#) - exception org.omg.CosNaming.NamingContextPackage.[InvalidName](#).

[InvalidName\(\)](#) - Constructor for class org.omg.CORBA.ORBPackage.[InvalidName](#)

Constructs an InvalidName exception with no reason message.

[InvalidName\(\)](#) - Constructor for class org.omg.CosNaming.NamingContextPackage.[InvalidName](#)

[InvalidName\(String\)](#) - Constructor for class org.omg.CORBA.ORBPackage.[InvalidName](#)

Constructs an InvalidName exception with the specified reason message.

[InvalidNameException](#) - exception javax.naming.[InvalidNameException](#).

This exception indicates that the name being specified does not conform to the naming syntax of a naming system.

[InvalidNameException\(\)](#) - Constructor for class javax.naming.[InvalidNameException](#)

Constructs an instance of InvalidNameException with all fields set to null.

[InvalidNameException\(String\)](#) - Constructor for class javax.naming.[InvalidNameException](#)

Constructs an instance of InvalidNameException using an explanation of the problem.

[InvalidNameHelper](#) - class org.omg.CosNaming.NamingContextPackage.[InvalidNameHelper](#).

[InvalidNameHolder](#) - class org.omg.CosNaming.NamingContextPackage.[InvalidNameHolder](#).

[InvalidNameHolder\(\)](#) - Constructor for class

org.omg.CosNaming.NamingContextPackage.[InvalidNameHolder](#)

[InvalidNameHolder\(InvalidName\)](#) - Constructor for class

org.omg.CosNaming.NamingContextPackage.[InvalidNameHolder](#)

InvalidObjectException - exception java.io.InvalidObjectException.

Indicates that one or more deserialized objects failed validation tests.

InvalidObjectException(String) - Constructor for class java.io.InvalidObjectException

Constructs an InvalidObjectException.

InvalidParameterException - exception java.security.InvalidParameterException.

This exception is thrown when an invalid parameter is passed to a method.

InvalidParameterException() - Constructor for class java.security.InvalidParameterException

Constructs an InvalidParameterException with no detail message.

InvalidParameterException(String) - Constructor for class java.security.InvalidParameterException

Constructs an InvalidParameterException with the specified detail message.

InvalidParameterSpecException - exception java.security.spec.InvalidParameterSpecException.

This is the exception for invalid parameter specifications.

InvalidParameterSpecException() - Constructor for class java.security.spec.InvalidParameterSpecException

Constructs an InvalidParameterSpecException with no detail message.

InvalidParameterSpecException(String) - Constructor for class
java.security.spec.InvalidParameterSpecException

Constructs an InvalidParameterSpecException with the specified detail message.

InvalidSearchControlsException - exception javax.naming.directory.InvalidSearchControlsException.

This exception is thrown when the specification of the SearchControls for a search operation is invalid.

InvalidSearchControlsException() - Constructor for class

javax.naming.directory.InvalidSearchControlsException

Constructs a new instance of InvalidSearchControlsException.

InvalidSearchControlsException(String) - Constructor for class

javax.naming.directory.InvalidSearchControlsException

Constructs a new instance of InvalidSearchControlsException with an explanation.

InvalidSearchFilterException - exception javax.naming.directory.InvalidSearchFilterException.

This exception is thrown when the specification of a search filter is invalid.

InvalidSearchFilterException() - Constructor for class javax.naming.directory.InvalidSearchFilterException

Constructs a new instance of InvalidSearchFilterException.

InvalidSearchFilterException(String) - Constructor for class

javax.naming.directory.InvalidSearchFilterException

Constructs a new instance of InvalidSearchFilterException with an explanation.

InvalidSeq - exception org.omg.CORBA.DynAnyPackage.InvalidSeq.

The InvalidSeq exception is thrown by all operations on dynamic anys that take a sequence (Java array) as an argument, when that sequence is invalid.

InvalidSeq() - Constructor for class org.omg.CORBA.DynAnyPackage.InvalidSeq

Constructs an InvalidSeq object.

InvalidSeq(String) - Constructor for class org.omg.CORBA.DynAnyPackage.InvalidSeq

Constructs an InvalidSeq object.

InvalidTransactionException - exception javax.transaction.InvalidTransactionException.

This exception indicates that the request carried an invalid transaction context.

InvalidTransactionException() - Constructor for class javax.transaction.InvalidTransactionException

InvalidTransactionException(String) - Constructor for class javax.transaction.InvalidTransactionException

InvalidValue - exception org.omg.CORBA.DynAnyPackage.InvalidValue.

InvalidValue() - Constructor for class org.omg.CORBA.DynAnyPackage.InvalidValue

Constructs an InvalidValue object.

InvalidValue(String) - Constructor for class org.omg.CORBA.DynAnyPackage.InvalidValue

Constructs an InvalidValue object.

inverseTransform(double[], int, double[], int, int) - Method in class java.awt.geom.AffineTransform

Inverse transforms an array of double precision coordinates by this transform.

inverseTransform(Point2D, Point2D) - Method in class java.awt.geom.AffineTransform

Inverse transforms the specified ptSrc and stores the result in ptDst.

INVITE - Static variable in class java.awt.PageAttributes.MediaType

An alias for INVITE_ENVELOPE.

INVITE_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for Invitation Envelope, 220 x 220 mm.

INVOCATION_DEFAULT - Static variable in class java.awt.event.InvocationEvent

The default id for all InvocationEvents.

INVOCATION_EVENT_MASK - Static variable in class java.awt.AWTEvent

The event mask for selecting invocation events.

INVOCATION_FIRST - Static variable in class java.awt.event.InvocationEvent

Marks the first integer id for the range of invocation event ids.

INVOCATION_LAST - Static variable in class java.awt.event.InvocationEvent

Marks the last integer id for the range of invocation event ids.

InvocationEvent - class java.awt.event.InvocationEvent.

An event which executes the run() method on a Runnable when dispatched by the AWT event dispatcher thread.

InvocationEvent(Object, int, Runnable, Object, boolean) - Constructor for class java.awt.event.InvocationEvent

Constructs an InvocationEvent with the specified source and ID which will execute the runnable's run() method when dispatched.

InvocationEvent(Object, Runnable) - Constructor for class java.awt.event.InvocationEvent

Constructs an InvocationEvent with the specified source which will execute the runnable's run() method when dispatched.

InvocationEvent(Object, Runnable, Object, boolean) - Constructor for class java.awt.event.InvocationEvent

Constructs an InvocationEvent with the specified source which will execute the runnable's run() method when dispatched.

InvocationHandler - interface java.lang.reflect.InvocationHandler.

InvocationHandler is the interface implemented by the *invocation handler* of a proxy instance.

InvocationTargetException - exception java.lang.reflect.InvocationTargetException.

InvocationTargetException is a checked exception that wraps an exception thrown by an invoked method or constructor.

InvocationTargetException() - Constructor for class java.lang.reflect.InvocationTargetException

Constructs an InvocationTargetException with null as the target exception.

InvocationTargetException(Throwable) - Constructor for class java.lang.reflect.InvocationTargetException

Constructs a InvocationTargetException with a target exception.

InvocationTargetException(Throwable, String) - Constructor for class java.lang.reflect.InvocationTargetException

Constructs a InvocationTargetException with a target exception and a detail message.

INVOICE - Static variable in class java.awt.PageAttributes.MediaType

The `MediaType` instance for Invoice, 5 1/2 x 8 1/2 in.

`invoke()` - Method in class `org.omg.CORBA.Request`

Makes a synchronous invocation using the information in the `Request` object.

`invoke(Object, Method, Object[])` - Method in interface `java.lang.reflect.InvocationHandler`

Processes a method invocation on a proxy instance and returns the result.

`invoke(Object, Object[])` - Method in class `java.lang.reflect.Method`

Invokes the underlying method represented by this `Method` object, on the specified object with the specified parameters.

`invoke(Object, OutputStream)` - Method in class `org.omg.CORBA.portable.Delegate`

`invoke` is called by a stub to invoke an operation.

`invoke(RemoteCall)` - Method in interface `java.rmi.server.RemoteRef`

Deprecated. 1.2 style stubs no longer use this method. Instead of using a sequence of method calls to the remote reference (`newCall`, `invoke`, and `done`), a stub uses a single method, `invoke(Remote, Method, Object[], int)`, on the remote reference to carry out parameter marshalling, remote method executing and unmarshalling of the return value.

1.2 stubs are generated using `rmic -v1.2`. By default, `rmic` generates stubs compatible with JDK1.1 and the Java 2 SDK. The compatible stubs can also be generated using `rmic -vcompat`.

`invoke(Remote, Method, Object[], long)` - Method in interface `java.rmi.server.RemoteRef`

Invoke a method.

`invoke(ServerRequest)` - Method in class `org.omg.CORBA.DynamicImplementation`

Accepts a `ServerRequest` object and uses its methods to determine the request target, operation, and parameters, and to set the result or exception.

`invoke(ServerRequest)` - Method in class `org.omg.CosNaming._BindingIteratorImplBase`

`invoke(ServerRequest)` - Method in class `org.omg.CosNaming._NamingContextImplBase`

`invokeAndWait(Runnable)` - Static method in class `java.awt.EventQueue`

Causes *runnable* to have its `run()` method called in the dispatch thread of the `EventQueue`.

`invokeAndWait(Runnable)` - Static method in class `javax.swing.SwingUtilities`

Causes *doRun.run()* to be executed synchronously on the AWT event dispatching thread.

`InvokeHandler` - interface `org.omg.CORBA.portable.InvokeHandler`.

This interface provides a dispatching mechanism for an incoming call.

`invokeLater(Runnable)` - Static method in class `java.awt.EventQueue`

Causes *runnable* to have its `run()` method called in the dispatch thread of the `EventQueue`.

`invokeLater(Runnable)` - Static method in class `javax.swing.SwingUtilities`

Causes *doRun.run()* to be executed asynchronously on the AWT event dispatching thread.

`INVOKES_STOP_CELL_EDITING_PROPERTY` - Static variable in class `javax.swing.JTree`

Bound property name for `messagesStopCellEditing`.

`invokesStopCellEditing` - Variable in class `javax.swing.JTree`

If true, when editing is to be stopped by way of selection changing, data in tree changing or other means `stopCellEditing` is invoked, and changes are saved.

`IOException` - exception `java.io.IOException`.

Signals that an I/O exception of some sort has occurred.

`IOException()` - Constructor for class `java.io.IOException`

Constructs an `IOException` with null as its error detail message.

IOException(String) - Constructor for class java.io.IOException

Constructs an IOException with the specified detail message.

IP_MULTICAST_IF - Static variable in interface java.net.SocketOptions

Set which outgoing interface on which to send multicast packets.

IPA_EXTENSIONS - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

ipadx - Variable in class java.awt.GridBagConstraints

This field specifies the internal padding of the component, how much space to add to the minimum width of the component.

ipady - Variable in class java.awt.GridBagConstraints

This field specifies the internal padding, that is, how much space to add to the minimum height of the component.

IObject - interface org.omg.CORBA.IObject.

An IObject IDL interface represents the most generic interface from which all other Interface Repository interfaces are derived, even the Repository itself.

IObjectOperations - interface org.omg.CORBA.IObjectOperations.

This is the Operations interface for the mapping from IObject.

is_a(Object, String) - Method in class org.omg.CORBA.portable.Delegate

Checks if the object reference is an instance of the given interface.

IS_CLOSED_PROPERTY - Static variable in class javax.swing.JInternalFrame

Constrained property name indicating that the frame is closed.

is_equivalent(Object, Object) - Method in class org.omg.CORBA.portable.Delegate

Determines if the two object references are equivalent.

IS_ICON_PROPERTY - Static variable in class javax.swing.JInternalFrame

Constrained property name indicating that the frame is iconified.

is_local(Object) - Method in class org.omg.CORBA.portable.Delegate

Returns true if this object is implemented by a local servant.

IS_MAXIMUM_PROPERTY - Static variable in class javax.swing.JInternalFrame

Constrained property name indicating that the frame is maximized.

IS_PALETTE - Static variable in class javax.swing.plaf.metal.MetalInternalFrameUI

IS_SELECTED_PROPERTY - Static variable in class javax.swing.JInternalFrame

Constrained property name indicated that this frame has selected status.

isAbsolute() - Method in class java.io.File

Tests whether this abstract pathname is absolute.

isAbstract(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the abstract modifier.

isAcceptAllFileFilterUsed() - Method in class javax.swing.JFileChooser

Returns whether the AcceptAll FileFilter is used.

isAccessible() - Method in class java.lang.reflect.AccessibleObject

Get the value of the accessible flag for this object.

isAccessibleChildSelected(int) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Determines if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class java.awt.List.AccessibleAWTList

Returns true if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in interface javax.accessibility.AccessibleSelection

Determines if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JTabbedPane.AccessibleJTabbedPane

isAccessibleChildSelected(int) - Method in class javax.swing.JMenu.AccessibleJMenu

Returns true if the current child of this object is selected (that is, if this child is a popped-up submenu).

isAccessibleChildSelected(int) - Method in class javax.swing.JComboBox.AccessibleJComboBox

Determines if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JList.AccessibleJList

Returns true if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JTree.AccessibleJTree

Returns true if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Returns true if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JTable.AccessibleJTable

Determines if the current child of this object is selected.

isAccessibleChildSelected(int) - Method in class javax.swing.JMenuBar.AccessibleJMenuBar

Returns true if the current child of this object is selected.

isAccessibleColumnSelected(int) - Method in interface javax.accessibility.AccessibleTable

Returns a boolean value indicating whether the specified column is selected.

isAccessibleColumnSelected(int) - Method in class javax.swing.JTable.AccessibleJTable

Returns a boolean value indicating whether the specified column is selected

isAccessibleRowSelected(int) - Method in interface javax.accessibility.AccessibleTable

Returns a boolean value indicating whether the specified row is selected.

isAccessibleRowSelected(int) - Method in class javax.swing.JTable.AccessibleJTable

Returns a boolean value indicating whether the specified row is selected

isAccessibleSelected(int, int) - Method in interface javax.accessibility.AccessibleTable

Returns a boolean value indicating whether the accessible at a specified row and column is selected.

isAccessibleSelected(int, int) - Method in class javax.swing.JTable.AccessibleJTable

Returns a boolean value indicating whether the accessible at a given (row, column) is selected

isActionKey() - Method in class java.awt.event.KeyEvent

Returns whether or not the key in this event is an "action" key, as defined in Event.java.

isActive() - Method in class java.applet.Applet

Determines if this applet is active.

isActive() - Method in interface java.applet.AppletStub

Determines if the applet is active.

isActive() - Method in class java.awt.dnd.DropTarget

This method returns a boolean indicating whether or not this DropTarget is currently active (ready to accept drops).

isActive() - Method in interface javax.sound.sampled.DataLine

Indicates whether the line is engaging in active I/O (such as playback or capture).

isAddedPath() - Method in class javax.swing.event.TreeSelectionEvent

Returns true if the first path element has been added to the selection, a return value of false means the first path has been removed from the selection.

isAddedPath(int) - Method in class javax.swing.event.TreeSelectionEvent

Returns true if the path identified by index was added to the selection.

isAddedPath(TreePath) - Method in class javax.swing.event.TreeSelectionEvent

Returns true if the path identified by path was added to the selection.

isAfter(int, int, Rectangle) - Method in class javax.swing.text.CompositeView

Tests whether a point lies after the rectangle range.

isAfter(int, int, Rectangle) - Method in class javax.swing.text.BoxView
Determines if a point falls after an allocated region.

isAfterLast() - Method in interface java.sql.ResultSet
Indicates whether the cursor is after the last row in this ResultSet object.

isAlive() - Method in class java.lang.Thread
Tests if this thread is alive.

isAllocationValid() - Method in class javax.swing.text.BoxView
Are the allocations for the children still valid?

isAlphaPremultiplied() - Method in class java.awt.image.BufferedImage
Returns whether or not the alpha has been premultiplied.

isAlphaPremultiplied() - Method in class java.awt.image.ColorModel
Returns whether or not the alpha has been premultiplied in the pixel values to be translated by this ColorModel.

isAltDown() - Method in class java.awt.event.InputEvent
Returns whether or not the Alt modifier is down on this event.

isAltGraphDown() - Method in class java.awt.event.InputEvent
Returns whether or not the Alt-Graph modifier is down on this event.

isAncestorOf(Component) - Method in class java.awt.Container
Checks if the component is contained in the component hierarchy of this container.

isAntiAliased() - Method in class java.awt.font.FontRenderContext
Gets the text anti-aliasing mode used in this FontRenderContext.

isArmed() - Method in class javax.swing.JMenuItem
Returns whether the menu item is "armed".

isArmed() - Method in interface javax.swing.ButtonModel
Indicates partial commitment towards pressing the button.

isArmed() - Method in class javax.swing.DefaultButtonModel
Indicates partial commitment towards pressing the button.

isArray() - Method in class java.lang.Class
Determines if this Class object represents an array class.

isAssignableFrom(Class) - Method in class java.lang.Class
Determines if the class or interface represented by this Class object is either the same as, or is a superclass or superinterface of, the class or interface represented by the specified Class parameter.

isAutoIncrement(int) - Method in interface java.sql.ResultSetMetaData
Indicates whether the designated column is automatically numbered, thus read-only.

isAutoScrolling - Variable in class javax.swing.plaf.basic.BasicComboPopup

isAutoWaitForIdle() - Method in class java.awt.Robot
Returns whether this Robot automatically invokes waitForIdle after generating an event.

isBackingStoreEnabled() - Method in class javax.swing.JViewport
Deprecated. As of Java 2 platform v1.3, replaced by getScrollMode().

isBefore(int, int, Rectangle) - Method in class javax.swing.text.CompositeView
Tests whether a point lies before the rectangle range.

isBefore(int, int, Rectangle) - Method in class javax.swing.text.BoxView
Determines if a point falls before an allocated region.

isBeforeFirst() - Method in interface java.sql.ResultSet
Indicates whether the cursor is before the first row in this ResultSet object.

isBigEndian() - Method in class javax.sound.sampled.AudioFormat
Indicates whether the audio data is stored in big-endian or little-endian byte order.

isBlock() - Method in class javax.swing.text.html.HTML.Tag
Block tags are tags that add structure to a document.

isBlockTag(AttributeSet) - Method in class javax.swing.text.html.HTMLWriter
Determines if the HTML.Tag associated with the element is a block tag.

isBold() - Method in class java.awt.Font
Indicates whether or not this Font object's style is BOLD.

isBold(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Checks whether the bold attribute is set.

isBorderOpaque() - Method in class javax.swing.border.AbstractBorder
This default implementation returns false.

isBorderOpaque() - Method in class javax.swing.border.BevelBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.SoftBevelBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.EmptyBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.MatteBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.CompoundBorder
Returns whether or not this compound border is opaque.

isBorderOpaque() - Method in class javax.swing.border.LineBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.TitledBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.border.EtchedBorder
Returns whether or not the border is opaque.

isBorderOpaque() - Method in interface javax.swing.border.Border
Returns whether or not the border is opaque.

isBorderOpaque() - Method in class javax.swing.plaf.BorderUIResource

isBorderOpaque() - Method in class javax.swing.plaf.basic.BasicBorders.SplitPaneBorder

isBorderPainted() - Method in class javax.swing.AbstractButton
Returns whether the border should be painted.

isBorderPainted() - Method in class javax.swing.JPopupMenu
Checks whether the border should be painted.

isBorderPainted() - Method in class javax.swing.JToolBar
Checks whether the border should be painted.

isBorderPainted() - Method in class javax.swing.JMenuBar
Returns true if the menu bars border should be painted.

isBorderPainted() - Method in class javax.swing.JProgressBar
Returns true if the progress bar has a border or false if it does not.

isBorderPaintedFlat() - Method in class javax.swing.JCheckBox
Returns whether the border should be painted flat.

isBound() - Method in class java.beans.PropertyDescriptor

Updates to "bound" properties will cause a "PropertyChange" event to get fired when the property is changed.

isBoundary(int) - Method in class java.text.BreakIterator

Return true if the specified position is a boundary position.

isCanceled() - Method in class javax.swing.ProgressMonitor

Returns true if the user hits the Cancel button in the progress dialog.

isCancelled() - Method in class java.awt.print.PrinterJob

Returns true if a print job is in progress, but is going to be cancelled at the next opportunity; otherwise returns false.

isCaseIgnored() - Method in interface javax.naming.directory.Attributes

Determines whether the attribute set ignores the case of attribute identifiers when retrieving or adding attributes.

isCaseIgnored() - Method in class javax.naming.directory.BasicAttributes

isCaseSensitive(int) - Method in interface java.sql.ResultSetMetaData

Indicates whether a column's case matters.

isCatalogAtStart() - Method in interface java.sql.DatabaseMetaData

Does a catalog appear at the start of a qualified table name? (Otherwise it appears at the end)

isCellEditable(EventObject) - Method in interface javax.swing.CellEditor

Ask the editor if it can start editing using *anEvent*.

isCellEditable(EventObject) - Method in class javax.swing.AbstractCellEditor

Returns true.

isCellEditable(EventObject) - Method in class javax.swing.DefaultCellEditor

isCellEditable(EventObject) - Method in class javax.swing.DefaultCellEditor.EditorDelegate

isCellEditable(EventObject) - Method in class javax.swing.tree.DefaultTreeCellEditor

If the realEditor returns true to this message, prepareForEditing is messaged and true is returned.

isCellEditable(int, int) - Method in class javax.swing.JTable

Returns true if the cell at row and column is editable.

isCellEditable(int, int) - Method in class javax.swing.table.AbstractTableModel

Returns false.

isCellEditable(int, int) - Method in class javax.swing.table.DefaultTableModel

Returns true regardless of parameter values.

isCellEditable(int, int) - Method in interface javax.swing.table.TableModel

Returns true if the cell at rowIndex and columnIndex is editable.

isCellSelected(int, int) - Method in class javax.swing.JTable

Returns true if the cell at the specified position is selected.

isCertificateEntry(String) - Method in class java.security.KeyStore

Returns true if the entry identified by the given alias is a *trusted certificate entry*, and false otherwise.

isClosable() - Method in class javax.swing.JInternalFrame

Returns whether this JInternalFrame be closed by some user action.

isClosed - Variable in class javax.swing.JInternalFrame

The frame has been closed.

isClosed() - Method in interface java.sql.Connection

Tests to see if a Connection is closed.

isClosed() - Method in class javax.swing.JInternalFrame

Returns whether this `JInternalFrame` is currently closed.

`isCoalesce()` - Method in class `javax.swing.Timer`
Returns true if the `Timer` coalesces multiple pending `performCommand()` messages.

`isCollapsed(int)` - Method in class `javax.swing.JTree`
Returns true if the node at the specified display row is collapsed.

`isCollapsed(TreePath)` - Method in class `javax.swing.JTree`
Returns true if the value identified by path is currently collapsed, this will return false if any of the values in path are currently not being displayed.

`isColumnSelected(int)` - Method in class `javax.swing.JTable`
Returns true if the column at the specified index is selected.

`isCombining()` - Method in class `java.awt.font.GlyphMetrics`
Returns true if this is a combining glyph.

`isCompatibleRaster(Raster)` - Method in class `java.awt.image.ColorModel`
Returns true if `raster` is compatible with this `ColorModel` and false if it is not.

`isCompatibleRaster(Raster)` - Method in class `java.awt.image.ComponentColorModel`
Returns true if `raster` is compatible with this `ColorModel`; false if it is not.

`isCompatibleRaster(Raster)` - Method in class `java.awt.image.DirectColorModel`
Returns true if `raster` is compatible with this `ColorModel` and false if it is not.

`isCompatibleRaster(Raster)` - Method in class `java.awt.image.IndexColorModel`
Returns true if `raster` is compatible with this `ColorModel` or false if it is not compatible with this `ColorModel`.

`isCompatibleSampleModel(SampleModel)` - Method in class `java.awt.image.ColorModel`
Checks if the `SampleModel` is compatible with this `ColorModel`.

`isCompatibleSampleModel(SampleModel)` - Method in class `java.awt.image.PackedColorModel`
Checks if the specified `SampleModel` is compatible with this `ColorModel`.

`isCompatibleSampleModel(SampleModel)` - Method in class `java.awt.image.ComponentColorModel`
Checks whether or not the specified `SampleModel` is compatible with this `ColorModel`.

`isCompatibleSampleModel(SampleModel)` - Method in class `java.awt.image.IndexColorModel`
Checks if the specified `SampleModel` is compatible with this `ColorModel`.

`isCompatibleValue(Object)` - Method in class `java.awt.RenderingHints.Key`
Returns true if the specified object is a valid value for this `Key`.

`isCompatibleWith(String)` - Method in class `java.lang.Package`
Compare this package's specification version with a desired version.

`isCompletelyDirty(JComponent)` - Method in class `javax.swing.RepaintManager`
Convenience method that returns true if `aComponent` will be completely painted during the next `paintDirtyRegions()`.

`isComponent()` - Method in class `java.awt.font.GlyphMetrics`
Returns true if this is a component glyph.

`isComponentPartOfCurrentMenu(Component)` - Method in class `javax.swing.MenuSelectionManager`
Return true if `c` is part of the currently used menu

`isCompositionEnabled()` - Method in class `java.awt.im.InputContext`
Determines whether the current input method is enabled for composition.

`isCompositionEnabled()` - Method in interface `java.awt.im.spi.InputMethod`
Determines whether this input method is enabled.

`isConstrained()` - Method in class `java.beans.PropertyDescriptor`
Attempted updates to "Constrained" properties will cause a "VetoableChange" event to get fired when the property is changed.

isConsumed() - Method in class java.awt.AWTEvent

isConsumed() - Method in class java.awt.event.InputMethodEvent

Returns whether or not this event has been consumed.

isConsumed() - Method in class java.awt.event.InputEvent

Returns whether or not this event has been consumed.

isConsumer(ImageConsumer) - Method in class java.awt.image.FilteredImageSource

Determines whether an ImageConsumer is on the list of consumers currently interested in data for this image.

isConsumer(ImageConsumer) - Method in interface java.awt.image.ImageProducer

This method determines if a given ImageConsumer object is currently registered with this ImageProducer as one of its consumers.

isConsumer(ImageConsumer) - Method in class java.awt.image.MemoryImageSource

Determine if an ImageConsumer is on the list of consumers currently interested in data for this image.

isConsumer(ImageConsumer) - Method in class java.awt.image.renderable.RenderableImageProducer

Determine if an ImageConsumer is on the list of consumers currently interested in data for this image.

isContentAreaFilled() - Method in class javax.swing.AbstractButton

Checks whether the "content area" of the button should be filled.

isContinuousLayout() - Method in class javax.swing.JSplitPane

Returns true if the child components are continuously redisplayed and layed out during user intervention.

isContinuousLayout() - Method in class javax.swing.plaf.basic.BasicSplitPaneUI

Determines whether the JSplitPane is set to use a continuous layout.

isControlDown() - Method in class java.awt.event.InputEvent

Returns whether or not the Control modifier is down on this event.

isControlSupported(Control.Type) - Method in interface javax.sound.sampled.Line

Indicates whether the line supports a control of the specified type.

isConversionSupported(AudioFormat.Encoding, AudioFormat) - Static method in class

javax.sound.sampled.AudioSystem

Indicates whether an audio input stream of the specified encoding can be obtained from an audio input stream that has the specified format.

isConversionSupported(AudioFormat.Encoding, AudioFormat) - Method in class

javax.sound.sampled.spi.FormatConversionProvider

Indicates whether the format converter supports conversion to a particular encoding from a particular format.

isConversionSupported(AudioFormat, AudioFormat) - Static method in class

javax.sound.sampled.AudioSystem

Indicates whether an audio input stream of a specified format can be obtained from an audio input stream of another specified format.

isConversionSupported(AudioFormat, AudioFormat) - Method in class

javax.sound.sampled.spi.FormatConversionProvider

Indicates whether the format converter supports conversion to one particular format from another.

isCritical() - Method in interface javax.naming.ldap.Control

Determines the criticality of the LDAP control.

isCS_sRGB() - Method in class java.awt.color.ColorSpace

Returns true if the ColorSpace is CS_sRGB.

isCurrency(int) - Method in interface java.sql.ResultSetMetaData

Indicates whether the designated column is a cash value.

isCurrentServiceInvalidNow() - Method in class java.beans.beancontext.BeanContextServiceRevokedEvent
Reports if the current service is being forcibly revoked, in which case the references are now invalidated and unusable.

isCustomMarshaled(Class) - Method in interface javax.rmi.CORBA.ValueHandler
Indicates whether the given class performs custom or default marshaling.

isCyclic() - Method in class java.awt.GradientPaint
Returns true if the gradient cycles repeatedly between the two colors C1 and C2.

isDaemon() - Method in class java.lang.ThreadGroup
Tests if this thread group is a daemon thread group.

isDaemon() - Method in class java.lang.Thread
Tests if this thread is a daemon thread.

isDataFlavorSupported(DataFlavor) - Method in interface java.awt.datatransfer.Transferable
Returns whether or not the specified data flavor is supported for this object.

isDataFlavorSupported(DataFlavor) - Method in class java.awt.datatransfer.StringSelection
Returns whether the requested flavor is supported by this Transferable.

isDataFlavorSupported(DataFlavor) - Method in class java.awt.dnd.DropTargetContext
This method returns a boolean indicating if the given DataFlavor is supported by this DropTargetContext.

isDataFlavorSupported(DataFlavor) - Method in class java.awt.dnd.DropTargetContext.TransferableProxy
check if a particular flavor is supported?

isDataFlavorSupported(DataFlavor) - Method in class java.awt.dnd.DropTargetDropEvent
This method returns a boolean indicating if the specified DataFlavor is available from the source.

isDataFlavorSupported(DataFlavor) - Method in class java.awt.dnd.DropTargetDragEvent
This method returns a boolean indicating if the specified DataFlavor is supported.

isDecimalSeparatorAlwaysShown() - Method in class java.text.DecimalFormat
Allows you to get the behavior of the decimal separator with integers.

isDefaultButton() - Method in class javax.swing.JButton
Returns whether or not this button is the default button on the RootPane.

isDefaultCapable() - Method in class javax.swing.JButton
Returns whether or not this button is capable of being the default button on the RootPane.

isDefined(char) - Static method in class java.lang.Character
Determines if a character has a defined meaning in Unicode.

isDefined(Object) - Method in class javax.swing.text.SimpleAttributeSet
Tells whether a given attribute is defined.

isDefined(Object) - Method in class javax.swing.text.StyleContext.SmallAttributeSet
Checks whether a given attribute is defined.

isDefined(Object) - Method in class javax.swing.text.StyleContext.NamedStyle
Checks whether a given attribute is defined.

isDefined(Object) - Method in class javax.swing.text.AbstractDocument.AbstractElement
Checks whether a given attribute is defined.

isDefined(Object) - Method in interface javax.swing.text.AttributeSet
Checks whether the named attribute has a value specified in the set without resolving through another attribute set.

isDefinitelyWritable(int) - Method in interface java.sql.ResultSetMetaData
Indicates whether a write on the designated column will definitely succeed.

isDelegated() - Method in class java.beans.beancontext.BeanContextChildSupport

Reports whether or not this class is a delegate of another.

isDescendant(TreePath) - Method in class javax.swing.tree.TreePath
Returns true if aTreePath is a descendant of this TreePath.

isDescendingFrom(Component, Component) - Static method in class javax.swing.SwingUtilities
Return true if a component a descends from a component b

isDesignTime() - Static method in class java.beans.Beans
Test if we are in design-mode.

isDesignTime() - Method in interface java.beans.DesignMode
A value of true denotes that JavaBeans should behave in design time mode, a value of false denotes runtime behavior.

isDesignTime() - Method in class java.beans.beancontext.BeanContextSupport
Reports whether or not this object is in currently in design time mode.

isDestroyed() - Method in class java.lang.ThreadGroup
Tests if this thread group has been destroyed.

isDeviceSupported(MidiDevice.Info) - Method in class javax.sound.midi.spi.MidiDeviceProvider
Indicates whether the device provider supports the device represented by the specified device info object.

isDigit(char) - Static method in class java.lang.Character
Determines if the specified character is a digit.

isDirectory() - Method in class java.io.File
Tests whether the file denoted by this abstract pathname is a directory.

isDirectory() - Method in class java.util.zip.ZipEntry
Returns true if this is a directory entry.

isDirectorySelectionEnabled() - Method in class javax.swing.JFileChooser
Convenience call that determines if directories are selectable based on the current file selection mode.

isDispatchThread() - Static method in class java.awt.EventQueue
Returns true if the calling thread is the current AWT EventQueue's dispatch thread.

isDisplayable() - Method in class java.awt.Component
Determines whether this component is displayable.

isDone() - Method in interface java.awt.geom.PathIterator
Tests if the iteration is complete.

isDone() - Method in class java.awt.geom.FlatteningPathIterator
Tests if the iteration is complete.

isDoubleBuffered() - Method in class java.awt.Component
Returns true if this component is painted to an offscreen image ("buffer") that's copied to the screen later.

isDoubleBuffered() - Method in class javax.swing.JComponent
Returns whether the receiving component should use a buffer to paint.

isDoubleBufferingEnabled() - Method in class javax.swing.RepaintManager
Returns true if this object is double buffered.

isDragging - Variable in class javax.swing.plaf.basic.BasicScrollBarUI

isDragging - Variable in class javax.swing.plaf.basic.BasicToolBarUI.DockingListener

isDragImageSupported() - Static method in class java.awt.dnd.DragSource
This method returns a boolean indicating whether or not drag Image support is available on the underlying platform.

isDrawingBuffer() - Method in class javax.swing.DebugGraphics

Returns the drawingBuffer value.

isDynamic() - Method in interface java.awt.image.renderable.ContextualRenderedImageFactory

Returns true if successive renderings (that is, calls to create(RenderContext, ParameterBlock)) with the same arguments may produce different results.

isDynamic() - Method in class java.awt.image.renderable.RenderableImageOp

Returns true if successive renderings (that is, calls to createRendering() or createScaledRendering()) with the same arguments may produce different results.

isDynamic() - Method in interface java.awt.image.renderable.RenderableImage

Returns true if successive renderings (that is, calls to createRendering() or createScaledRendering()) with the same arguments may produce different results.

isEditable - Variable in class javax.swing.JComboBox

isEditable() - Method in class java.awt.TextComponent

Indicates whether or not this text component is editable.

isEditable() - Method in class javax.swing.JComboBox

Returns true if the JComboBox is editable.

isEditable() - Method in class javax.swing.JTree

Returns true if the tree is editable.

isEditable() - Method in class javax.swing.text.JTextComponent

Returns the boolean indicating whether this TextComponent is editable or not.

isEditable() - Method in class javax.swing.plaf.basic.BasicTreeUI

isEditing() - Method in class javax.swing.JTree

Returns true if the tree is being edited.

isEditing() - Method in class javax.swing.JTable

Returns true if a cell is being edited.

isEditing(JTree) - Method in class javax.swing.plaf.TreeUI

Returns true if the tree is being edited.

isEditing(JTree) - Method in class javax.swing.plaf.basic.BasicTreeUI

Returns true if the tree is being edited.

isEditing(JTree) - Method in class javax.swing.plaf.multi.MultiTreeUI

Call isEditing on each UI handled by this MultiUI.

isEmpty() - Method in class java.awt.RenderingHints

Returns true if this RenderingHints contains no key-value mappings.

isEmpty() - Method in class java.awt.Rectangle

Determines whether or not this Rectangle is empty.

isEmpty() - Method in class java.awt.geom.RectangularShape

Determines whether the RectangularShape is empty.

isEmpty() - Method in class java.awt.geom.RoundRectangle2D.Float

Determines whether or not this RoundRectangle2D is empty.

isEmpty() - Method in class java.awt.geom.RoundRectangle2D.Double

Determines whether or not this RoundRectangle2D is empty.

isEmpty() - Method in class java.awt.geom.Area

Tests whether this Area object encloses any area.

isEmpty() - Method in class java.awt.geom.Rectangle2D.Float

Determines whether or not this Rectangle2D is empty.

isEmpty() - Method in class java.awt.geom.Rectangle2D.Double
Determines whether or not this Rectangle2D is empty.

isEmpty() - Method in class java.awt.geom.Arc2D.Float
Determines whether the arc is empty.

isEmpty() - Method in class java.awt.geom.Arc2D.Double
Determines whether the arc is empty.

isEmpty() - Method in class java.awt.geom.Ellipse2D.Float
Determines whether or not the bounding box of this Ellipse2D is empty.

isEmpty() - Method in class java.awt.geom.Ellipse2D.Double
Determines whether or not the bounding box of this Ellipse2D is empty.

isEmpty() - Method in class java.beans.beancontext.BeanContextSupport
Reports whether or not this BeanContext is empty.

isEmpty() - Method in class java.util.Dictionary
Tests if this dictionary maps no keys to value.

isEmpty() - Method in class java.util.Hashtable
Tests if this hashtable maps no keys to values.

isEmpty() - Method in class java.util.AbstractCollection
Returns `true` if this collection contains no elements.

isEmpty() - Method in class java.util.TreeSet
Returns `true` if this set contains no elements.

isEmpty() - Method in class java.util.AbstractMap
Returns `true` if this map contains no key-value mappings.

isEmpty() - Method in class java.util.Vector
Tests if this vector has no components.

isEmpty() - Method in interface java.util.Collection
Returns `true` if this collection contains no elements.

isEmpty() - Method in class java.util.WeakHashMap
Returns `true` if this map contains no key-value mappings.

isEmpty() - Method in class java.util.HashSet
Returns `true` if this set contains no elements.

isEmpty() - Method in interface java.util.Set
Returns `true` if this set contains no elements.

isEmpty() - Method in interface java.util.List
Returns `true` if this list contains no elements.

isEmpty() - Method in class java.util.ArrayList
Tests if this list has no elements.

isEmpty() - Method in class java.util.HashMap
Returns `true` if this map contains no key-value mappings.

isEmpty() - Method in interface java.util.Map
Returns `true` if this map contains no key-value mappings.

isEmpty() - Method in class java.util.jar.Attributes
Returns `true` if this Map contains no attributes.

isEmpty() - Method in interface javax.naming.Name
Determines whether this name is empty.

isEmpty() - Method in class javax.naming.CompoundName
Determines whether this compound name is empty.

isEmpty() - Method in class javax.naming.CompositeName

Determines whether this composite name is empty.

isEmpty() - Method in class javax.swing.DefaultListModel
Tests if this list has no components.

isEmpty() - Method in class javax.swing.text.SimpleAttributeSet
Checks whether the set of attributes is empty.

isEmpty() - Method in class javax.swing.text.html.parser.Element
Check if empty

isEnabled() - Method in class java.awt.Component
Determines whether this component is enabled.

isEnabled() - Method in class java.awt.Component.AccessibleAWTComponent
Determine if the object is enabled.

isEnabled() - Method in class java.awt.MenuItem
Checks whether this menu item is enabled.

isEnabled() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
Determine if the object is enabled.

isEnabled() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild
Determine if the object is enabled.

isEnabled() - Method in interface javax.accessibility.AccessibleComponent
Determines if the object is enabled.

isEnabled() - Method in class javax.swing.ToolTipManager
Returns true if this object is enabled.

isEnabled() - Method in interface javax.swing.Action
Returns the enabled state of the Action.

isEnabled() - Method in interface javax.swing.ButtonModel
Indicates if the button can be selected or pressed by an input device (such as a mouse pointer).

isEnabled() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

isEnabled() - Method in class javax.swing.DefaultButtonModel
Indicates if the button can be selected or pressed by an input device (such as a mouse pointer).

isEnabled() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

isEnabled() - Method in class javax.swing.AbstractAction
Returns true if the action is enabled.

isEnabled() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
Determines if the object is enabled.

isEnabled() - Method in class javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

isEnabled() - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI.OpenAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI.CloseAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI.MinimizeAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI.MaximizeAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI.NavigateAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreeTraverseAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreePageAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreeIncrementAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreeHomeAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreeToggleAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicTreeUI.TreeCancelEditingAction

isEnabled() - Method in class javax.swing.plaf.basic.BasicSliderUI.ActionScroller

isEnabledAt(int) - Method in class javax.swing.JTabbedPane

Returns whether or not the tab at index is currently enabled.

isEnqueued() - Method in class java.lang.ref.Reference

Tells whether or not this reference object has been enqueued, either by the program or by the garbage collector.

isEqual(AttributeSet) - Method in class javax.swing.text.SimpleAttributeSet

Compares two attribute sets.

isEqual(AttributeSet) - Method in class javax.swing.text.StyleContext.SmallAttributeSet

Checks whether two attribute sets are equal.

isEqual(AttributeSet) - Method in class javax.swing.text.StyleContext.NamedStyle

Checks whether two attribute sets are equal.

isEqual(AttributeSet) - Method in class javax.swing.text.AbstractDocument.AbstractElement

Checks whether two attribute sets are equal.

isEqual(AttributeSet) - Method in interface javax.swing.text.AttributeSet

Determines if the two attribute sets are equivalent.

isEqual(byte[], byte[]) - Static method in class java.security.MessageDigest

Compares two digests for equality.

isErrorAny() - Method in class java.awt.MediaTracker

Checks the error status of all of the images.

isErrorID(int) - Method in class java.awt.MediaTracker

Checks the error status of all of the images tracked by this media tracker with the specified identifier.

isEventDispatchThread() - Static method in class javax.swing.SwingUtilities

Returns true if the current thread is an AWT event dispatching thread.

isExpanded(int) - Method in class javax.swing.JTree

Returns true if the node at the specified display row is currently expanded.

isExpanded(TreePath) - Method in class javax.swing.JTree

Returns true if the node identified by the path is currently expanded,

isExpanded(TreePath) - Method in class javax.swing.tree.AbstractLayoutCache

Returns true if the value identified by row is currently expanded.

isExpanded(TreePath) - Method in class javax.swing.tree.VariableHeightLayoutCache

Returns true if the value identified by row is currently expanded.

isExpanded(TreePath) - Method in class javax.swing.tree.FixedHeightLayoutCache

Returns true if the value identified by row is currently expanded.

isExpert() - Method in class java.beans.FeatureDescriptor

The "expert" flag is used to distinguish between those features that are intended for expert users from those that are intended for normal users.

isFile() - Method in class java.io.File

Tests whether the file denoted by this abstract pathname is a normal file.

isFileHidingEnabled() - Method in class javax.swing.JFileChooser

Returns true if hidden files are not shown in the file chooser; otherwise, returns false.

isFileSelectionEnabled() - Method in class javax.swing.JFileChooser

Convenience call that determines if files are selectable based on the current file selection mode.

isFileTypeSupported(AudioFormat.Type) - Static method in class javax.sound.sampled.AudioSystem

Indicates whether file writing support for the specified file type is provided by the system.

isFileTypeSupported(AudioFormat.Type) - Method in class javax.sound.sampled.spi.AudioFileWriter

Indicates whether file writing support for the specified file type is provided by this audio file writer.

isFileTypeSupported(AudioFormat.Type, AudioInputStream) - Static method in class javax.sound.sampled.AudioSystem

Indicates whether an audio file of the specified file type can be written from the indicated audio input stream.

isFileTypeSupported(AudioFormat.Type, AudioInputStream) - Method in class javax.sound.sampled.spi.AudioFileWriter

Indicates whether an audio file of the type specified can be written from the audio input stream indicated.

isFileTypeSupported(int) - Static method in class javax.sound.midi.MidiSystem

Indicates whether file writing support for the specified MIDI file type is provided by the system.

isFileTypeSupported(int) - Method in class javax.sound.midi.spi.MidiFileWriter

Indicates whether file writing support for the specified MIDI file type is provided by this file writer.

isFileTypeSupported(int, Sequence) - Static method in class javax.sound.midi.MidiSystem

Indicates whether a MIDI file of the file type specified can be written from the sequence indicated.

isFileTypeSupported(int, Sequence) - Method in class javax.sound.midi.spi.MidiFileWriter

Indicates whether a MIDI file of the file type specified can be written from the sequence indicated.

isFinal(int) - Static method in class java.lang.reflect.Modifier

Return true if the specified integer includes the `final` modifier.

isFirst() - Method in interface java.sql.ResultSet

Indicates whether the cursor is on the first row of this `ResultSet` object.

isFixedRowHeight() - Method in class javax.swing.JTree

Returns true if the height of each display row is a fixed size.

isFixedRowHeight() - Method in class javax.swing.tree.AbstractLayoutCache

Returns true if the height of each row is a fixed size.

isFlavorJavaFileListType() - Method in class java.awt.datatransfer.DataFlavor

isFlavorRemoteObjectType() - Method in class java.awt.datatransfer.DataFlavor

isFlavorSerializedObjectType() - Method in class java.awt.datatransfer.DataFlavor

isFloatable() - Method in class javax.swing.JToolBar

Returns true if the `JToolBar` can be dragged out by the user.

isFloating() - Method in class javax.swing.plaf.basic.BasicToolBarUI

isFocusCycleRoot() - Method in class javax.swing.JComponent

Override this method and return true if your component is the root of a component tree with its own focus cycle.

isFocusCycleRoot() - Method in class javax.swing.JEditorPane

Makes JEditorPane be the root of a focus cycle.

isFocusCycleRoot() - Method in class javax.swing.JRootPane

Make JRootPane be the root of a focus cycle.

isFocusManagerEnabled() - Static method in class javax.swing.FocusManager

Return whether Swing's focus manager is enabled

isFocusPainted() - Method in class javax.swing.AbstractButton

Returns whether focus should be painted.

isFocusTraversable() - Method in class java.awt.Component

Returns the value of a flag that indicates whether this component can be traversed using Tab or Shift-Tab keyboard focus traversal.

isFocusTraversable() - Method in class java.awt.Component.AccessibleAWTComponent

Returns whether this object can accept focus or not.

isFocusTraversable() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Returns whether this object can accept focus or not.

isFocusTraversable() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Returns whether this object can accept focus or not.

isFocusTraversable() - Method in interface javax.accessibility.AccessibleComponent

Returns whether this object can accept focus or not.

isFocusTraversable() - Method in class javax.swing.JComponent

Identifies whether or not this component can receive the focus.

isFocusTraversable() - Method in class javax.swing.AbstractButton

Identifies whether or not this component can receive the focus.

isFocusTraversable() - Method in class javax.swing.JSeparator

Identifies whether or not this component can receive the focus.

isFocusTraversable() - Method in class javax.swing.JComboBox

Returns true if the component can receive the focus.

isFocusTraversable() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

isFocusTraversable() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

isFocusTraversable() - Method in class javax.swing.JTable

We override this method, whose implementation in JComponent returns false, to return true.

isFocusTraversable() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

isFocusTraversable() - Method in class javax.swing.JScrollBar

Identifies whether or not this component can receive the focus.

isFocusTraversable() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

isFocusTraversable() - Method in class javax.swing.text.JTextComponent

Returns true if the focus can be traversed.

isFocusTraversable() - Method in class javax.swing.plaf.basic.BasicComboPopup

Overridden to unconditionally return false.

isFocusTraversable() - Method in class javax.swing.plaf.basic.BasicInternalFrameTitlePane.SystemMenuBar

isFocusTraversable() - Method in class javax.swing.plaf.basic.BasicArrowButton

isFocusTraversable() - Method in class javax.swing.plaf.metal.MetalComboBoxButton

isFocusTraversable(JComboBox) - Method in class javax.swing.plaf.ComboBoxUI

Determine whether or not the combo box itself is traversable

isFocusTraversable(JComboBox) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

Determines if the JComboBox is focus traversable.

isFocusTraversable(JComboBox) - Method in class javax.swing.plaf.metal.MetalComboBoxUI

isFocusTraversable(JComboBox) - Method in class javax.swing.plaf.multi.MultiComboBoxUI

Call isFocusTraversable on each UI handled by this MultiUI.

isFormatSupported(AudioFormat) - Method in class javax.sound.sampled.DataLine.Info

Indicates whether this data line supports a particular audio format.

isFreeStanding - Variable in class javax.swing.plaf.metal.MetalScrollBarUI

isGeneral() - Method in class javax.swing.text.html.parser.Entity

Return true if it is a parameter entity.

isGraphicsConfigSupported(GraphicsConfiguration) - Method in class java.awt.GraphicsConfigTemplate

Returns a boolean indicating whether or not the specified GraphicsConfiguration can be used to create a drawing surface that supports the indicated features.

isGroupingUsed() - Method in class java.text.NumberFormat

Returns true if grouping is used in this format.

isGuiAvailable() - Static method in class java.beans.Beans

Determines whether beans can assume a GUI is available.

isHidden() - Method in class java.beans.FeatureDescriptor

The "hidden" flag is used to identify features that are intended only for tool use, and which should not be exposed to humans.

isHidden() - Method in class java.io.File

Tests whether the file named by this abstract pathname is a hidden file.

isHidden(File) - Method in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

isHiddenFile(File) - Method in class javax.swing.filechooser.FileSystemView

Returns whether a file is hidden or not.

isHorizontal() - Method in class java.awt.ComponentOrientation

Are lines horizontal? This will return true for horizontal, left-to-right writing systems such as Roman.

isHTMLString(String) - Static method in class javax.swing.plaf.basic.BasicHTML

Check the given string to see if it should trigger the html rendering logic in a non-text component that supports html rendering.

isIcon - Variable in class javax.swing.JInternalFrame

The frame has been iconized.

isIcon() - Method in class javax.swing.JInternalFrame

Returns whether the JInternalFrame is currently iconified.

isIconifiable() - Method in class javax.swing.JInternalFrame

Returns whether the `JInternalFrame` can be iconified by some user action.
`isIconOnly()` - Method in class `javax.swing.plaf.metal.MetalComboBoxButton`

`isIdentifierIgnorable(char)` - Static method in class `java.lang.Character`

Determines if the specified character should be regarded as an ignorable character in a Java identifier or a Unicode identifier.

`isIdentity()` - Method in class `java.awt.geom.AffineTransform`

Returns `true` if this `AffineTransform` is an identity transform.

`isInDefaultEventSet()` - Method in class `java.beans.EventSetDescriptor`

Report if an event set is in the "default set".

`isindex` - Variable in class `javax.swing.text.html.parser.DTD`

`ISINDEX` - Static variable in class `javax.swing.text.html.HTML.Tag`

`isIndexSelected(int)` - Method in class `java.awt.List`

Determines if the specified item in this scrolling list is selected.

`isInfinite()` - Method in class `java.lang.Float`

Returns `true` if this `Float` value is infinitely large in magnitude.

`isInfinite()` - Method in class `java.lang.Double`

Returns `true` if this `Double` value is infinitely large in magnitude.

`isInfinite(double)` - Static method in class `java.lang.Double`

Returns `true` if the specified number is infinitely large in magnitude.

`isInfinite(float)` - Static method in class `java.lang.Float`

Returns `true` if the specified number is infinitely large in magnitude.

`isInherited()` - Method in class `javax.swing.text.html.CSS.Attribute`

Indicates if the attribute should be inherited from the parent or not.

`isInProgress()` - Method in class `javax.swing.undo.CompoundEdit`

Returns `true` if this edit is in progress--that is, it has not received end.

`isInstance(Object)` - Method in class `java.lang.Class`

Determines if the specified `Object` is assignment-compatible with the object represented by this `Class`.

`isInstanceOf(Object, Class)` - Static method in class `java.beans.Beans`

Check if a bean can be viewed as a given target type.

`isInterface()` - Method in class `java.lang.Class`

Determines if the specified `Class` object represents an interface type.

`isInterface(int)` - Static method in class `java.lang.reflect.Modifier`

Return `true` if the specifier integer includes the interface modifier.

`isInterrupted()` - Method in class `java.lang.Thread`

Tests whether this thread has been interrupted.

`isISOControl(char)` - Static method in class `java.lang.Character`

Determines if the specified character is an ISO control character.

`isItalic()` - Method in class `java.awt.Font`

Indicates whether or not this `Font` object's style is `ITALIC`.

`isItalic(AttributeSet)` - Static method in class `javax.swing.text.StyleConstants`

Checks whether the italic attribute is set.

`isJavaIdentifierPart(char)` - Static method in class `java.lang.Character`

Determines if the specified character may be part of a Java identifier as other than the first character.

`isJavaIdentifierStart(char)` - Static method in class `java.lang.Character`

Determines if the specified character is permissible as the first character in a Java identifier.

isJavaLetter(char) - Static method in class java.lang.Character
 Deprecated. Replaced by *isJavaIdentifierStart(char)*.

isJavaLetterOrDigit(char) - Static method in class java.lang.Character
 Deprecated. Replaced by *isJavaIdentifierPart(char)*.

isJavaMimeType(String) - Static method in class java.awt.datatransfer.SystemFlavorMap

isKeyBindingActive() - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

isKeyBindingRegistered() - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

isKeyDown - Variable in class javax.swing.plaf.basic.BasicTreeUI.KeyHandler
 Set to true while keyPressed is active.

isKeyEntry(String) - Method in class java.security.KeyStore
 Returns true if the entry identified by the given alias is a *key entry*, and false otherwise.

isLargeModel() - Method in class javax.swing.JTree
 Returns true if the tree is configured for a large model.

isLargeModel() - Method in class javax.swing.plaf.basic.BasicTreeUI

isLast() - Method in interface java.sql.ResultSet
 Indicates whether the cursor is on the last row of this ResultSet object.

isLayoutValid() - Method in class javax.swing.text.AsyncBoxView.ChildState
 Has the child view been laid out.

isLeadAnchorNotificationEnabled() - Method in class javax.swing.DefaultListSelectionModel
 Returns the value of the leadAnchorNotificationEnabled flag.

isLeadingEdge() - Method in class java.awt.font.TextHitInfo
 Returns true if the leading edge of the character was hit.

isLeaf() - Method in class javax.swing.JTree.DynamicUtilTreeNode
 Returns true if this node allows children.

isLeaf() - Method in interface javax.swing.text.Element
 Is this element a leaf element?

isLeaf() - Method in class javax.swing.text.AbstractDocument.AbstractElement
 Checks whether the element is a leaf.

isLeaf() - Method in class javax.swing.text.AbstractDocument.BranchElement
 Checks whether the element is a leaf.

isLeaf() - Method in class javax.swing.text.AbstractDocument.LeafElement
 Checks whether the element is a leaf.

isLeaf() - Method in class javax.swing.tree.DefaultMutableTreeNode
 Returns true if this node has no children.

isLeaf() - Method in interface javax.swing.tree.TreeNode
 Returns true if the receiver is a leaf.

isLeaf(int) - Method in class javax.swing.plaf.basic.BasicTreeUI

isLeaf(Object) - Method in interface javax.swing.tree.TreeModel
 Returns true if *node* is a leaf.

isLeaf(Object) - Method in class javax.swing.tree.DefaultTreeModel
 Returns whether the specified node is a leaf node.

isLeapYear(int) - Method in class java.util.GregorianCalendar

Determines if the given year is a leap year.

isLeftMouseButton(MouseEvent) - Static method in class javax.swing.SwingUtilities

Returns true if the mouse event specifies the left mouse button.

isLeftToRight() - Method in class java.awt.ComponentOrientation

HorizontalLines: Do items run left-to-right?

Vertical Lines: Do lines run left-to-right?

This will return true for horizontal, left-to-right writing systems such as Roman.

isLeftToRight() - Method in class java.awt.font.TextLayout

Returns true if this TextLayout has a left-to-right base direction or false if it has a right-to-left base direction.

isLenient() - Method in class java.text.DateFormat

Tell whether date/time parsing is to be lenient.

isLenient() - Method in class java.util.Calendar

Tell whether date/time interpretation is to be lenient.

isLetter(char) - Static method in class java.lang.Character

Determines if the specified character is a letter.

isLetterOrDigit(char) - Static method in class java.lang.Character

Determines if the specified character is a letter or digit.

isLigature() - Method in class java.awt.font.GlyphMetrics

Returns true if this is a ligature glyph.

isLight - Variable in class javax.swing.plaf.metal.MetalIconFactory.TreeControlIcon

isLightweight() - Method in class java.awt.Component

A lightweight component doesn't have a native toolkit peer.

isLightweightComponent(Component) - Static method in class javax.swing.JComponent

Returns true if this component is a lightweight, that is, if it doesn't have a native window system peer.

isLightWeightPopupEnabled() - Method in class javax.swing.ToolTipManager

Returns true if lightweight (all-Java) Tooltips are in use, or false if heavyweight (native peer) Tooltips are being used.

isLightWeightPopupEnabled() - Method in class javax.swing.JPopupMenu

Returns true if light weight (all-Java) popups are in use, or false if heavy weight (native peer) popups are being used.

isLightWeightPopupEnabled() - Method in class javax.swing.JComboBox

Returns true if lightweight (all-Java) popups are in use, or false if heavyweight (native peer) popups are being used.

isLineEmpty() - Method in class javax.swing.text.AbstractWriter

Returns true if the current line should be considered empty.

isLineSupported(Line.Info) - Method in interface javax.sound.sampled.Mixer

Indicates whether the mixer supports a line (or lines) that match the specified Line.Info object.

isLineSupported(Line.Info) - Static method in class javax.sound.sampled.AudioSystem

Indicates whether the the system supports any lines that match the specified Line.Info object.

isLocal - Variable in class java.awt.dnd.DropTargetContext.TransferableProxy

A boolean indicating if the DragSource is in the same JVM as the DropTarget.

isLocal(Stub) - Static method in class javax.rmi.CORBA.Util

Returns true if the stub is in the same ORB instance as is the servant.

isLocal(Stub) - Method in interface javax.rmi.CORBA.UtilDelegate

Delegation call for Util.isLocal(javax.rmi.CORBA.Stub).
isLocallyDefined(KeyStroke) - Method in interface javax.swing.text.Keymap
 Determines if the given key sequence is locally defined.
isLocalTransfer() - Method in class java.awt.dnd.DropTargetDropEvent
 This method returns an int indicating if the source is in the same JVM as the target.
isLocationInExpandControl(int, int, int, int) - Method in class javax.swing.plaf.metal.MetalTreeUI

isLocationInExpandControl(TreePath, int, int) - Method in class javax.swing.plaf.basic.BasicTreeUI
 Returns true if mouseX and mouseY fall in the area of row that is used to expand/collapse the node and the node at row does not represent a leaf.
isLowerCase(char) - Static method in class java.lang.Character
 Determines if the specified character is a lowercase character.
isManagingFocus() - Method in class javax.swing.JComponent
 Override this method and return true if your JComponent manages focus.
isManagingFocus() - Method in class javax.swing.JEditorPane
 Turns off tab traversal once focus is gained.
isManagingFocus() - Method in class javax.swing.JTable
 We override this method, whose implementation in JComponent returns false, to return true.
isManagingFocus() - Method in class javax.swing.JMenuBar
 Returns true to indicate that this component manages focus events internally.
isManagingFocus() - Method in class javax.swing.JTextArea
 Turns off tab traversal once focus is gained.
ISMAP - Static variable in class javax.swing.text.html.HTML.Attribute

isMaximizable() - Method in class javax.swing.JInternalFrame
 Returns whether the JInternalFrame can be maximized by some user action.
isMaximum - Variable in class javax.swing.JInternalFrame
 The frame has been expanded to its maximum size.
isMaximum() - Method in class javax.swing.JInternalFrame
 Returns whether the JInternalFrame is currently maximized.
isMaximumSizeSet() - Method in class javax.swing.JComponent
 Returns true if the maximum size has been set to a non-null value otherwise returns false.
isMember(Principal) - Method in interface java.security.acl.Group
 Returns true if the passed principal is a member of the group.
isMenuComponent(Component) - Method in class javax.swing.JMenu
 Returns true if the specified component exists in the submenu hierarchy.
isMetaDown() - Method in class java.awt.event.InputEvent
 Returns whether or not the Meta modifier is down on this event.
isMiddleMouseButton(MouseEvent) - Static method in class javax.swing.SwingUtilities
 Returns true if the mouse event specifies the middle mouse button.
isMimeTypeEqual(DataFlavor) - Method in class java.awt.datatransfer.DataFlavor
 Compare the mimeType of two DataFlavor objects no parameters are considered
isMimeTypeEqual(String) - Method in class java.awt.datatransfer.DataFlavor
 Returns whether the string representation of the MIME type passed in is equivalent to the MIME type of this DataFlavor.
isMimeTypeSerializedObject() - Method in class java.awt.datatransfer.DataFlavor
 does the DataFlavor represent a serialized object?

isMinimumSizeDirty - Variable in class javax.swing.plaf.basic.BasicComboBoxUI

isMinimumSizeSet() - Method in class javax.swing.JComponent

Returns true if the minimum size has been set to a non-null value otherwise returns false.

isMixerSupported(Mixer.Info) - Method in class javax.sound.sampled.spi.MixerProvider

Indicates whether the mixer provider supports the mixer represented by the specified mixer info object.

isModal() - Method in class java.awt.Dialog

Indicates whether the dialog is modal.

isMulticastAddress() - Method in class java.net.InetAddress

Utility routine to check if the InetAddress is an IP multicast address.

isMultipleMode() - Method in class java.awt.List

Determines whether this list allows multiple selections.

isMultiSelectEvent(MouseEvent) - Method in class javax.swing.plaf.basic.BasicTreeUI

Returning true signifies a mouse event on the node should select from the anchor point.

isMultiSelectionEnabled() - Method in class javax.swing.JFileChooser

Returns true if multiple files can be selected.

isNaN() - Method in class java.lang.Float

Returns true if this Float value is Not-a-Number (NaN).

isNaN() - Method in class java.lang.Double

Returns true if this Double value is the special Not-a-Number (NaN) value.

isNaN(double) - Static method in class java.lang.Double

Returns true if the specified number is the special Not-a-Number (NaN) value.

isNaN(float) - Static method in class java.lang.Float

Returns true if the specified number is the special Not-a-Number (NaN) value.

isNative(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the native modifier.

isNativeLookAndFeel() - Method in class javax.swing.LookAndFeel

If the underlying platform has a "native" look and feel, and this is an implementation of it, return true.

isNativeLookAndFeel() - Method in class javax.swing.plaf.metal.MetalLookAndFeel

isNativeLookAndFeel() - Method in class javax.swing.plaf.multi.MultiLookAndFeel

isNavigationKey(int) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

Returns whether or not the supplied keyCode maps to a key that is used for navigation.

isNegative() - Method in interface java.security.acl.AclEntry

Returns true if this is a negative ACL entry (one denying the associated principal the set of permissions in the entry), false otherwise.

isNodeAncestor(TreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if anotherNode is an ancestor of this node -- if it is this node, this node's parent, or an ancestor of this node's parent.

isNodeChild(TreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if aNode is a child of this node.

isNodeDescendant(DefaultMutableTreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if anotherNode is a descendant of this node -- if it is this node, one of this node's children, or a descendant of one of this node's children.

isNodeRelated(DefaultMutableTreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if and only if aNode is in the same tree as this node.

insertText(String, int) - Method in class java.awt.TextArea

Deprecated. *As of JDK version 1.1, replaced by insert(String, int).*

insertUpdate(AbstractDocument.DefaultDocumentEvent, AttributeSet) - Method in class javax.swing.text.AbstractDocument

Updates document structure as a result of text insertion.

insertUpdate(AbstractDocument.DefaultDocumentEvent, AttributeSet) - Method in class javax.swing.text.PlainDocument

Updates document structure as a result of text insertion.

insertUpdate(AbstractDocument.DefaultDocumentEvent, AttributeSet) - Method in class javax.swing.text.DefaultStyledDocument

Updates document structure as a result of text insertion.

insertUpdate(AbstractDocument.DefaultDocumentEvent, AttributeSet) - Method in class javax.swing.text.html.HTMLDocument

Updates document structure as a result of text insertion.

insertUpdate(DefaultStyledDocument.ElementSpec[]) - Method in class javax.swing.text.DefaultStyledDocument.ElementBuffer

Inserts an update into the document.

insertUpdate(DocumentEvent) - Method in interface javax.swing.event.DocumentListener

Gives notification that there was an insert into the document.

insertUpdate(DocumentEvent) - Method in class

javax.swing.text.JTextComponent.AccessibleJTextComponent

Handles document insert (fire appropriate property change event which is AccessibleContext.ACCESSIBLE_TEXT_PROPERTY).

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.View

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.GlyphView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.FlowView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.PlainView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.FieldView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.WrappedPlainView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(DocumentEvent, Shape, ViewFactory) - Method in class javax.swing.text.ZoneView

Gives notification that something was inserted into the document in a location that this view is responsible for.

insertUpdate(FlowView, DocumentEvent, Rectangle) - Method in class

javax.swing.text.FlowView.FlowStrategy

Gives notification that something was inserted into the document in a location that the given flow view

is responsible for.

insetCache - Variable in class javax.swing.plaf.basic.BasicSliderUI

insets - Variable in class java.awt.GridBagConstraints

This field specifies the external padding of the component, the minimum amount of space between the component and the edges of its display area.

Insets - class java.awt.Insets.

An Insets object is a representation of the borders of a container.

insets() - Method in class java.awt.Container

Deprecated. *As of JDK version 1.1, replaced by getInsets().*

Insets(int, int, int, int) - Constructor for class java.awt.Insets

Creates and initializes a new Insets object with the specified top, left, bottom, and right insets.

InsetsUIResource - class javax.swing.plaf.InsetsUIResource.

InsetsUIResource(int, int, int, int) - Constructor for class javax.swing.plaf.InsetsUIResource

inside(int, int) - Method in class java.awt.Component

Deprecated. *As of JDK version 1.1, replaced by contains(int, int).*

inside(int, int) - Method in class java.awt.Polygon

Deprecated. *As of JDK version 1.1, replaced by contains(int, int).*

inside(int, int) - Method in class java.awt.Rectangle

Deprecated. *As of JDK version 1.1, replaced by contains(int, int).*

insideBorder - Variable in class javax.swing.border.CompoundBorder

install(JEditorPane) - Method in class javax.swing.text.EditorKit

Called when the kit is being installed into the a JEditorPane.

install(JEditorPane) - Method in class javax.swing.text.StyledEditorKit

Called when the kit is being installed into a JEditorPane.

install(JEditorPane) - Method in class javax.swing.text.html.HTMLEditorKit

Called when the kit is being installed into the a JEditorPane.

install(JTextComponent) - Method in interface javax.swing.text.Highlighter

Called when the UI is being installed into the interface of a JTextComponent.

install(JTextComponent) - Method in class javax.swing.text.DefaultHighlighter

Called when the UI is being installed into the interface of a JTextComponent.

install(JTextComponent) - Method in class javax.swing.text.DefaultCaret

Called when the UI is being installed into the interface of a JTextComponent.

install(JTextComponent) - Method in interface javax.swing.text.Caret

Called when the UI is being installed into the interface of a JTextComponent.

installAncestorListener() - Method in class javax.swing.JComboBox

installBorder(JComponent, String) - Static method in class javax.swing.LookAndFeel

Convenience method for installing a component's default Border object on the specified component if either the border is currently null or already an instance of UIResource.

installChooserPanel(JColorChooser) - Method in class javax.swing.colorchooser.AbstractColorChooserPanel

Invoked when the panel is added to the chooser.

installColors(JComponent, String, String) - Static method in class javax.swing.LookAndFeel

Convenience method for initializing a component's foreground and background color properties with

values from the current defaults table.

[installColorsAndFont\(JComponent, String, String, String\)](#) - Static method in class [javax.swing.LookAndFeel](#)
Convenience method for initializing a components foreground background and font properties with values from the current defaults table.

[installComboBoxListeners\(\)](#) - Method in class [javax.swing.plaf.basic.BasicComboPopup](#)

This method adds the necessary listeners to the JComboBox.

[installComboBoxModelListeners\(ComboBoxModel\)](#) - Method in class [javax.swing.plaf.basic.BasicComboPopup](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicOptionPaneUI](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicScrollBarUI](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicToolBarUI](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicInternalFrameUI](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicComboBoxUI](#)

The editor and arrow button are added to the JComboBox here.

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)

Intalls the subcomponents of the tree, which is the renderer pane.

[installComponents\(\)](#) - Method in class [javax.swing.plaf.basic.BasicDesktopIconUI](#)

[installComponents\(\)](#) - Method in class [javax.swing.plaf.metal.MetalDesktopIconUI](#)

[installComponents\(JFileChooser\)](#) - Method in class [javax.swing.plaf.basic.BasicFileChooserUI](#)

[installComponents\(JFileChooser\)](#) - Method in class [javax.swing.plaf.metal.MetalFileChooserUI](#)

[installComponents\(JLabel\)](#) - Method in class [javax.swing.plaf.basic.BasicLabelUI](#)

[installComponents\(JMenuItem\)](#) - Method in class [javax.swing.plaf.basic.BasicMenuItemUI](#)

[installComponents\(JRootPane\)](#) - Method in class [javax.swing.plaf.basic.BasicRootPaneUI](#)

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTextUI](#)

Initializes component properties, e.g.

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicMenuItemUI](#)

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicRadioButtonMenuItemUI](#)

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicMenuUI](#)

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicProgressBarUI](#)

[installDefaults\(\)](#) - Method in class [javax.swing.plaf.basic.BasicOptionPaneUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicCheckBoxMenuItemUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicPopupMenuUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableUI](#)

Initialize JTable properties, e.g.

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameTitlePane](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollBarUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopPaneUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicListUI](#)

Initialize JList properties, e.g.

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

Installs the default colors, default font, default renderer, and default editor into the JComboBox.

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableHeaderUI](#)

Initialize JTableHeader properties, e.g.

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuBarUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicColorChooserUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)

Installs the UI defaults.

[installDefaults\(\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopIconUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTabbedPaneUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.metal.[MetalInternalFrameTitlePane](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.metal.[MetalScrollBarUI](#)

[installDefaults\(\)](#) - Method in class javax.swing.plaf.metal.[MetalDesktopIconUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.basic.[BasicRadioButtonUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.metal.[MetalToggleButtonUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.metal.[MetalRadioButtonUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.metal.[MetalButtonUI](#)

[installDefaults\(AbstractButton\)](#) - Method in class javax.swing.plaf.metal.[MetalCheckBoxUI](#)

[installDefaults\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicViewportUI](#)

[installDefaults\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolTipUI](#)

[installDefaults\(JFileChooser\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[installDefaults\(JLabel\)](#) - Method in class javax.swing.plaf.basic.[BasicLabelUI](#)

[installDefaults\(JPanel\)](#) - Method in class javax.swing.plaf.basic.[BasicPanelUI](#)

[installDefaults\(JRootPane\)](#) - Method in class javax.swing.plaf.basic.[BasicRootPaneUI](#)

[installDefaults\(JScrollPane\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollPaneUI](#)

[installDefaults\(JSeparator\)](#) - Method in class javax.swing.plaf.basic.[BasicSeparatorUI](#)

[installDefaults\(JSeparator\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarSeparatorUI](#)

[installDefaults\(JSeparator\)](#) - Method in class javax.swing.plaf.metal.[MetalSeparatorUI](#)

[installDefaults\(JSlider\)](#) - Method in class javax.swing.plaf.basic.[BasicSliderUI](#)

[installDesktopManager\(\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopPaneUI](#)

[installIcons\(JFileChooser\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTextUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicEditorPaneUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuItemUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboPopup](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicOptionPaneUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicPopupMenuUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableUI](#)

Register all keyboard actions on the JTable.

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollBarUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopPaneUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicListUI](#)

Register keyboard actions for the up and down arrow keys.

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

Adds keyboard actions to the JComboBox.

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableHeaderUI](#)

Register all keyboard actions on the JTableHeader.

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuBarUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)

Installs the keyboard actions for the UI.

[installKeyboardActions\(\)](#) - Method in class javax.swing.plaf.metal.[MetalInternalFrameUI](#)

[installKeyboardActions\(AbstractButton\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonUI](#)

[installKeyboardActions\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonListener](#)

Register default key actions: pressing space to "click" a button and registering the keyboard mnemonic (if any).

[installKeyboardActions\(JLabel\)](#) - Method in class javax.swing.plaf.basic.[BasicLabelUI](#)

[installKeyboardActions\(JRootPane\)](#) - Method in class javax.swing.plaf.basic.[BasicRootPaneUI](#)

[installKeyboardActions\(JScrollPane\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollPaneUI](#)

[installKeyboardActions\(JSlider\)](#) - Method in class javax.swing.plaf.basic.[BasicSliderUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTextUI](#)

Installs listeners for the UI.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuItemUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicProgressBarUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicOptionPaneUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicPopupMenuUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableUI](#)

Attaches listeners to the JTable.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameTitlePane](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollBarUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicListUI](#)

Create and install the listeners for the JList, its model, and its selectionModel.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

Attaches listeners to the JComboBox and JComboBoxModel.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTableHeaderUI](#)

Attaches listeners to the JTableHeader.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuBarUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicColorChooserUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)

Installs the event listeners for the UI.

[installListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopIconUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.metal.[MetalComboBoxUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.metal.[MetalScrollBarUI](#)

[installListeners\(\)](#) - Method in class javax.swing.plaf.metal.[MetalToolBarUI](#)

[installListeners\(AbstractButton\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonUI](#)

[installListeners\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolTipUI](#)

[installListeners\(JFileChooser\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[installListeners\(JFileChooser\)](#) - Method in class javax.swing.plaf.metal.[MetalFileChooserUI](#)

[installListeners\(JLabel\)](#) - Method in class javax.swing.plaf.basic.[BasicLabelUI](#)

[installListeners\(JRootPane\)](#) - Method in class javax.swing.plaf.basic.[BasicRootPaneUI](#)

[installListeners\(JScrollPane\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollPaneUI](#)

[installListeners\(JScrollPane\)](#) - Method in class javax.swing.plaf.metal.[MetalScrollPaneUI](#)

[installListeners\(JSeparator\)](#) - Method in class javax.swing.plaf.basic.[BasicSeparatorUI](#)

[installListeners\(JSlider\)](#) - Method in class javax.swing.plaf.basic.[BasicSliderUI](#)

[installListListeners\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboPopup](#)

Called by `configureList()` to add the necessary listeners to the list.

[installLookAndFeel\(String, String\)](#) - Static method in class javax.swing.[UIManager](#)

Creates a new look and feel and adds it to the current array.

[installLookAndFeel\(UIManager.LookAndFeelInfo\)](#) - Static method in class javax.swing.[UIManager](#)

Adds the specified look and feel to the current array and then calls

`UIManager.setInstalledLookAndFeels(javax.swing.UIManager.LookAndFeelInfo[])`.

[installMouseHandlers\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[installNonRolloverBorders\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalToolBarUI](#)

[installNormalBorders\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalToolBarUI](#)

[installPreviewPanel\(\)](#) - Method in class javax.swing.plaf.basic.[BasicColorChooserUI](#)

[installRolloverBorders\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalToolBarUI](#)

[installStrings\(JFileChooser\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[installStrings\(JFileChooser\)](#) - Method in class javax.swing.plaf.metal.[MetalFileChooserUI](#)

[installTitlePane\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameTitlePane](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.[ComponentUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTextUI](#)

Installs the UI for a component.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicSeparatorUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuItemUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicProgressBarUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicOptionPaneUI](#)

Installs the receiver as the L&F for the passed in JOptionPane

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicPanelUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicPopupMenuUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTableUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicViewportUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolTipUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollBarUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopPaneUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicListUI](#)
 Initializes this list by calling `installDefaults()`, `installListeners()`, and `installKeyboardActions()` in order.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicLabelUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTableHeaderUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuBarUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicColorChooserUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)
 Installs the UI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollPaneUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicRootPaneUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicDesktopIconUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicSliderUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalTreeUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalTextFieldUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalFileChooserUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalInternalFrameUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalComboBoxUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalSliderUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalToolBarUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalScrollPaneUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.metal.[MetalToolTipUI](#)

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiListUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiSeparatorUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiLabelUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiPopupMenuUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiPanelUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiScrollBarUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTextUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiComboBoxUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTableHeaderUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiFileChooserUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiColorChooserUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTreeUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiViewportUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTabbedPaneUI](#)
 Call [installUI](#) on each UI handled by this [MultiUI](#).

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiProgressBarUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiScrollPaneUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiOptionPaneUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiSplitPaneUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiButtonUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiToolBarUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiSliderUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiDesktopPaneUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTableUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiDesktopIconUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiMenuItemUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiInternalFrameUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiToolTipUI](#)
 Call installUI on each UI handled by this MultiUI.

[installUI\(JComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiMenuBarUI](#)
 Call installUI on each UI handled by this MultiUI.

[instanceFollowRedirects](#) - Variable in class java.net.[HttpURLConnection](#)
 If true, the protocol will automatically follow redirects.

[instantiate\(ClassLoader, String\)](#) - Static method in class java.beans.[Beans](#)
 Instantiate a JavaBean.

[instantiate\(ClassLoader, String, BeanContext\)](#) - Static method in class java.beans.[Beans](#)
 Instantiate a JavaBean.

[instantiate\(ClassLoader, String, BeanContext, AppletInitializer\)](#) - Static method in class java.beans.[Beans](#)
 Instantiate a bean.

[instantiateChild\(String\)](#) - Method in class java.beans.beancontext.[BeanContextSupport](#)
 The instantiateChild method is a convenience hook in BeanContext to simplify the task of instantiating a Bean, nested, into a BeanContext.

[instantiateChild\(String\)](#) - Method in interface java.beans.beancontext.[BeanContext](#)
 Instantiate the javaBean named as a child of this BeanContext.

[InstantiationError](#) - error java.lang.[InstantiationError](#).
 Thrown when an application tries to use the Java new construct to instantiate an abstract class or an interface.

[InstantiationError\(\)](#) - Constructor for class java.lang.[InstantiationError](#)
 Constructs an InstantiationError with no detail message.

[InstantiationError\(String\)](#) - Constructor for class java.lang.[InstantiationError](#)

Constructs an `InstantiationException` with the specified detail message.

`InstantiationException` - exception `java.langInstantiationException`.

Thrown when an application tries to create an instance of a class using the `newInstance` method in class `Class`, but the specified class object cannot be instantiated because it is an interface or is an abstract class.

`InstantiationException()` - Constructor for class `java.langInstantiationException`

Constructs an `InstantiationException` with no detail message.

`InstantiationException(String)` - Constructor for class `java.langInstantiationException`

Constructs an `InstantiationException` with the specified detail message.

`Instrument` - class `javax.sound.midi.Instrument`.

An instrument is a sound-synthesis algorithm with certain parameter settings, usually designed to emulate a specific real-world musical instrument or to achieve a specific sort of sound effect.

`Instrument(Soundbank, Patch, String, Class)` - Constructor for class `javax.sound.midi.Instrument`

Constructs a new MIDI instrument from the specified sound bank, bank index, and program index.

`InsufficientResourcesException` - exception `javax.naming.InsufficientResourcesException`.

This exception is thrown when resources are not available to complete the requested operation.

`InsufficientResourcesException()` - Constructor for class `javax.naming.InsufficientResourcesException`

Constructs a new instance of `InsufficientResourcesException` with all name resolution fields and explanation initialized to null.

`InsufficientResourcesException(String)` - Constructor for class `javax.naming.InsufficientResourcesException`

Constructs a new instance of `InsufficientResourcesException` using an explanation.

`insureRowContinuity()` - Method in class `javax.swing.tree.DefaultTreeSelectionModel`

Makes sure the currently selected `TreePaths` are valid for the current selection mode.

`insureUniqueness()` - Method in class `javax.swing.tree.DefaultTreeSelectionModel`

This method is obsolete and its implementation is now a noop.

`intBitsToFloat(int)` - Static method in class `java.lang.Float`

Returns the single-float corresponding to a given bit representation.

`Integer` - class `java.lang.Integer`.

The `Integer` class wraps a value of the primitive type `int` in an object.

`INTEGER` - Static variable in class `java.sql.Types`

The constant in the Java programming language, sometimes referred to as a type code, that identifies the generic SQL type `INTEGER`.

`INTEGER_FIELD` - Static variable in class `java.text.NumberFormat`

Field constant used to construct a `FieldPosition` object.

`Integer(int)` - Constructor for class `java.lang.Integer`

Constructs a newly allocated `Integer` object that represents the primitive `int` argument.

`Integer(String)` - Constructor for class `java.lang.Integer`

Constructs a newly allocated `Integer` object that represents the value represented by the string.

`INTERFACE` - Static variable in class `java.lang.reflect.Modifier`

The `int` value representing the interface modifier.

`intern()` - Method in class `java.lang.String`

Returns a canonical representation for the string object.

`INTERNAL` - exception `org.omg.CORBA.INTERNAL`.

The CORBA `INTERNAL` exception, which is thrown when there is an ORB internal error.

`INTERNAL_CLOCK` - Static variable in class `javax.sound.midi.Sequencer.SyncMode`

A master synchronization mode that makes the sequencer get its timing information from its internal clock.

INTERNAL_FRAME - Static variable in class javax.accessibility.AccessibleRole

A frame-like object that is clipped by a desktop pane.

INTERNAL_FRAME_ACTIVATED - Static variable in class javax.swing.event.InternalFrameEvent

The window activated event type.

INTERNAL_FRAME_CLOSED - Static variable in class javax.swing.event.InternalFrameEvent

The window closed event.

INTERNAL_FRAME_CLOSING - Static variable in class javax.swing.event.InternalFrameEvent

The "window is closing" event.

INTERNAL_FRAME_DEACTIVATED - Static variable in class javax.swing.event.InternalFrameEvent

The window deactivated event type.

INTERNAL_FRAME_DEICONIFIED - Static variable in class javax.swing.event.InternalFrameEvent

The window deiconified event type.

INTERNAL_FRAME_FIRST - Static variable in class javax.swing.event.InternalFrameEvent

The first number in the range of ids used for window events.

INTERNAL_FRAME_ICONIFIED - Static variable in class javax.swing.event.InternalFrameEvent

The window iconified event.

INTERNAL_FRAME_LAST - Static variable in class javax.swing.event.InternalFrameEvent

The last number in the range of ids used for window events.

INTERNAL_FRAME_OPENED - Static variable in class javax.swing.event.InternalFrameEvent

The window opened event.

INTERNAL() - Constructor for class org.omg.CORBA.INTERNAL

Constructs an INTERNAL exception with a default minor code of 0 and a completion state of COMPLETED_MAYBE.

INTERNAL(int, CompletionStatus) - Constructor for class org.omg.CORBA.INTERNAL

Constructs an INTERNAL exception with the specified minor code and completion status.

INTERNAL(String) - Constructor for class org.omg.CORBA.INTERNAL

Constructs an INTERNAL exception with the specified detail message, a minor code of 0, and a completion state of COMPLETED_NO.

INTERNAL(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INTERNAL

Constructs an INTERNAL exception with the specified detail message, minor code, and completion status.

InternalError - error java.lang.InternalError.

Thrown to indicate some unexpected internal error has occurred in the Java Virtual Machine.

InternalError() - Constructor for class java.lang.InternalError

Constructs an InternalError with no detail message.

InternalError(String) - Constructor for class java.lang.InternalError

Constructs an InternalError with the specified detail message.

internalFrameActivated(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame is activated.

internalFrameActivated(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame is activated.

internalFrameActivated(InternalFrameEvent) - Method in class javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

InternalFrameAdapter - class javax.swing.event.InternalFrameAdapter.

An abstract adapter class for receiving internal frame events.

InternalFrameAdapter() - Constructor for class javax.swing.event.InternalFrameAdapter

internalFrameClosed(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame has been closed.

internalFrameClosed(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame has been closed.

internalFrameClosed(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

internalFrameClosing(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame is in the process of being closed.

internalFrameClosing(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame is in the process of being closed.

internalFrameClosing(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

internalFrameDeactivated(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame is de-activated.

internalFrameDeactivated(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame is de-activated.

internalFrameDeactivated(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

internalFrameDeiconified(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame is de-iconified.

internalFrameDeiconified(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame is de-iconified.

internalFrameDeiconified(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

InternalFrameEvent - class javax.swing.event.InternalFrameEvent.

InternalFrameEvent: an AWTEvent which adds support for JInternalFrame objects as the event source.

InternalFrameEvent(JInternalFrame, int) - Constructor for class javax.swing.event.InternalFrameEvent

Constructs a InternalFrameEvent object.

internalFrameIconified(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame is iconified.

internalFrameIconified(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when an internal frame is iconified.

internalFrameIconified(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

internalFrameLayout - Variable in class javax.swing.plaf.basic.BasicInternalFrameUI

InternalFrameListener - interface javax.swing.event.InternalFrameListener.

The listener interface for receiving internal frame events.

internalFrameOpened(InternalFrameEvent) - Method in class javax.swing.event.InternalFrameAdapter

Invoked when an internal frame has been opened.

internalFrameOpened(InternalFrameEvent) - Method in interface javax.swing.event.InternalFrameListener

Invoked when a internal frame has been opened.

internalFrameOpened(InternalFrameEvent) - Method in class

javax.swing.plaf.basic.BasicInternalFrameUI.BasicInternalFrameListener

InternalFrameUI - class javax.swing.plaf.InternalFrameUI.

Pluggable look and feel interface for JInternalFrame.

InternalFrameUI() - Constructor for class javax.swing.plaf.InternalFrameUI

internalGet(int) - Method in class java.util.Calendar

Gets the value for a given time field.

interrupt() - Method in class java.lang.ThreadGroup

Interrupts all threads in this thread group.

interrupt() - Method in class java.lang.Thread

Interrupts this thread.

interrupted() - Static method in class java.lang.Thread

Tests whether the current thread has been interrupted.

InterruptedException - exception java.lang InterruptedException.

Thrown when a thread is waiting, sleeping, or otherwise paused for a long time and another thread interrupts it using the interrupt method in class Thread.

InterruptedException() - Constructor for class java.lang InterruptedException

Constructs an InterruptedException with no detail message.

InterruptedException(String) - Constructor for class java.lang InterruptedException

Constructs an InterruptedException with the specified detail message.

InterruptedIOException - exception java.io InterruptedException.

Signals that an I/O operation has been interrupted.

InterruptedIOException() - Constructor for class java.io InterruptedException

Constructs an InterruptedIOException with null as its error detail message.

InterruptedIOException(String) - Constructor for class java.io InterruptedException

Constructs an InterruptedIOException with the specified detail message.

InterruptedNamingException - exception javax.naming InterruptedException.

This exception is thrown when the naming operation being invoked has been interrupted.

InterruptedNamingException() - Constructor for class javax.naming InterruptedException

Constructs an instance of InterruptedNamingException with all name resolution fields and explanation initialized to null.

InterruptedNamingException(String) - Constructor for class javax.naming InterruptedException

Constructs an instance of InterruptedNamingException using an explanation of the problem.

intersect(Area) - Method in class java.awt.geom.Area

Sets the shape of this Area to the intersection of its current shape and the shape of the specified Area.

intersect(Rectangle2D, Rectangle2D, Rectangle2D) - Static method in class java.awt.geom.Rectangle2D

Intersects the pair of specified source Rectangle2D objects and puts the result into the specified destination Rectangle2D object.

intersection(Rectangle) - Method in class java.awt.Rectangle

Computes the intersection of this Rectangle with the specified Rectangle.

intersects(double, double, double, double) - Method in class java.awt.Polygon

Tests if the interior of this Polygon intersects the interior of a specified set of rectangular coordinates.

intersects(double, double, double, double) - Method in interface java.awt.Shape

Tests if the interior of the Shape intersects the interior of a specified rectangular area.

intersects(double, double, double, double) - Method in class java.awt.geom.Rectangle2D

Tests if the interior of this `Rectangle2D` intersects the interior of a specified set of rectangular coordinates.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.RoundRectangle2D`

Tests if the interior of this `RoundRectangle2D` intersects the interior of a specified set of rectangular coordinates.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.Area`

Tests whether the interior of this `Area` object intersects the interior of the specified rectangular area.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.Line2D`

Tests if this `Line2D` intersects the interior of a specified set of rectangular coordinates.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.Arc2D`

Determines whether or not the interior of the arc intersects the interior of the specified rectangle.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.Ellipse2D`

Tests if the interior of this `Ellipse2D` intersects the interior of a specified rectangular area.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.GeneralPath`

Tests if the interior of this `Shape` intersects the interior of a specified set of rectangular coordinates.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.QuadCurve2D`

Tests if the shape of this `QuadCurve2D` intersects the interior of a specified set of rectangular coordinates.

`intersects(double, double, double, double)` - Method in class `java.awt.geom.CubicCurve2D`

Tests if the shape intersects the interior of a specified set of rectangular coordinates.

`intersects(Rectangle)` - Method in class `java.awt.Rectangle`

Determines whether or not this `Rectangle` and the specified `Rectangle` intersect.

`intersects(Rectangle2D)` - Method in class `java.awt.Polygon`

Tests if the interior of this `Polygon` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in interface `java.awt.Shape`

Tests if the interior of the `Shape` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.RectangularShape`

Tests if the interior of the `Shape` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.Area`

Tests whether the interior of this `Area` object intersects the interior of the specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.Line2D`

Tests if this `Line2D` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.GeneralPath`

Tests if the interior of this `Shape` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.QuadCurve2D`

Tests if the shape of this `QuadCurve2D` intersects the interior of a specified `Rectangle2D`.

`intersects(Rectangle2D)` - Method in class `java.awt.geom.CubicCurve2D`

Tests if the shape intersects the interior of a specified `Rectangle2D`.

`intersectsLine(double, double, double, double)` - Method in class `java.awt.geom.Rectangle2D`

Tests if the specified line segment intersects the interior of this `Rectangle2D`.

`intersectsLine(double, double, double, double)` - Method in class `java.awt.geom.Line2D`

Tests if the line segment from (X1, Y1) to (X2, Y2) intersects this line segment.

`intersectsLine(Line2D)` - Method in class `java.awt.geom.Rectangle2D`

Tests if the specified line segment intersects the interior of this `Rectangle2D`.

`intersectsLine(Line2D)` - Method in class `java.awt.geom.Line2D`

Tests if the specified line segment intersects this line segment.

`INTERVAL_ADDED` - Static variable in class `javax.swing.event.ListDataEvent`

Identifies the addition of one or more contiguous items to the list

INTERVAL_REMOVED - Static variable in class javax.swing.event.ListDataEvent

Identifies the removal of one or more contiguous items from the list

intervalAdded(ListDataEvent) - Method in class javax.swing.JComboBox

Invoked items have been added to the internal data model.

intervalAdded(ListDataEvent) - Method in class javax.swing.JList.AccessibleJList

List Data Listener interval added method.

intervalAdded(ListDataEvent) - Method in interface javax.swing.event.ListDataListener

Sent after the indices in the index0,index1 interval have been inserted in the data model.

intervalAdded(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicComboPopup.ListDataHandler

intervalAdded(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicListUI.ListDataHandler

intervalAdded(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI.ListDataHandler

intervalAdded(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicDirectoryModel

intervalRemoved(ListDataEvent) - Method in class javax.swing.JComboBox

Invoked when values have been removed from the data model.

intervalRemoved(ListDataEvent) - Method in class javax.swing.JList.AccessibleJList

List Data Listener interval removed method.

intervalRemoved(ListDataEvent) - Method in interface javax.swing.event.ListDataListener

Sent after the indices in the index0,index1 interval have been removed from the data model.

intervalRemoved(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicComboPopup.ListDataHandler

intervalRemoved(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicListUI.ListDataHandler

intervalRemoved(ListDataEvent) - Method in class
javax.swing.plaf.basic.BasicComboBoxUI.ListDataHandler

intervalRemoved(ListDataEvent) - Method in class javax.swing.plaf.basic.BasicDirectoryModel

INTF_REPOS - exception org.omg.CORBA.INTF_REPOS.

The CORBA INTF_REPOS exception, which is thrown when there is an error accessing the interface repository.

INTF_REPOS() - Constructor for class org.omg.CORBA.INTF_REPOS

Constructs an INTF_REPOS exception with a default minor code of 0 and a completion state of COMPLETED_NO.

INTF_REPOS(int, CompletionStatus) - Constructor for class org.omg.CORBA.INTF_REPOS

Constructs an INTF_REPOS exception with the specified minor code and completion status.

INTF_REPOS(String) - Constructor for class org.omg.CORBA.INTF_REPOS

Constructs an INTF_REPOS exception with the specified detail.

INTF_REPOS(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INTF_REPOS

Constructs an INTF_REPOS exception with the specified detail message, minor code, and completion status.

IntHolder - class org.omg.CORBA.IntHolder.

A Holder class for an int that is used to store "out" and "inout" parameters in IDL methods.

IntHolder() - Constructor for class org.omg.CORBA.IntHolder

Constructs a new `IntHolder` object with its value field initialized to 0.

IntHolder(int) - Constructor for class `org.omg.CORBA.IntHolder`

Constructs a new `IntHolder` object with its value field initialized to the given `int`.

intKey() - Method in class `java.awt.RenderingHints.Key`

Returns the private integer key that the subclass instantiated this `Key` with.

IntrospectionException - exception `java.beans.IntrospectionException`.

Thrown when an exception happens during Introspection.

IntrospectionException(String) - Constructor for class `java.beans.IntrospectionException`

Constructs an `IntrospectionException` with a detailed message.

Introspector - class `java.beans.Introspector`.

The `Introspector` class provides a standard way for tools to learn about the properties, events, and methods supported by a target Java Bean.

intValue() - Method in class `java.lang.Number`

Returns the value of the specified number as an `int`.

intValue() - Method in class `java.lang.Long`

Returns the value of this `Long` as an `int`.

intValue() - Method in class `java.lang.Short`

Returns the value of this `Short` as an `int`.

intValue() - Method in class `java.lang.Float`

Returns the integer value of this `Float` (by casting to an `int`).

intValue() - Method in class `java.lang.Integer`

Returns the value of this `Integer` as an `int`.

intValue() - Method in class `java.lang.Byte`

Returns the value of this `Byte` as an `int`.

intValue() - Method in class `java.lang.Double`

Returns the integer value of this `Double` (by casting to an `int`).

intValue() - Method in class `java.math.BigInteger`

Converts this `BigInteger` to an `int`.

intValue() - Method in class `java.math.BigDecimal`

Converts this `BigDecimal` to an `int`.

INV_FLAG - exception `org.omg.CORBA.INV_FLAG`.

The `CORBA INV_FLAG` exception, which is thrown when an invalid flag is specified.

INV_FLAG() - Constructor for class `org.omg.CORBA.INV_FLAG`

Constructs an `INV_FLAG` exception with a default minor code of 0 and a completion state of `COMPLETED_NO`.

INV_FLAG(int, CompletionStatus) - Constructor for class `org.omg.CORBA.INV_FLAG`

Constructs an `INV_FLAG` exception with the specified minor code and completion status.

INV_FLAG(String) - Constructor for class `org.omg.CORBA.INV_FLAG`

Constructs an `INV_FLAG` exception with the specified detail message, a minor code of 0, and a completion state of `COMPLETED_NO`.

INV_FLAG(String, int, CompletionStatus) - Constructor for class `org.omg.CORBA.INV_FLAG`

Constructs an `INV_FLAG` exception with the specified detail message, minor code, and completion status.

INV_IDENT - exception `org.omg.CORBA.INV_IDENT`.

The `CORBA INV_IDENT` exception, which is thrown when identifier syntax is invalid.

INV_IDENT() - Constructor for class `org.omg.CORBA.INV_IDENT`

Constructs an `INV_IDENT` exception with a default minor code of 0 and a completion state of `COMPLETED_NO`.

INV_IDENT(int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_IDENT
Constructs an INV_IDENT exception with the specified minor code and completion status.

INV_IDENT(String) - Constructor for class org.omg.CORBA.INV_IDENT
Constructs an INV_IDENT exception with the specified detail message, a minor code of 0, and a completion state of COMPLETED_NO.

INV_IDENT(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_IDENT
Constructs an INV_IDENT exception with the specified detail message, minor code, and completion status.

INV_OBJREF - exception org.omg.CORBA.INV_OBJREF.
The CORBA INV_OBJREF exception, which is thrown when an invalid object reference is specified.

INV_OBJREF() - Constructor for class org.omg.CORBA.INV_OBJREF
Constructs an INV_OBJREF exception with a default minor code of 0 and a completion state of COMPLETED_MAYBE.

INV_OBJREF(int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_OBJREF
Constructs an INV_OBJREF exception with the specified minor code and completion status.

INV_OBJREF(String) - Constructor for class org.omg.CORBA.INV_OBJREF
Constructs an INV_OBJREF exception with the specified detail message, a minor code of 0, and a completion state of COMPLETED_NO.

INV_OBJREF(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_OBJREF
Constructs an INV_OBJREF exception with the specified detail message, minor code, and completion status.

INV_POLICY - exception org.omg.CORBA.INV_POLICY.
The CORBA INV_POLICY standard exception, which is thrown when an invocation cannot be made because of an incompatibility between Policy overrides.

INV_POLICY() - Constructor for class org.omg.CORBA.INV_POLICY
Constructs a INV_POLICY exception with a default minor code of 0, a completion state of CompletionStatus.COMPLETED_NO, and a null description.

INV_POLICY(int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_POLICY
Constructs a INV_POLICY exception with the specified minor code and completion status.

INV_POLICY(String) - Constructor for class org.omg.CORBA.INV_POLICY
Constructs a INV_POLICY exception with the specified description message, a minor code of 0, and a completion state of COMPLETED_NO.

INV_POLICY(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INV_POLICY
Constructs a INV_POLICY exception with the specified description message, minor code, and completion status.

Invalid - exception org.omg.CORBA.DynAnyPackage.Invalid.
Invalid is thrown by dynamic any operations when a bad DynAny or Any is passed as a parameter.

INVALID_TRANSACTION - exception org.omg.CORBA.INVALID_TRANSACTION.
The CORBA INVALID_TRANSACTION exception, which is thrown when there is a transaction error.

INVALID_TRANSACTION() - Constructor for class org.omg.CORBA.INVALID_TRANSACTION
Constructs an INVALID_TRANSACTION exception with a default minor code of 0 and a completion state of COMPLETED_MAYBE.

INVALID_TRANSACTION(int, CompletionStatus) - Constructor for class org.omg.CORBA.INVALID_TRANSACTION
Constructs an INVALID_TRANSACTION exception with the specified minor code and completion status.

INVALID_TRANSACTION(String) - Constructor for class org.omg.CORBA.INVALID_TRANSACTION
Constructs an INVALID_TRANSACTION exception with the specified detail message.

isNodeSibling(TreeNode) - Method in class `javax.swing.tree.DefaultMutableTreeNode`

Returns true if anotherNode is a sibling of (has the same parent as) this node.

isNullable(int) - Method in interface `java.sql.ResultSetMetaData`

Indicates the nullability of values in the designated column.

ISO_2A0 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS 2A0, 1189 x 1682 mm.

ISO_4A0 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS 4A0, 1682 x 2378 mm.

ISO_A0 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A0, 841 x 1189 mm.

ISO_A1 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A1, 594 x 841 mm.

ISO_A10 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A10, 26 x 37 mm.

ISO_A2 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A2, 420 x 594 mm.

ISO_A3 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A3, 297 x 420 mm.

ISO_A4 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A4, 210 x 297 mm.

ISO_A5 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A5, 148 x 210 mm.

ISO_A6 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A6, 105 x 148 mm.

ISO_A7 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A7, 74 x 105 mm.

ISO_A8 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A8, 52 x 74 mm.

ISO_A9 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN & JIS A9, 37 x 52 mm.

ISO_B0 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B0, 1000 x 1414 mm.

ISO_B1 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B1, 707 x 1000 mm.

ISO_B10 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B10, 31 x 44 mm.

ISO_B2 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B2, 500 x 707 mm.

ISO_B3 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B3, 353 x 500 mm.

ISO_B4 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B4, 250 x 353 mm.

ISO_B4_ENVELOPE - Static variable in class `java.awt.PageAttributes.MediaType`

An alias for ISO_B4.

ISO_B5 - Static variable in class `java.awt.PageAttributes.MediaType`

The MediaType instance for ISO/DIN B5, 176 x 250 mm.

ISO_B5_ENVELOPE - Static variable in class `java.awt.PageAttributes.MediaType`

An alias for ISO_B5.

ISO_B6 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN B6, 125 x 176 mm.

ISO_B7 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN B7, 88 x 125 mm.

ISO_B8 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN B8, 62 x 88 mm.

ISO_B9 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN B9, 44 x 62 mm.

ISO_C0 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C0, 917 x 1297 mm.

ISO_C0_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C0.

ISO_C1 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C1, 648 x 917 mm.

ISO_C1_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C1.

ISO_C10 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C10, 28 x 40 mm.

ISO_C10_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C10.

ISO_C2 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C2, 458 x 648 mm.

ISO_C2_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C2.

ISO_C3 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C3, 324 x 458 mm.

ISO_C3_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C3.

ISO_C4 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C4, 229 x 324 mm.

ISO_C4_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C4.

ISO_C5 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C5, 162 x 229 mm.

ISO_C5_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C5.

ISO_C6 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C6, 114 x 162 mm.

ISO_C6_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C6.

ISO_C7 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C7, 81 x 114 mm.

ISO_C7_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C7.

ISO_C8 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C8, 57 x 81 mm.

ISO_C8_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C8.

ISO_C9 - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO/DIN C9, 40 x 57 mm.

ISO_C9_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_C9.

ISO_DESIGNATED_LONG - Static variable in class java.awt.PageAttributes.MediaType

The MediaType instance for ISO Designated Long, 110 x 220 mm.

ISO_DESIGNATED_LONG_ENVELOPE - Static variable in class java.awt.PageAttributes.MediaType

An alias for ISO_DESIGNATED_LONG.

isOneTouchExpandable() - Method in class javax.swing.JSplitPane

Returns true if the pane provides a UI widget to collapse/expand the divider.

isOnKeyRelease() - Method in class javax.swing.KeyStroke

Returns true if this keystroke is active on key release.

isOpaque() - Method in class java.awt.Component

Returns true if this component is completely opaque, returns false by default.

isOpaque() - Method in class javax.swing.JComponent

Returns true if this component is completely opaque.

isOpaque() - Method in class javax.swing.JDesktopPane

Returns true to indicate that this component paints every pixel in its range.

isOpaque() - Method in class javax.swing.plaf.basic.BasicInternalFrameTitlePane.SystemMenuBar

isOpen() - Method in interface javax.sound.sampled.Line

Indicates whether the line is open, meaning that it has reserved system resources and is operational, although it might not currently be playing or capturing sound.

isOpen() - Method in interface javax.sound.midi.MidiDevice

Reports whether the device is open.

isOptimizedDrawingEnabled() - Method in class javax.swing.JComponent

Returns true if this component tiles its children -- that is, if it can guarantee that the children will not overlap.

isOptimizedDrawingEnabled() - Method in class javax.swing.JViewport

The JViewport overrides the default implementation of this method (in JComponent) to return false.

isOptimizedDrawingEnabled() - Method in class javax.swing.JLayeredPane

Returns false if components in the pane can overlap, which makes optimized drawing impossible.

isOptimizedDrawingEnabled() - Method in class javax.swing.JRootPane

The GlassPane and ContentPane have the same bounds, which means JRootPane does not tiles its children and this should return false.

isOrdered() - Method in class javax.naming.directory.BasicAttribute

isOrdered() - Method in interface javax.naming.directory.Attribute

Determines whether this attribute's values are ordered.

isOwner(Principal) - Method in interface java.security.acl.Owner

Returns true if the given principal is an owner of the ACL.

isPaintable() - Method in interface java.beans.PropertyEditor

Determines whether this property editor is paintable.

isPaintable() - Method in class java.beans.PropertyEditorSupport

Determines whether the class will honor the paintValue method.

isPaintingTile() - Method in class javax.swing.JComponent

Returns true if the receiving component is currently painting a tile.

isPalette - Variable in class javax.swing.plaf.metal.MetalInternalFrameTitlePane

isParameter() - Method in class javax.swing.text.html.parser.Entity

Return true if it is a parameter entity.

isParseIntegerOnly() - Method in class java.text.NumberFormat

Returns true if this format will parse numbers as integers only.

isPathEditable(TreePath) - Method in class javax.swing.JTree

Returns isEditable.

isPathSelected(TreePath) - Method in class javax.swing.JTree

Returns true if the item identified by the path is currently selected.

isPathSelected(TreePath) - Method in class javax.swing.tree.DefaultTreeSelectionModel

Returns true if the path, path, is in the current selection.

isPathSelected(TreePath) - Method in interface javax.swing.tree.TreeSelectionModel

Returns true if the path, path, is in the current selection.

isPlain() - Method in class java.awt.Font

Indicates whether or not this Font object's style is PLAIN.

isPolygonal() - Method in class java.awt.geom.Area

Tests whether this Area consists entirely of straight edged polygonal geometry.

isPopupMenuVisible() - Method in class javax.swing.JMenu

Returns true if the menu's popup window is visible.

isPopupTrigger() - Method in class java.awt.event.MouseEvent

Returns whether or not this mouse event is the popup-menu trigger event for the platform.

isPopupTrigger(MouseEvent) - Method in class javax.swing.JPopupMenu

Returns true if the MouseEvent is considered a popup trigger by the JPopupMenu's currently installed UI.

isPopupTrigger(MouseEvent) - Method in class javax.swing.plaf.PopupMenuUI

isPopupTrigger(MouseEvent) - Method in class javax.swing.plaf.basic.BasicPopupMenuUI

isPopupVisible() - Method in class javax.swing.JComboBox

Determines the visibility of the popup.

isPopupVisible(JComboBox) - Method in class javax.swing.plaf.ComboBoxUI

Determine the visibility of the popup

isPopupVisible(JComboBox) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

Tells if the popup is visible or not.

isPopupVisible(JComboBox) - Method in class javax.swing.plaf.multi.MultiComboBoxUI

Call isPopupVisible on each UI handled by this MultiUI.

isPreferred() - Method in class java.beans.FeatureDescriptor

The "preferred" flag is used to identify features that are particularly important for presenting to humans.

isPreferredSizeSet() - Method in class javax.swing.JComponent

Returns true if the preferred size has been set to a non-null value otherwise returns false.

isPreformatted() - Method in class javax.swing.text.html.HTML.Tag

isPreformatted() - Method in class javax.swing.text.html.parser.TagElement

isPressed() - Method in interface javax.swing.ButtonModel

Indicates if button has been pressed.

isPressed() - Method in class javax.swing.DefaultButtonModel

Indicates if button has been pressed.

isPrimitive() - Method in class java.io.ObjectStreamField

Return true if this field has a primitive type.

isPrimitive() - Method in class java.lang.Class

Determines if the specified Class object represents a primitive type.

isPrivate(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the private modifier.

isProbablePrime(int) - Method in class java.math.BigInteger

Returns true if this BigInteger is probably prime, false if it's definitely composite.

isPropagated() - Method in class java.beans.beancontext.BeanContextEvent

Reports whether or not this event is propagated from some other BeanContext.

isProtected(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the protected modifier.

isProxyClass(Class) - Static method in class java.lang.reflect.Proxy

Returns true if and only if the specified class was dynamically generated to be a proxy class using the getProxyClass method or the newProxyInstance method.

isPublic(int) - Static method in class java.lang.reflect.Modifier

Return true if the specified integer includes the public modifier.

isReadOnly() - Method in class java.security.PermissionCollection

Returns true if this PermissionCollection object is marked as readonly.

isReadOnly() - Method in interface java.sql.Connection

Tests to see if the connection is in read-only mode.

isReadOnly() - Method in interface java.sql.DatabaseMetaData

Is the database in read-only mode?

isReadOnly(int) - Method in interface java.sql.ResultSetMetaData

Indicates whether the designated column is definitely not writable.

isRecording() - Method in interface javax.sound.midi.Sequencer

Indicates whether the Sequencer is currently recording.

isRectangleContainingRectangle(Rectangle, Rectangle) - Static method in class javax.swing.SwingUtilities

Return true if a contains b

isRectangular() - Method in class java.awt.geom.Area

Tests whether this Area is rectangular in shape.

isRelative() - Method in class javax.naming.NameClassPair

Determines whether the name of this binding is relative to the target context (which is named by the first parameter of the list() method).

isRepeats() - Method in class javax.swing.Timer

Returns true if the Timer will send a actionPerformed() message to its listeners multiple times.

isReplacing - Variable in class javax.swing.text.DefaultStyledDocument.AttributeUndoableEdit

isRepresentationClassInputStream() - Method in class java.awt.datatransfer.DataFlavor

does the DataFlavor represent a java.io.InputStream

isRepresentationClassRemote() - Method in class java.awt.datatransfer.DataFlavor

isRepresentationClassSerializable() - Method in class java.awt.datatransfer.DataFlavor

isRequestFocusEnabled() - Method in class javax.swing.JComponent

Returns whether the receiving component can obtain the focus by calling requestFocus.

isResizable - Variable in class javax.swing.table.TableColumn

If true, the user is allowed to resize the column; the default is true.

isResizable() - Method in class java.awt.Dialog

Indicates whether this dialog is resizable by the user.

isResizable() - Method in class java.awt.Frame

Indicates whether this frame is resizable by the user.

isResizable() - Method in class javax.swing.JInternalFrame

Returns whether the JInternalFrame can be resized by some user action.

isRevoked(Certificate) - Method in class java.security.cert.CRL

Checks whether the given certificate is on this CRL.

isRightMouseButton(MouseEvent) - Static method in class javax.swing.SwingUtilities

Returns true if the mouse event specifies the right mouse button.

isRollover() - Method in interface javax.swing.ButtonModel

Indicates that the mouse is over the button.

isRollover() - Method in class javax.swing.DefaultButtonModel

Indicates that the mouse is over the button.

isRolloverBorders() - Method in class javax.swing.plaf.metal.MetalToolBarUI

isRolloverEnabled() - Method in class javax.swing.AbstractButton

Checks whether rollover effects are enabled.

isRoot() - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if this node is the root of the tree.

isRoot(File) - Method in class javax.swing.filechooser.FileSystemView

Determines if the given file is a root partition or drive.

isRootPaneCheckingEnabled() - Method in class javax.swing.JWindow

Returns whether calls to add and setLayout will cause an exception to be thrown.

isRootPaneCheckingEnabled() - Method in class javax.swing.JApplet

isRootPaneCheckingEnabled() - Method in class javax.swing.JInternalFrame

Returns whether calls to add and setLayout cause an exception to be thrown.

isRootPaneCheckingEnabled() - Method in class javax.swing.JFrame

Returns whether calls to add and setLayout cause an exception to be thrown.

isRootPaneCheckingEnabled() - Method in class javax.swing.JDialog

Returns true if the methods add and setLayout should be checked.

isRootVisible() - Method in class javax.swing.JTree

Returns true if the root node of the tree is displayed.

isRootVisible() - Method in class javax.swing.tree.AbstractLayoutCache

Returns true if the root node of the tree is displayed.

isRootVisible() - Method in class javax.swing.plaf.basic.BasicTreeUI

isRowSelected(int) - Method in class javax.swing.JTree

Returns true if the node identified by row is selected.

isRowSelected(int) - Method in class javax.swing.JTable

Returns true if the row at the specified index is selected.

isRowSelected(int) - Method in class javax.swing.tree.DefaultTreeSelectionModel

Returns true if the row identified by row is selected.

isSelected(int) - Method in interface javax.swing.tree.TreeSelectionModel
Returns true if the row identified by row is selected.

isRunning() - Method in interface javax.sound.sampled.DataLine
Indicates whether the line is running.

isRunning() - Method in interface javax.sound.midi.Sequencer
Indicates whether the Sequencer is currently running.

isRunning() - Method in class javax.swing.Timer
Returns true if the Timer is running.

isSealed() - Method in class java.lang.Package
Returns true if this package is sealed.

isSealed(URL) - Method in class java.lang.Package
Returns true if this package is sealed with respect to the specified code source url.

isSearchable(int) - Method in interface java.sql.ResultSetMetaData
Indicates whether the designated column can be used in a where clause.

isSelected - Variable in class javax.swing.JInternalFrame
The frame is currently selected.

isSelected - Variable in class javax.swing.plaf.basic.BasicMenuUI.ChangeHandler

isSelected() - Method in class java.awt.im.InputMethodHighlight
Returns whether the text range is selected.

isSelected() - Method in class javax.swing.DefaultSingleSelectionModel

isSelected() - Method in interface javax.swing.SingleSelectionModel
Returns true if the selection model currently has a selected value.

isSelected() - Method in class javax.swing.AbstractButton
Returns the state of the button.

isSelected() - Method in class javax.swing.JMenu
Returns true if the menu is currently selected (highlighted).

isSelected() - Method in interface javax.swing.ButtonModel
Indicates if the button has been selected.

isSelected() - Method in class javax.swing.DefaultButtonModel
Indicates if the button has been selected.

isSelected() - Method in class javax.swing.JInternalFrame
Returns whether the JInternalFrame is the currently "selected" or active frame.

isSelected() - Method in class javax.swing.JToggleButton.ToggleButtonModel
Checks if the button is selected.

isSelected() - Method in class javax.swing.JMenuBar
Returns true if the menu bar currently has a component selected.

isSelected() - Method in class javax.swing.text.html.Option
Fetches the selection state associated with this option.

isSelected(ButtonModel) - Method in class javax.swing.ButtonGroup
Returns the selected value for the button.

isSelected(int) - Method in class java.awt.List
Deprecated. As of JDK version 1.1, replaced by *isIndexSelected(int)*.

isSelectedIndex(int) - Method in class javax.swing.DefaultListSelectionModel

isSelectedIndex(int) - Method in class javax.swing.JList

Returns true if the specified index is selected.

isSelectedIndex(int) - Method in interface javax.swing.ListSelectionModel

Returns true if the specified index is selected.

isSelectionEmpty() - Method in class javax.swing.DefaultListSelectionModel

isSelectionEmpty() - Method in class javax.swing.JList

Returns true if nothing is selected.

isSelectionEmpty() - Method in class javax.swing.JTree

Returns true if the selection is currently empty.

isSelectionEmpty() - Method in interface javax.swing.ListSelectionModel

Returns true if no indices are selected.

isSelectionEmpty() - Method in class javax.swing.tree.DefaultTreeSelectionModel

Returns true if the selection is currently empty.

isSelectionEmpty() - Method in interface javax.swing.tree.TreeSelectionModel

Returns true if the selection is currently empty.

isSelectionVisible() - Method in class javax.swing.text.DefaultCaret

Checks whether the current selection is visible.

isSelectionVisible() - Method in interface javax.swing.text.Caret

Determines if the selection is currently visible.

isSerializing() - Method in class java.beans.beancontext.BeanContextSupport

Is this BeanContext in the process of being serialized?

isServiceClass(Class) - Method in class java.beans.beancontext.BeanContextServiceRevokedEvent

Checks this event to determine whether or not the service being revoked is of a particular class.

isSet - Variable in class java.util.Calendar

The flags which tell if a specified time field for the calendar is set.

isSet(int) - Method in class java.util.Calendar

Determines if the given time field has a value set.

isShiftDown() - Method in class java.awt.event.InputEvent

Returns whether or not the Shift modifier is down on this event.

isShowing() - Method in class java.awt.Component

Determines whether this component is showing on screen.

isShowing() - Method in class java.awt.Component.AccessibleAWTComponent

Determine if the object is showing.

isShowing() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Determine if the object is showing.

isShowing() - Method in class java.awt.Window

Checks if this Window is showing on screen.

isShowing() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Determine if the object is showing.

isShowing() - Method in interface javax.accessibility.AccessibleComponent

Determines if the object is showing.

isShowing() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

isShowing() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

isShowing() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Determines if the object is showing.

isShowing() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

isSigned(int) - Method in interface java.sql.ResultSetMetaData

Indicates whether values in the designated column are signed numbers.

isSignificant() - Method in class javax.swing.text.AbstractDocument.DefaultDocumentEvent

DefaultDocument events are significant.

isSignificant() - Method in class javax.swing.undo.AbstractUndoableEdit

This default implementation returns true.

isSignificant() - Method in class javax.swing.undo.CompoundEdit

Returns true if any of the UndoableEdits in edits do.

isSignificant() - Method in interface javax.swing.undo.UndoableEdit

Return false if this edit is insignificant--for example one that maintains the user's selection, but does not change any model state.

isSingular() - Method in class java.awt.geom.Area

Tests whether this Area is comprised of a single closed subpath.

isSoundbankSupported(Soundbank) - Method in interface javax.sound.midi.Synthesizer

Informs the caller whether this synthesizer is capable of loading instruments from the specified soundbank.

isSource() - Method in class javax.sound.sampled.Port.Info

Indicates whether the port is a source or a target for its mixer.

isSourceEncodingSupported(AudioFormat.Encoding) - Method in class

javax.sound.sampled.spi.FormatConversionProvider

Indicates whether the format converter supports conversion from the specified source format encoding.

isSpace(char) - Static method in class java.lang.Character

Deprecated. *Replaced by isWhitespace(char).*

isSpaceChar(char) - Static method in class java.lang.Character

Determines if the specified character is a Unicode space character.

isStandard() - Method in class java.awt.font.GlyphMetrics

Returns true if this is a standard glyph.

isStatic(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the `static` modifier.

isStrict(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the `strictfp` modifier.

isStrikeThrough() - Method in class javax.swing.text.GlyphView

Determine if the glyphs should have a strikethrough line.

isStrikeThrough() - Method in class javax.swing.text.LabelView

Determine if the glyphs should have a strikethrough line.

isStrikeThrough(AttributeSet) - Static method in class javax.swing.text.StyleConstants

Checks whether the strikethrough attribute is set.

isStringPainted() - Method in class javax.swing.JProgressBar

Returns true if the progress bar will render a string onto the representation of the progress bar.

isSubscript() - Method in class javax.swing.text.GlyphView

Determine if the glyphs should be rendered as superscript.

isSubscript() - Method in class javax.swing.text.LabelView

Determine if the glyphs should be rendered as superscript.

[ByteArrayInputStream\(byte\[\], int, int\)](#) - Constructor for class [java.io.ByteArrayInputStream](#)

Creates [ByteArrayInputStream](#) that uses `buf` as its buffer array.

[ByteArrayOutputStream](#) - class [java.io.ByteArrayOutputStream](#).

This class implements an output stream in which the data is written into a byte array.

[ByteArrayOutputStream\(\)](#) - Constructor for class [java.io.ByteArrayOutputStream](#)

Creates a new byte array output stream.

[ByteArrayOutputStream\(int\)](#) - Constructor for class [java.io.ByteArrayOutputStream](#)

Creates a new byte array output stream, with a buffer capacity of the specified size, in bytes.

[ByteHolder](#) - class [org.omg.CORBA.ByteHolder](#).

A Holder class for a byte that is used to store "out" and "inout" parameters in IDL methods.

[ByteHolder\(\)](#) - Constructor for class [org.omg.CORBA.ByteHolder](#)

Constructs a new [ByteHolder](#) object with its `value` field initialized to 0.

[ByteHolder\(byte\)](#) - Constructor for class [org.omg.CORBA.ByteHolder](#)

Constructs a new [ByteHolder](#) object for the given byte.

[byteLength](#) - Variable in class [javax.sound.midi.MidiFileFormat](#)

The length of the MIDI file in bytes.

[ByteLookupTable](#) - class [java.awt.image.ByteLookupTable](#).

This class defines a lookup table object.

[ByteLookupTable\(int, byte\[\]\)](#) - Constructor for class [java.awt.image.ByteLookupTable](#)

Constructs a [ByteLookupTable](#) object from an array of bytes representing a lookup table to be applied to all bands.

[ByteLookupTable\(int, byte\[\]\[\]\)](#) - Constructor for class [java.awt.image.ByteLookupTable](#)

Constructs a [ByteLookupTable](#) object from an array of byte arrays representing a lookup table for each band.

[bytesTransferred](#) - Variable in class [java.io.InterruptedIOException](#)

Reports how many bytes had been transferred as part of the I/O operation before it was interrupted.

[bytesWidth\(byte\[\], int, int\)](#) - Method in class [java.awt.FontMetrics](#)

Returns the total advance width for showing the specified array of bytes in this [Font](#).

[byteValue\(\)](#) - Method in class [java.lang.Number](#)

Returns the value of the specified number as a byte.

[byteValue\(\)](#) - Method in class [java.lang.Long](#)

Returns the value of this [Long](#) as a byte.

[byteValue\(\)](#) - Method in class [java.lang.Short](#)

Returns the value of this [Short](#) as a byte.

[byteValue\(\)](#) - Method in class [java.lang.Float](#)

Returns the value of this [Float](#) as a byte (by casting to a byte).

[byteValue\(\)](#) - Method in class [java.lang.Integer](#)

Returns the value of this [Integer](#) as a byte.

[byteValue\(\)](#) - Method in class [java.lang.Byte](#)

Returns the value of this [Byte](#) as a byte.

[byteValue\(\)](#) - Method in class [java.lang.Double](#)

Returns the value of this [Double](#) as a byte (by casting to a byte).

[Overview](#) **[Package](#)** **[Class](#)** **[Use](#)** **[Tree](#)** **[Deprecated](#)** **[Index](#)** **[Help](#)**

*Java™ 2 Platform
Std. Ed. v1.3.1*

[PREV LETTER](#) [NEXT LETTER](#)

[FRAMES](#) [NO FRAMES](#)

[A](#) [B](#) [C](#) [D](#) [E](#) [F](#) [G](#) [H](#) [I](#) [J](#) [K](#) [L](#) [M](#) [N](#) [O](#) [P](#) [Q](#) [R](#) [S](#) [T](#) [U](#) [V](#) [W](#) [X](#) [Y](#) [Z](#) [_](#)

[Submit a bug or feature](#)

For further API reference and developer documentation, see [Java 2 SDK SE Developer Documentation](#). That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Java, Java 2D, and JDBC are trademarks or registered trademarks of Sun Microsystems, Inc. in the US and other countries.
Copyright 1993-2001 Sun Microsystems, Inc. 901 San Antonio Road
Palo Alto, California, 94303, U.S.A. All Rights Reserved.

I

I - Static variable in class javax.swing.text.html.HTML.Tag

icAbsoluteColorimetric - Static variable in class java.awt.color.ICC_Profile

ICC Profile Rendering Intent: AbsoluteColorimetric.

ICC_ColorSpace - class java.awt.color.ICC_ColorSpace.

An implementation of the abstract ColorSpace class.

ICC_ColorSpace(ICC_Profile) - Constructor for class java.awt.color.ICC_ColorSpace

Constructs a new ICC_ColorSpace from an ICC_Profile object.

ICC_Profile - class java.awt.color.ICC_Profile.

A representation of color profile data for device independent and device dependent color spaces based on the International Color Consortium Specification ICC.1:1998-09, File Format for Color Profiles, September 1998, and the addendum ICC.1A:1999-04, April 1999, to that specification (see <http://www.color.org>).

ICC_ProfileGray - class java.awt.color.ICC_ProfileGray.

A subclass of the ICC_Profile class which represents profiles which meet the following criteria: the color space type of the profile is TYPE_GRAY and the profile includes the grayTRCTag and mediaWhitePointTag tags.

ICC_ProfileRGB - class java.awt.color.ICC_ProfileRGB.

A subclass of the ICC_Profile class which represents profiles which meet the following criteria: the color space type of the profile is RGB and the profile includes the redColorantTag, greenColorantTag, blueColorantTag, redTRCTag, greenTRCTag, blueTRCTag, and mediaWhitePointTag tags.

icCurveCount - Static variable in class java.awt.color.ICC_Profile

ICC Profile Constant: curveType count.

icCurveData - Static variable in class java.awt.color.ICC_Profile

ICC Profile Constant: curveType data.

icHdrAttributes - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: device attributes.

icHdrCmmId - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: CMM for this profile.

icHdrColorSpace - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: color space of data.

icHdrCreator - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: profile creator.

icHdrDate - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: date profile was created.

icHdrDeviceClass - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: type of profile.

icHdrFlags - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: various bit settings.

icHdrIlluminant - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: profile illuminant.

icHdrMagic - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: icMagicNumber.

icHdrManufacturer - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: device manufacturer.

icHdrModel - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: device model number.

icHdrPcs - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: PCS - XYZ or Lab only.

icHdrPlatform - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: primary platform.

icHdrRenderingIntent - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: rendering intent.

icHdrSize - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: profile size in bytes.

icHdrVersion - Static variable in class java.awt.color.ICC_Profile

ICC Profile Header Location: format version number.

icon - Variable in class javax.swing.JOptionPane

Icon used in pane.

icon - Variable in class javax.swing.plaf.basic.BasicRadioButtonUI

Icon - interface javax.swing.Icon.

A small fixed size picture, typically used to decorate components.

ICON - Static variable in class javax.accessibility.AccessibleRole

A small fixed size picture, typically used to decorate components.

ICON_CHANGED_PROPERTY - Static variable in class javax.swing.AbstractButton

Identifies a change to the icon that represents the button.

ICON_COLOR_16x16 - Static variable in interface java.beans.BeanInfo

Constant to indicate a 16 x 16 color icon.

ICON_COLOR_32x32 - Static variable in interface java.beans.BeanInfo

Constant to indicate a 32 x 32 color icon.

ICON_MONO_16x16 - Static variable in interface java.beans.BeanInfo

Constant to indicate a 16 x 16 monochrome icon.

ICON_MONO_32x32 - Static variable in interface java.beans.BeanInfo

Constant to indicate a 32 x 32 monochrome icon.

ICON_PROPERTY - Static variable in class javax.swing.JOptionPane

Bound property name for icon.

iconable - Variable in class javax.swing.JInternalFrame

The frame can "iconized" (shrunk down and displayed as an icon-image).

IconAttribute - Static variable in class javax.swing.text.StyleConstants

Name of the icon attribute.

IconAttribute - Static variable in class javax.swing.text.StyleConstants.CharacterConstants

Name of the icon attribute.

iconButton - Variable in class javax.swing.plaf.basic.BasicInternalFrameTitlePane

iconCache - Variable in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

IconElementName - Static variable in class javax.swing.text.StyleConstants

Name of elements used to represent icons.

iconIcon - Variable in class javax.swing.plaf.basic.BasicInternalFrameTitlePane

ICONIFIED - Static variable in class java.awt.Frame

ICONIFIED - Static variable in class javax.accessibility.AccessibleState

Indicates this object is minimized and is represented only by an icon.

ICONIFY_CMD - Static variable in class javax.swing.plaf.basic.BasicInternalFrameTitlePane

iconifyAction - Variable in class javax.swing.plaf.basic.BasicInternalFrameTitlePane

iconifyFrame(JInternalFrame) - Method in interface javax.swing.DesktopManager

Generally, remove this frame from it's parent and add an iconic representation.

iconifyFrame(JInternalFrame) - Method in class javax.swing.DefaultDesktopManager

Removes the frame from its parent and adds its desktopIcon to the parent.

iconifyFrame(JInternalFrame) - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

This method is called when the user wants to iconify the frame.

iconOnly - Variable in class javax.swing.plaf.metal.MetalComboBoxButton

IconUIResource - class javax.swing.plaf.IconUIResource.

IconUIResource(Icon) - Constructor for class javax.swing.plaf.IconUIResource

Creates a UIResource icon object which wraps an existing Icon instance.

IconView - class javax.swing.text.IconView.

Icon decorator that implements the view interface.

IconView(Element) - Constructor for class javax.swing.text.IconView

Creates a new icon view that represents an element.

icPerceptual - Static variable in class java.awt.color.ICC_Profile

ICC Profile Rendering Intent: Perceptual.

icRelativeColorimetric - Static variable in class java.awt.color.ICC_Profile

ICC Profile Rendering Intent: RelativeColorimetric.

icSaturation - Static variable in class java.awt.color.ICC_Profile

ICC Profile Rendering Intent: Saturation.

icSigAbstractClass - Static variable in class java.awt.color.ICC_Profile

ICC Profile Class Signature: 'abst'.

icSigAtoB0Tag - Static variable in class java.awt.color.ICC_Profile

ICC Profile Tag Signature: 'A2B0'.

icSigAtoB1Tag - Static variable in class java.awt.color.ICC_Profile

ICC Profile Tag Signature: 'A2B1'.

icSigAtoB2Tag - Static variable in class java.awt.color.ICC_Profile

ICC Profile Tag Signature: 'A2B2'.

icSigBlueColorantTag - Static variable in class java.awt.color.ICC_Profile

ICC Profile Tag Signature: 'bXYZ'.

icSigBlueTRCTag - Static variable in class java.awt.color.ICC_Profile

ICC Profile Tag Signature: 'bTRC'.

icSigBToA0Tag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'B2A0'.

icSigBToA1Tag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'B2A1'.

icSigBToA2Tag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'B2A2'.

icSigCalibrationDateTimeTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'calt'.

icSigCharTargetTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'targ'.

icSigChromaticityTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'chrn'.

icSigCmyData - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Color Space Type Signature: 'CMY '.

icSigCmykData - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Color Space Type Signature: 'CMYK'.

icSigColorSpaceClass - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Class Signature: 'spac'.

icSigCopyrightTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'cpri'.

icSigCrdInfoTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'crdi'.

icSigDeviceMfgDescTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'dmnd'.

icSigDeviceModelDescTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'dmdd'.

icSigDeviceSettingsTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'devs'.

icSigDisplayClass - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Class Signature: 'mntr'.

icSigGamutTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'gamt'.

icSigGrayData - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Color Space Type Signature: 'GRAY'.

icSigGrayTRCTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'kTRC'.

icSigGreenColorantTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'gXYZ'.

icSigGreenTRCTag - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'gTRC'.

icSigHead - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Tag Signature: 'head' - special.

icSigHlsData - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Color Space Type Signature: 'HLS'.

icSigHsvData - Static variable in class [java.awt.color.ICC_Profile](#)
ICC Profile Color Space Type Signature: 'HSV'.

icSigInputClass - Static variable in class [java.awt.color.ICC_Profile](#)

ICC Profile Class Signature: 'scnr'.
icSigLabData - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'Lab'.
icSigLinkClass - Static variable in class java.awt.color.ICC_Profile
ICC Profile Class Signature: 'link'.
icSigLuminanceTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'lumi'.
icSigLuvData - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'Luv'.
icSigMeasurementTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'meas'.
icSigMediaBlackPointTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'bkpt'.
icSigMediaWhitePointTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'wtpt'.
icSigNamedColor2Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'ncl2'.
icSigNamedColorClass - Static variable in class java.awt.color.ICC_Profile
ICC Profile Class Signature: 'nmcl'.
icSigOutputClass - Static variable in class java.awt.color.ICC_Profile
ICC Profile Class Signature: 'ptr'.
icSigOutputResponseTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'resp'.
icSigPreview0Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'pre0'.
icSigPreview1Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'pre1'.
icSigPreview2Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'pre2'.
icSigProfileDescriptionTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'desc'.
icSigProfileSequenceDescTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'pseq'.
icSigPs2CRD0Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'psd0'.
icSigPs2CRD1Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'psd1'.
icSigPs2CRD2Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'psd2'.
icSigPs2CRD3Tag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'psd3'.
icSigPs2CSATag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'ps2s'.
icSigPs2RenderingIntentTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'ps2i'.
icSigRedColorantTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'rXYZ'.

icSigRedTRCTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'rTRC'.

icSigRgbData - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'RGB '.

icSigScreeningDescTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'scrd'.

icSigScreeningTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'scrn'.

icSigSpace2CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '2CLR'.

icSigSpace3CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '3CLR'.

icSigSpace4CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '4CLR'.

icSigSpace5CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '5CLR'.

icSigSpace6CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '6CLR'.

icSigSpace7CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '7CLR'.

icSigSpace8CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '8CLR'.

icSigSpace9CLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: '9CLR'.

icSigSpaceACLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'ACLR'.

icSigSpaceBCLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'BCLR'.

icSigSpaceCCLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'CCLR'.

icSigSpaceDCLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'DCLR'.

icSigSpaceECLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'ECLR'.

icSigSpaceFCLR - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'FCLR'.

icSigTechnologyTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'tech'.

icSigUcrBgTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'bfd '.

icSigViewingCondDescTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'vued'.

icSigViewingConditionsTag - Static variable in class java.awt.color.ICC_Profile
ICC Profile Tag Signature: 'view'.

icSigXYZData - Static variable in class java.awt.color.ICC_Profile
ICC Profile Color Space Type Signature: 'XYZ '.

icSigYCbCrData - Static variable in class java.awt.color.ICC_Profile

ICC Profile Color Space Type Signature: 'YCbCr'.

icSigYxyData - Static variable in class java.awt.color.ICC_Profile

ICC Profile Color Space Type Signature: 'Yxy '.

icTagReserved - Static variable in class java.awt.color.ICC_Profile

ICC Profile Constant: reserved.

icTagType - Static variable in class java.awt.color.ICC_Profile

ICC Profile Constant: tag type signature.

icXYZNumberX - Static variable in class java.awt.color.ICC_Profile

ICC Profile Constant: XYZNumber X.

id - Variable in class java.awt.Event

Indicates which type of event the event is, and which other Event variables are relevant for the event.

id - Variable in class java.awt.AWTEvent

id - Variable in class org.omg.CORBA.NameValuePair

The name to be associated with a value by this NameValuePair object.

id - Variable in class org.omg.CORBA.ValueMember

The name of the value member described by this ValueMember object.

id - Variable in class org.omg.CosNaming.NameComponent

ID - Static variable in class javax.swing.text.html.HTML.Attribute

ID - Static variable in interface javax.swing.text.html.parser.DTDConstants

id() - Static method in class org.omg.CORBA.UnionMemberHelper

id() - Static method in class org.omg.CORBA.ServiceInformationHelper

id() - Static method in class org.omg.CORBA.PolicyListHelper

id() - Static method in class org.omg.CORBA.NameValuePairHelper

id() - Static method in class org.omg.CORBA.LongSeqHelper

id() - Static method in class org.omg.CORBA.OctetSeqHelper

id() - Static method in class org.omg.CORBA.IdentifierHelper

id() - Static method in class org.omg.CORBA.FloatSeqHelper

id() - Static method in class org.omg.CORBA.ServiceDetailHelper

id() - Static method in class org.omg.CORBA.BooleanSeqHelper

id() - Static method in class org.omg.CORBA.VisibilityHelper

id() - Static method in class org.omg.CORBA.ULongSeqHelper

id() - Static method in class org.omg.CORBA.StringValueHelper

id() - Static method in class org.omg.CORBA.CharSeqHelper

id() - Static method in class org.omg.CORBA.SetOverrideTypeHelper

id() - Static method in class org.omg.CORBA.VersionSpecHelper

id() - Static method in class org.omg.CORBA.DefinitionKindHelper

id() - Static method in class org.omg.CORBA.StructMemberHelper

id() - Static method in class org.omg.CORBA.IDLTypeHelper

id() - Static method in class org.omg.CORBA.UShortSeqHelper

id() - Static method in class org.omg.CORBA.WCharSeqHelper

id() - Method in class org.omg.CORBA.TypeCode
Retrieves the RepositoryId globally identifying the type of this TypeCode object.

id() - Static method in class org.omg.CORBA.DoubleSeqHelper

id() - Static method in class org.omg.CORBA.WStringValueHelper

id() - Static method in class org.omg.CORBA.PolicyTypeHelper

id() - Static method in class org.omg.CORBA.ULongLongSeqHelper

id() - Static method in class org.omg.CORBA.RepositoryIdHelper

id() - Static method in class org.omg.CORBA.ShortSeqHelper

id() - Static method in class org.omg.CORBA.ObjectHelper

id() - Static method in class org.omg.CORBA.CurrentHelper

id() - Static method in class org.omg.CORBA.LongLongSeqHelper

id() - Static method in class org.omg.CORBA.CompletionStatusHelper

id() - Static method in class org.omg.CORBA.FieldNameHelper

id() - Static method in class org.omg.CORBA.ValueBaseHelper

id() - Static method in class org.omg.CORBA.PolicyHelper

id() - Static method in class org.omg.CORBA.AnySeqHelper

id() - Static method in class org.omg.CORBA.ValueMemberHelper

id() - Static method in class org.omg.CosNaming.NameHelper

id() - Static method in class org.omg.CosNaming.IstringHelper

id() - Static method in class org.omg.CosNaming.BindingListHelper

id() - Static method in class org.omg.CosNaming.BindingIteratorHelper

id() - Static method in class org.omg.CosNaming.NameComponentHelper

id() - Static method in class org.omg.CosNaming.BindingTypeHelper

id() - Static method in class org.omg.CosNaming.NamingContextHelper

id() - Static method in class org.omg.CosNaming.BindingHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.AlreadyBoundHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.NotFoundReasonHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.NotFoundHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.CannotProceedHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.InvalidNameHelper

id() - Static method in class org.omg.CosNaming.NamingContextPackage.NotEmptyHelper

IDENTICAL - Static variable in class java.text.Collator

Collator strength value.

identifier - Variable in class javax.swing.table.TableColumn

This object is not used internally by the drawing machinery of the JTable; identifiers may be set in the TableColumn as an optional way to tag and locate table columns.

IdentifierHelper - class org.omg.CORBA.IdentifierHelper.

org.omg/CORBA/IdentifierHelper.java Generated by the IDL-to-Java compiler (portable), version "3.0"
from ir.idl 03 June 1999 11:33:42 o'clock GMT+00:00

IdentifierHelper() - Constructor for class org.omg.CORBA.IdentifierHelper

identities() - Method in class java.security.IdentityScope

Deprecated. Returns an enumeration of all identities in this identity scope.

Identity - class java.security.Identity.

Deprecated. *This class is no longer used. Its functionality has been replaced by java.security.KeyStore, the java.security.cert package, and java.security.Principal.*

Identity() - Constructor for class java.security.Identity

Deprecated. Constructor for serialization only.

Identity(String) - Constructor for class java.security.Identity

Deprecated. Constructs an identity with the specified name and no scope.

Identity(String, IdentityScope) - Constructor for class java.security.Identity

Deprecated. Constructs an identity with the specified name and scope.

identityEquals(Identity) - Method in class java.security.Identity

Deprecated. Tests for equality between the specified identity and this identity.

identityHashCode(Object) - Static method in class java.lang.System

Returns the same hashcode for the given object as would be returned by the default method hashCode(), whether or not the given object's class overrides hashCode().

IdentityScope - class java.security.IdentityScope.

Deprecated. *This class is no longer used. Its functionality has been replaced by java.security.KeyStore, the java.security.cert package, and java.security.Principal.*

IdentityScope() - Constructor for class java.security.IdentityScope

Deprecated. This constructor is used for serialization only and should not be used by subclasses.

IdentityScope(String) - Constructor for class java.security.IdentityScope

Deprecated. Constructs a new identity scope with the specified name.

IdentityScope(String, IdentityScope) - Constructor for class java.security.IdentityScope

Deprecated. Constructs a new identity scope with the specified name and scope.

IDLEntity - interface org.omg.CORBA.portable.IDLEntity.

An interface with no members whose only purpose is to serve as a marker indicating that an implementing class is a Java value type from IDL that has a corresponding Helper class.

IDLType - interface org.omg.CORBA.IDLType.

An abstract interface inherited by all Interface Repository (IR) objects that represent OMG IDL types.

IDLTypeHelper - class org.omg.CORBA.IDLTypeHelper.

org/omg/CORBA/IDLTypeHelper.java Generated by the IDL-to-Java compiler (portable), version "3.0" from ir.idl 03 June 1999 11:33:44 o'clock GMT+00:00

IDLTypeHelper() - Constructor for class org.omg.CORBA.IDLTypeHelper

IDLTypeOperations - interface org.omg.CORBA.IDLTypeOperations.

This interface must be implemented by all IDLType objects.

IDREF - Static variable in interface javax.swing.text.html.parser.DTDConstants

IDREFS - Static variable in interface javax.swing.text.html.parser.DTDConstants

IEEEremainder(double, double) - Static method in class java.lang.StrictMath

Computes the remainder operation on two arguments as prescribed by the IEEE 754 standard.

IEEEremainder(double, double) - Static method in class java.lang.Math

Computes the remainder operation on two arguments as prescribed by the IEEE 754 standard.

ifModifiedSince - Variable in class java.net.URLConnection

Some protocols support skipping the fetching of the object unless the object has been modified more recently than a certain time.

IGNORE_ALL_BEANINFO - Static variable in class java.beans.Introspector

IGNORE_IMMEDIATE_BEANINFO - Static variable in class java.beans.Introspector

IllegalAccessError - error java.lang.IllegalAccessError.

Thrown if an application attempts to access or modify a field, or to call a method that it does not have access to.

IllegalAccessError() - Constructor for class java.lang.**IllegalAccessError**

Constructs an **IllegalAccessError** with no detail message.

IllegalAccessError(String) - Constructor for class java.lang.**IllegalAccessError**

Constructs an **IllegalAccessError** with the specified detail message.

IllegalAccessException - exception java.lang.**IllegalAccessException**.

Thrown when an application tries to load in a class, but the currently executing method does not have access to the definition of the specified class, because the class is not public and in another package.

IllegalAccessException() - Constructor for class java.lang.**IllegalAccessException**

Constructs an **IllegalAccessException** without a detail message.

IllegalAccessException(String) - Constructor for class java.lang.**IllegalAccessException**

Constructs an **IllegalAccessException** with a detail message.

IllegalArgumentException - exception java.lang.**IllegalArgumentException**.

Thrown to indicate that a method has been passed an illegal or inappropriate argument.

IllegalArgumentException() - Constructor for class java.lang.**IllegalArgumentException**

Constructs an **IllegalArgumentException** with no detail message.

IllegalArgumentException(String) - Constructor for class java.lang.**IllegalArgumentException**

Constructs an **IllegalArgumentException** with the specified detail message.

IllegalComponentStateException - exception java.awt.**IllegalComponentStateException**.

Signals that an AWT component is not in an appropriate state for the requested operation.

IllegalComponentStateException() - Constructor for class java.awt.**IllegalComponentStateException**

Constructs an **IllegalComponentStateException** with no detail message.

IllegalComponentStateException(String) - Constructor for class java.awt.**IllegalComponentStateException**

Constructs an **IllegalComponentStateException** with the specified detail message.

IllegalMonitorStateException - exception java.lang.**IllegalMonitorStateException**.

Thrown to indicate that a thread has attempted to wait on an object's monitor or to notify other threads waiting on an object's monitor without owning the specified monitor.

IllegalMonitorStateException() - Constructor for class java.lang.**IllegalMonitorStateException**

Constructs an **IllegalMonitorStateException** with no detail message.

IllegalMonitorStateException(String) - Constructor for class java.lang.**IllegalMonitorStateException**

Constructs an **IllegalMonitorStateException** with the specified detail message.

IllegalPathStateException - exception java.awt.geom.**IllegalPathStateException**.

The **IllegalPathStateException** represents an exception that is thrown if an operation is performed on a path that is in an illegal state with respect to the particular operation being performed, such as appending a path segment to a **GeneralPath** without an initial moveto.

IllegalPathStateException() - Constructor for class java.awt.geom.**IllegalPathStateException**

Constructs an **IllegalPathStateException** with no detail message.

IllegalPathStateException(String) - Constructor for class java.awt.geom.**IllegalPathStateException**

Constructs an **IllegalPathStateException** with the specified detail message.

IllegalStateException - exception java.lang.**IllegalStateException**.

Signals that a method has been invoked at an illegal or inappropriate time.

IllegalStateException() - Constructor for class java.lang.**IllegalStateException**

Constructs an **IllegalStateException** with no detail message.

IllegalStateException(String) - Constructor for class java.lang.**IllegalStateException**

Constructs an **IllegalStateException** with the specified detail message.

IllegalThreadStateException - exception java.lang.**IllegalThreadStateException**.

Thrown to indicate that a thread is not in an appropriate state for the requested operation.
[IllegalThreadStateException\(\)](#) - Constructor for class java.lang.[IllegalThreadStateException](#)
Constructs an [IllegalThreadStateException](#) with no detail message.
[IllegalThreadStateException\(String\)](#) - Constructor for class java.lang.[IllegalThreadStateException](#)
Constructs an [IllegalThreadStateException](#) with the specified detail message.
[Image](#) - class java.awt.[Image](#).
The abstract class [Image](#) is the superclass of all classes that represent graphical images.
[Image\(\)](#) - Constructor for class java.awt.[Image](#)

[IMAGEABORTED](#) - Static variable in interface java.awt.image.[ImageConsumer](#)
The image creation process was deliberately aborted.

[imageComplete\(int\)](#) - Method in class java.awt.image.[ImageFilter](#)
Filters the information provided in the [imageComplete](#) method of the [ImageConsumer](#) interface.

[imageComplete\(int\)](#) - Method in class java.awt.image.[PixelGrabber](#)
The [imageComplete](#) method is part of the [ImageConsumer](#) API which this class must implement to retrieve the pixels.

[imageComplete\(int\)](#) - Method in interface java.awt.image.[ImageConsumer](#)
The [imageComplete](#) method is called when the [ImageProducer](#) is finished delivering all of the pixels that the source image contains, or when a single frame of a multi-frame animation has been completed, or when an error in loading or producing the image has occurred.

[imageComplete\(int\)](#) - Method in class java.awt.image.[BufferedImageFilter](#)
Filters the information provided in the [imageComplete](#) method of the [ImageConsumer](#) interface.

[ImageConsumer](#) - interface java.awt.image.[ImageConsumer](#).
The interface for objects expressing interest in image data through the [ImageProducer](#) interfaces.

[IMAGEERROR](#) - Static variable in interface java.awt.image.[ImageConsumer](#)
An error was encountered while producing the image.

[ImageFilter](#) - class java.awt.image.[ImageFilter](#).
This class implements a filter for the set of interface methods that are used to deliver data from an [ImageProducer](#) to an [ImageConsumer](#).

[ImageFilter\(\)](#) - Constructor for class java.awt.image.[ImageFilter](#)

[ImageGraphicAttribute](#) - class java.awt.font.[ImageGraphicAttribute](#).
The [ImageGraphicAttribute](#) class is an implementation of [GraphicAttribute](#) which draws images in a [TextLayout](#).

[ImageGraphicAttribute\(Image, int\)](#) - Constructor for class java.awt.font.[ImageGraphicAttribute](#)
Constructs an [ImageGraphicAttribute](#) from the specified [Image](#).

[ImageGraphicAttribute\(Image, int, float, float\)](#) - Constructor for class java.awt.font.[ImageGraphicAttribute](#)
Constructs an [ImageGraphicAttribute](#) from the specified [Image](#).

[ImageIcon](#) - class javax.swing.[ImageIcon](#).
An implementation of the [Icon](#) interface that paints Icons from Images.

[ImageIcon.AccessibleImageIcon](#) - class javax.swing.[ImageIcon.AccessibleImageIcon](#).
This class implements accessibility support for the [ImageIcon](#) class.

[ImageIcon.AccessibleImageIcon\(ImageIcon\)](#) - Constructor for class javax.swing.[ImageIcon.AccessibleImageIcon](#)

[ImageIcon\(\)](#) - Constructor for class javax.swing.[ImageIcon](#)
Creates an uninitialized image icon.

ImageIcon(byte[]) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from an array of bytes which were read from an image file containing a supported image format, such as GIF or JPEG.

ImageIcon(byte[], String) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from an array of bytes which were read from an image file containing a supported image format, such as GIF or JPEG.

ImageIcon(Image) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from an image object.

ImageIcon(Image, String) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from the image.

ImageIcon(String) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from the specified file.

ImageIcon(String, String) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from the specified file.

ImageIcon(URL) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from the specified URL.

ImageIcon(URL, String) - Constructor for class javax.swing.ImageIcon

Creates an ImageIcon from the specified URL.

ImageObserver - interface java.awt.image.ImageObserver.

An asynchronous update interface for receiving notifications about Image information as the Image is constructed.

ImageProducer - interface java.awt.image.ImageProducer.

The interface for objects which can produce the image data for Images.

imageSubmit(String) - Method in class javax.swing.text.html.FormView

This method is called to submit a form in response to a click on an image -- an <INPUT> form element of type "image".

imageUpdate(Image, int, int, int, int, int) - Method in class java.awt.Component

Repaints the component when the image has changed.

imageUpdate(Image, int, int, int, int, int) - Method in interface java.awt.image.ImageObserver

This method is called when information about an image which was previously requested using an asynchronous interface becomes available.

imageUpdate(Image, int, int, int, int, int) - Method in class javax.swing.AbstractButton

This is overridden to return false if the current Icon's Image is not equal to the passed in Image img.

imageUpdate(Image, int, int, int, int, int) - Method in class javax.swing.JLabel

This is overridden to return false if the current Icon's Image is not equal to the passed in Image img.

ImagingOpException - exception java.awt.image.ImagingOpException.

The ImagingOpException is thrown if one of the BufferedImageOp or RasterOp filter methods cannot process the image.

ImagingOpException(String) - Constructor for class java.awt.image.ImagingOpException

Constructs an ImagingOpException object with the specified message.

IMG - Static variable in class javax.swing.text.html.HTML.Tag

IMG_ALIGN_BOTTOM - Static variable in class javax.swing.text.html.HTMLEditorKit

Align images at the bottom.

IMG_ALIGN_MIDDLE - Static variable in class javax.swing.text.html.HTMLEditorKit

Align images in the middle.

IMG_ALIGN_TOP - Static variable in class javax.swing.text.html.HTMLEditorKit

Align images at the top.

IMG_BORDER - Static variable in class javax.swing.text.html.**HTMLEditorKit**

Align images at the border.

IMP_LIMIT - exception org.omg.CORBA.**IMP_LIMIT**.

The CORBA **IMP_LIMIT** exception, which is thrown when the implementation limit has been violated.

IMP_LIMIT() - Constructor for class org.omg.CORBA.**IMP_LIMIT**

Constructs an **IMP_LIMIT** exception with a default minor code of 0 and a completion state of **COMPLETED_NO**.

IMP_LIMIT(int, CompletionStatus) - Constructor for class org.omg.CORBA.**IMP_LIMIT**

Constructs an **IMP_LIMIT** exception with the specified minor code and completion status.

IMP_LIMIT(String) - Constructor for class org.omg.CORBA.**IMP_LIMIT**

Constructs an **IMP_LIMIT** exception with the specified detail message, a minor code of 0, and a completion state of **COMPLETED_NO**.

IMP_LIMIT(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.**IMP_LIMIT**

Constructs an **IMP_LIMIT** exception with the specified detail message, minor code, and completion status.

impl - Variable in class javax.naming.**CompoundName**

Implementation of this compound name.

implAccept(Socket) - Method in class java.net.**ServerSocket**

Subclasses of **ServerSocket** use this method to override **accept()** to return their own subclass of socket.

IMPLEMENTATION_TITLE - Static variable in class java.util.jar.**Attributes.Name**

Name object for Implementation-Title manifest attribute used for package versioning.

IMPLEMENTATION_URL - Static variable in class java.util.jar.**Attributes.Name**

Name object for Implementation-Vendor-URL manifest attribute used for package versioning.

IMPLEMENTATION_VENDOR - Static variable in class java.util.jar.**Attributes.Name**

Name object for Implementation-Vendor manifest attribute used for package versioning.

IMPLEMENTATION_VENDOR_ID - Static variable in class java.util.jar.**Attributes.Name**

Name object for Implementation-Vendor-Id manifest attribute used for package versioning.

IMPLEMENTATION_VERSION - Static variable in class java.util.jar.**Attributes.Name**

Name object for Implementation-Version manifest attribute used for package versioning.

IMPLIED - Static variable in class javax.swing.text.html.**HTML.Tag**

All text content must be in a paragraph element.

IMPLIED - Static variable in class javax.swing.text.html.**HTMLEditorKit.ParserCallback**

This is passed as an attribute in the attributeset to indicate the element is implied eg, the string '**<foo>**' contains an implied html element and an implied body element.

IMPLIED - Static variable in interface javax.swing.text.html.parser.**DTDConstants**

implies(CodeSource) - Method in class java.security.**CodeSource**

Returns true if this **CodeSource** object "implies" the specified **CodeSource**.

implies(Permission) - Method in class java.io.**FilePermission**

Checks if this **FilePermission** object "implies" the specified permission.

implies(Permission) - Method in class java.net.**SocketPermission**

Checks if this socket permission object "implies" the specified permission.

implies(Permission) - Method in class java.security.**Permission**

Checks if the specified permission's actions are "implied by" this object's actions.

implies(Permission) - Method in class java.security.**BasicPermission**

Checks if the specified permission is "implied" by this object.

implies(Permission) - Method in class java.security.UnresolvedPermission

This method always returns false for unresolved permissions.

implies(Permission) - Method in class java.security.AllPermission

Checks if the specified permission is "implied" by this object.

implies(Permission) - Method in class java.security.ProtectionDomain

Check and see if this ProtectionDomain implies the permissions expressed in the Permission object.

implies(Permission) - Method in class java.security.PermissionCollection

Checks to see if the specified permission is implied by the collection of Permission objects held in this PermissionCollection.

implies(Permission) - Method in class java.security.Permissions

Checks to see if this object's PermissionCollection for permissions of the specified permission's type implies the permissions expressed in the *permission* object.

implies(Permission) - Method in class java.util.PropertyPermission

Checks if this PropertyPermission object "implies" the specified permission.

importedKeyCascade - Static variable in interface java.sql.DatabaseMetaData

A possible value for the columns UPDATE_RULE and DELETE_RULE in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeyInitiallyDeferred - Static variable in interface java.sql.DatabaseMetaData

A possible value for the column DEFERRABILITY in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeyInitiallyImmediate - Static variable in interface java.sql.DatabaseMetaData

A possible value for the column DEFERRABILITY in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeyNoAction - Static variable in interface java.sql.DatabaseMetaData

A possible value for the columns UPDATE_RULE and DELETE_RULE in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeyNotDeferrable - Static variable in interface java.sql.DatabaseMetaData

A possible value for the column DEFERRABILITY in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeyRestrict - Static variable in interface java.sql.DatabaseMetaData

A possible value for the columns UPDATE_RULE and DELETE_RULE in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeySetDefault - Static variable in interface java.sql.DatabaseMetaData

A possible value for the columns UPDATE_RULE and DELETE_RULE in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importedKeySetNull - Static variable in interface java.sql.DatabaseMetaData

A possible value for the columns UPDATE_RULE and DELETE_RULE in the ResultSet objects returned by the methods getImportedKeys, getExportedKeys, and getCrossReference.

importStyleSheet(URL) - Method in class javax.swing.text.html.StyleSheet

Imports a style sheet from url.

in - Variable in class java.io.FilterReader

The underlying character-input stream, or null if the stream has been closed.

in - Variable in class java.io.FilterInputStream

The input stream to be filtered.

in - Variable in class java.io.PipedInputStream

The index of the position in the circular buffer at which the next byte of data will be stored when received from the connected piped output stream.

in - Static variable in class java.io.FileDescriptor

A handle to the standard input stream.

in - Static variable in class java.lang.System

The "standard" input stream.

INACTIVE_CAPTION - Static variable in class java.awt.SystemColor

The array index for the inactive caption background color.

INACTIVE_CAPTION_BORDER - Static variable in class java.awt.SystemColor

The array index for the inactive caption border color.

INACTIVE_CAPTION_TEXT - Static variable in class java.awt.SystemColor

The array index for the inactive caption text color.

inactive(ActivationID) - Static method in class java.rmi.activation.Activatable

Informs the system that the object with the corresponding activation id is currently inactive.

inactiveCaption - Static variable in class java.awt.SystemColor

The background color for inactive captions in window borders.

inactiveCaptionBorder - Static variable in class java.awt.SystemColor

The border color for inactive captios in window borders.

inactiveCaptionText - Static variable in class java.awt.SystemColor

The text color for inactive captions in window borders.

inactiveGroup() - Method in class java.rmi.activation.ActivationGroup

This protected method is necessary for subclasses to make the `inactiveGroup` callback to the group's monitor.

inactiveGroup(ActivationGroupID, long) - Method in interface java.rmi.activation.ActivationMonitor

Informs that the group is now inactive.

inactiveObject(ActivationID) - Method in class java.rmi.activation.ActivationGroup

The group's `inactiveObject` method is called indirectly via a call to the `Activatable.inactive` method.

inactiveObject(ActivationID) - Method in interface java.rmi.activation.ActivationMonitor

An activation group calls its monitor's `inactiveObject` method when an object in its group becomes inactive (deactivates).

inCheck - Variable in class java.lang.SecurityManager

Deprecated. *This type of security checking is not recommended. It is recommended that the `checkPermission` call be used instead.*

inClass(String) - Method in class java.lang.SecurityManager

Deprecated. *This type of security checking is not recommended. It is recommended that the `checkPermission` call be used instead.*

inClassLoader() - Method in class java.lang.SecurityManager

Deprecated. *This type of security checking is not recommended. It is recommended that the `checkPermission` call be used instead.*

inclusions - Variable in class javax.swing.text.html.parser.Element

IncompatibleClassChangeError - error java.lang.IncompatibleClassChangeError.

Thrown when an incompatible class change has occurred to some class definition.

IncompatibleClassChangeError() - Constructor for class java.lang.IncompatibleClassChangeError

Constructs an `IncompatibleClassChangeError` with no detail message.

IncompatibleClassChangeError(String) - Constructor for class java.lang.IncompatibleClassChangeError

Constructs an `IncompatibleClassChangeError` with the specified detail message.

InconsistentTypeCode - exception org.omg.CORBA.ORBPackage.InconsistentTypeCode.

`InconsistentTypeCode` is thrown when an attempt is made to create a dynamic any with a type code that

does not match the particular subclass of DynAny.

InconsistentTypeCode() - Constructor for class org.omg.CORBA.ORBPackage.InconsistentTypeCode

Constructs an InconsistentTypeCode user exception with no reason message.

InconsistentTypeCode(String) - Constructor for class org.omg.CORBA.ORBPackage.InconsistentTypeCode

Constructs an InconsistentTypeCode user exception with the specified reason message.

incrButton - Variable in class javax.swing.plaf.basic.BasicScrollBarUI

INCREASE_HIGHLIGHT - Static variable in class javax.swing.plaf.basic.BasicScrollBarUI

increaseButton - Variable in class javax.swing.plaf.metal.MetalScrollBarUI

incrIndent() - Method in class javax.swing.text.AbstractWriter

Increments the indent level.

inDaylightTime(Date) - Method in class java.util.TimeZone

Queries if the given date is in daylight savings time in this time zone.

inDaylightTime(Date) - Method in class java.util.SimpleTimeZone

Overrides TimeZone Queries if the given date is in Daylight Savings Time.

indent() - Method in class javax.swing.text.AbstractWriter

Does indentation.

index - Variable in class javax.swing.text.html.parser.Element

IndexColorModel - class java.awt.image.IndexColorModel.

The IndexColorModel class is a ColorModel class that works with pixel values consisting of a single sample which is an index into a fixed colormap in the default sRGB ColorSpace.

IndexColorModel(int, int, byte[], byte[], byte[]) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from the specified arrays of red, green, and blue components.

IndexColorModel(int, int, byte[], byte[], byte[], byte[]) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from the given arrays of red, green, blue and alpha components.

IndexColorModel(int, int, byte[], byte[], byte[], int) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from the given arrays of red, green, and blue components.

IndexColorModel(int, int, byte[], int, boolean) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from a single array of interleaved red, green, blue and optional alpha components.

IndexColorModel(int, int, byte[], int, boolean, int) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from a single array of interleaved red, green, blue and optional alpha components.

IndexColorModel(int, int, int[], int, boolean, int, int) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from an array of ints where each int is comprised of red, green, blue, and optional alpha components in the default RGB color model format.

IndexColorModel(int, int, int[], int, int, BigInteger) - Constructor for class java.awt.image.IndexColorModel

Constructs an IndexColorModel from an int array where each int is comprised of red, green, blue, and alpha components in the default RGB color model format.

IndexedPropertyDescriptor - class java.beans.IndexedPropertyDescriptor.

An IndexedPropertyDescriptor describes a property that acts like an array and has an indexed read and/or indexed write method to access specific elements of the array.

IndexedPropertyDescriptor(String, Class) - Constructor for class java.beans.IndexedPropertyDescriptor

This constructor constructs an `IndexedPropertyDescriptor` for a property that follows the standard Java conventions by having `getFoo` and `setFoo` accessor methods, for both indexed access and array access.

`IndexedPropertyDescriptor(String, Class, String, String, String, String)` - Constructor for class `java.beans.IndexedPropertyDescriptor`

This constructor takes the name of a simple property, and method names for reading and writing the property, both indexed and non-indexed.

`IndexedPropertyDescriptor(String, Method, Method, Method, Method, Method)` - Constructor for class `java.beans.IndexedPropertyDescriptor`

This constructor takes the name of a simple property, and Method objects for reading and writing the property.

`indexOf(int)` - Method in class `java.lang.String`

Returns the index within this string of the first occurrence of the specified character.

`indexOf(int, int)` - Method in class `java.lang.String`

Returns the index within this string of the first occurrence of the specified character, starting the search at the specified index.

`indexOf(Object)` - Method in class `java.util.AbstractList`

Returns the index in this list of the first occurrence of the specified element, or -1 if the list does not contain this element.

`indexOf(Object)` - Method in class `java.util.Vector`

Searches for the first occurrence of the given argument, testing for equality using the `equals` method.

`indexOf(Object)` - Method in class `java.util.LinkedList`

Returns the index in this list of the first occurrence of the specified element, or -1 if the List does not contain this element.

`indexOf(Object)` - Method in interface `java.util.List`

Returns the index in this list of the first occurrence of the specified element, or -1 if this list does not contain this element.

`indexOf(Object)` - Method in class `java.util.ArrayList`

Searches for the first occurrence of the given argument, testing for equality using the `equals` method.

`indexOf(Object)` - Method in class `javax.swing.DefaultListModel`

Searches for the first occurrence of the given argument.

`indexOf(Object)` - Method in class `javax.swing.plaf.basic.BasicDirectoryModel`

`indexOf(Object, int)` - Method in class `java.util.Vector`

Searches for the first occurrence of the given argument, beginning the search at `index`, and testing for equality using the `equals` method.

`indexOf(Object, int)` - Method in class `javax.swing.DefaultListModel`

Searches for the first occurrence of the given argument, beginning the search at `index`.

`indexOf(String)` - Method in class `java.lang.String`

Returns the index within this string of the first occurrence of the specified substring.

`indexOf(String, int)` - Method in class `java.lang.String`

Returns the index within this string of the first occurrence of the specified substring, starting at the specified index.

`indexOfComponent(Component)` - Method in class `javax.swing.JTabbedPane`

Returns the index of the tab for the specified component.

`indexOfTab(Icon)` - Method in class `javax.swing.JTabbedPane`

Returns the first tab index with a given `icon`, or -1 if no tab has this icon.

`indexOfTab(String)` - Method in class `javax.swing.JTabbedPane`

Returns the first tab index with a given title, or -1 if no tab has this title.

[IndexOutOfBoundsException](#) - exception java.lang.[IndexOutOfBoundsException](#).
 Thrown to indicate that an index of some sort (such as to an array, to a string, or to a vector) is out of range.

[IndexOutOfBoundsException\(\)](#) - Constructor for class java.lang.[IndexOutOfBoundsException](#)
 Constructs an [IndexOutOfBoundsException](#) with no detail message.

[IndexOutOfBoundsException\(String\)](#) - Constructor for class java.lang.[IndexOutOfBoundsException](#)
 Constructs an [IndexOutOfBoundsException](#) with the specified detail message.

[indexToLocation\(int\)](#) - Method in class javax.swing.[JList](#)
 Returns the origin of the specified item in [JList](#) coordinates.

[indexToLocation\(JList, int\)](#) - Method in class javax.swing.plaf.[ListUI](#)
 Returns the origin of the specified item in [JList](#) coordinates, null if index isn't valid.

[indexToLocation\(JList, int\)](#) - Method in class javax.swing.plaf.basic.[BasicListUI](#)

[indexToLocation\(JList, int\)](#) - Method in class javax.swing.plaf.multi.[MultiListUI](#)
 Call [indexToLocation](#) on each UI handled by this [MultiUI](#).

[IndirectionException](#) - exception org.omg.CORBA.portable.[IndirectionException](#).
 The [Indirection](#) exception is a Java specific system exception.

[IndirectionException\(int\)](#) - Constructor for class org.omg.CORBA.portable.[IndirectionException](#)
 Creates an [IndirectionException](#) with the right offset value.

[InetAddress](#) - class java.net.[InetAddress](#).
 This class represents an Internet Protocol (IP) address.

[inf](#) - Variable in class java.util.zip.[InflaterInputStream](#)
 Decompressor for this stream.

[inflate\(byte\[\]\)](#) - Method in class java.util.zip.[Inflater](#)
 Uncompresses bytes into specified buffer.

[inflate\(byte\[\], int, int\)](#) - Method in class java.util.zip.[Inflater](#)
 Uncompresses bytes into specified buffer.

[Inflater](#) - class java.util.zip.[Inflater](#).
 This class provides support for general purpose decompression using popular ZLIB compression library.

[Inflater\(\)](#) - Constructor for class java.util.zip.[Inflater](#)
 Creates a new decompressor.

[Inflater\(boolean\)](#) - Constructor for class java.util.zip.[Inflater](#)
 Creates a new decompressor.

[InflaterInputStream](#) - class java.util.zip.[InflaterInputStream](#).
 This class implements a stream filter for uncompressing data in the "deflate" compression format.

[InflaterInputStream\(InputStream\)](#) - Constructor for class java.util.zip.[InflaterInputStream](#)
 Creates a new input stream with a default decompressor and buffer size.

[InflaterInputStream\(InputStream, Inflater\)](#) - Constructor for class java.util.zip.[InflaterInputStream](#)
 Creates a new input stream with the specified decompressor and a default buffer size.

[InflaterInputStream\(InputStream, Inflater, int\)](#) - Constructor for class java.util.zip.[InflaterInputStream](#)
 Creates a new input stream with the specified decompressor and buffer size.

[info](#) - Static variable in class java.awt.[SystemColor](#)
 The background color for info(help) text.

[INFO](#) - Static variable in class java.awt.[SystemColor](#)
 The array index for the info background color.

INFO_TEXT - Static variable in class java.awt.SystemColor

The array index for the info text color.

inFontTag() - Method in class javax.swing.text.html.MinimalHTMLWriter

Returns true if we are currently in a tag.

INFORMATION_MESSAGE - Static variable in class javax.swing.JOptionPane

Used for information messages.

infoText - Static variable in class java.awt.SystemColor

The text color for info(help) text.

InheritableThreadLocal - class java.lang.InheritableThreadLocal.

This class extends ThreadLocal to provide inheritance of values from parent Thread to child Thread: when a child thread is created, the child receives initial values for all InheritableThreadLocals for which the parent has values.

InheritableThreadLocal() - Constructor for class java.lang.InheritableThreadLocal

Creates an InheritableThreadLocal variable.

inHitRegion(int, int) - Method in class javax.swing.tree.DefaultTreeCellEditor

Should return true if the passed in location is a valid mouse location to start editing from.

init() - Method in class java.applet.Applet

Called by the browser or applet viewer to inform this applet that it has been loaded into the system.

init() - Static method in class org.omg.CORBA.ORB

Returns the ORB singleton object.

init(AlgorithmParameterSpec) - Method in class java.security.AlgorithmParameters

Initializes this parameter object using the parameters specified in paramSpec.

init(AlgorithmParameterSpec) - Method in class java.security.AlgorithmParameterGenerator

Initializes this parameter generator with a set of algorithm-specific parameter generation values.

init(AlgorithmParameterSpec, SecureRandom) - Method in class java.security.AlgorithmParameterGenerator

Initializes this parameter generator with a set of algorithm-specific parameter generation values.

init(Applet, Properties) - Static method in class org.omg.CORBA.ORB

Creates a new ORB instance for an applet.

init(byte[]) - Method in class java.security.AlgorithmParameters

Imports the specified parameters and decodes them according to the primary decoding format for parameters.

init(byte[], String) - Method in class java.security.AlgorithmParameters

Imports the parameters from params and decodes them according to the specified decoding scheme.

init(Hashtable) - Method in class javax.naming.InitialContext

Initializes the initial context using the supplied environment.

init(int) - Method in class java.security.AlgorithmParameterGenerator

Initializes this parameter generator for a certain size.

init(int, SecureRandom) - Method in class java.security.AlgorithmParameterGenerator

Initializes this parameter generator for a certain size and source of randomness.

init(StateEditable, String) - Method in class javax.swing.undo.StateEdit

init(String[], Properties) - Static method in class org.omg.CORBA.ORB

Creates a new ORB instance for a standalone application.

init(String, Icon) - Method in class javax.swing.AbstractButton

init(String, Icon) - Method in class javax.swing.JMenuItem

Initialize the menu item with the specified text and icon.

initClassDefaults(UIDefaults) - Method in class javax.swing.plaf.basic.BasicLookAndFeel

Initialize the uiClassID to BasicComponentUI mapping.

initClassDefaults(UIDefaults) - Method in class javax.swing.plaf.metal.MetalLookAndFeel

Initialize the uiClassID to BasicComponentUI mapping.

initComponentDefaults(UIDefaults) - Method in class javax.swing.plaf.basic.BasicLookAndFeel

initComponentDefaults(UIDefaults) - Method in class javax.swing.plaf.metal.MetalLookAndFeel

INITIAL_CONTEXT_FACTORY - Static variable in interface javax.naming.Context

Constant that holds the name of the environment property for specifying the initial context factory to use.

INITIAL_SELECTION_VALUE_PROPERTY - Static variable in class javax.swing.JOptionPane

Bound property name for initialSelectionValue.

INITIAL_VALUE_PROPERTY - Static variable in class javax.swing.JOptionPane

Bounds property name for initialValue.

InitialContext - class javax.naming.InitialContext.

This class is the starting context for performing naming operations.

InitialContext() - Constructor for class javax.naming.InitialContext

Constructs an initial context.

InitialContext(boolean) - Constructor for class javax.naming.InitialContext

Constructs an initial context with the option of not initializing it.

InitialContext(Hashtable) - Constructor for class javax.naming.InitialContext

Constructs an initial context using the supplied environment.

InitialContextFactory - interface javax.naming.spi.InitialContextFactory.

This interface represents a factory that creates an initial context.

InitialContextFactoryBuilder - interface javax.naming.spi.InitialContextFactoryBuilder.

This interface represents a builder that creates initial context factories.

InitialDirContext - class javax.naming.directory.InitialDirContext.

This class is the starting context for performing directory operations.

InitialDirContext() - Constructor for class javax.naming.directory.InitialDirContext

Constructs an initial DirContext.

InitialDirContext(boolean) - Constructor for class javax.naming.directory.InitialDirContext

Constructs an initial DirContext with the option of not initializing it.

InitialDirContext(Hashtable) - Constructor for class javax.naming.directory.InitialDirContext

Constructs an initial DirContext using the supplied environment.

initialFocusComponent - Variable in class javax.swing.plaf.basic.BasicOptionPaneUI

Component to receive focus when messaged with selectInitialValue.

INITIALIZE - exception org.omg.CORBA.INITIALIZE.

The CORBA INITIALIZE exception, which is thrown when there is an ORB initialization error.

initialize() - Method in class java.beans.beancontext.BeanContextSupport

protected method called from constructor and readObject to initialize transient state of BeanContextSupport instance.

initialize() - Method in class java.beans.beancontext.BeanContextServicesSupport

called by BeanContextSupport superclass during construction and deserialization to initialize subclass transient state.

initialize() - Method in class javax.swing.LookAndFeel

UIManager.setLookAndFeel calls this method before the first call (and typically the only call) to

getDefaults().

INITIALIZE() - Constructor for class org.omg.CORBA.INITIALIZE

Constructs an INITIALIZE exception with a default minor code of 0 and a completion state of `CompletionStatus.COMPLETED_NO`.

initialize(AlgorithmParameterSpec) - Method in class java.security.KeyPairGenerator

Initializes the key pair generator using the specified parameter set and the `SecureRandom` implementation of the highest-priority installed provider as the source of randomness.

initialize(AlgorithmParameterSpec, SecureRandom) - Method in class java.security.KeyPairGeneratorSpi

Initializes the key pair generator using the specified parameter set and user-provided source of randomness.

initialize(AlgorithmParameterSpec, SecureRandom) - Method in class java.security.KeyPairGenerator

Initializes the key pair generator with the given parameter set and source of randomness.

initialize(Applet, BeanContext) - Method in interface java.beans.AppletInitializer

If passed to the appropriate variant of `java.beans.Beans.instantiate` this method will be called in order to associate the newly instantiated Applet (JavaBean) with its `AppletContext`, `AppletStub`, and `Container`.

initialize(DSAParams, SecureRandom) - Method in interface java.security.interfaces.DSAKeyPairGenerator

Initializes the key pair generator using `p`, `q` and `g`, the DSA family parameters.

initialize(int) - Method in class java.security.KeyPairGenerator

Initializes the key pair generator for a certain keysize using a default parameter set and the `SecureRandom` implementation of the highest-priority installed provider as the source of randomness.

initialize(int, boolean, SecureRandom) - Method in interface java.security.interfaces.DSAKeyPairGenerator

Initializes the key pair generator for a given modulus length, without parameters.

INITIALIZE(int, CompletionStatus) - Constructor for class org.omg.CORBA.INITIALIZE

Constructs an INITIALIZE exception with the specified minor code and completion status.

initialize(int, SecureRandom) - Method in class java.security.KeyPairGeneratorSpi

Initializes the key pair generator for a certain keysize, using the default parameter set.

initialize(int, SecureRandom) - Method in class java.security.KeyPairGenerator

Initializes the key pair generator for a certain keysize with the given source of randomness (and a default parameter set).

INITIALIZE(String) - Constructor for class org.omg.CORBA.INITIALIZE

Constructs an INITIALIZE exception with the specified detail message, a minor code of 0, and a completion state of `CompletionStatus.COMPLETED_NO`.

INITIALIZE(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.INITIALIZE

Constructs an INITIALIZE exception with the specified detail message, minor code, and completion status.

initializeAutoscrolling(Point) - Method in class java.awt.dnd.DropTarget

initializeAutoscrolling

initializeBeanContextResources() - Method in class java.beans.beancontext.BeanContextChildSupport

This method may be overridden by subclasses to provide their own initialization behaviors.

initializeBeanContextResources() - Method in class java.beans.beancontext.BeanContextServicesSupport

called from `setBeanContext` to notify a `BeanContextChild` to allocate resources obtained from the nesting `BeanContext`.

initializeDesktopProperties() - Method in class java.awt.Toolkit

initializeDesktopProperties

initializeLocalVars() - Method in class javax.swing.JTable

Initializes table properties to their default values.

initializeLocalVars() - Method in class javax.swing.table.JTableHeader

Initializes the local variables and properties with default values.

Initializer - class org.omg.CORBA.Initializer.

This is the mapping for an IDL structure which specifies an initializer for a value type.

Initializer() - Constructor for class org.omg.CORBA.Initializer

Constructs an Initializer object with the members attribute null.

Initializer(StructMember[]) - Constructor for class org.omg.CORBA.Initializer

Constructs an Initializer object and assigns the members attribute with the given parameter.

InitialLdapContext - class javax.naming.ldap.InitialLdapContext.

This class is the starting context for performing LDAPv3-style extended operations and controls.

InitialLdapContext() - Constructor for class javax.naming.ldap.InitialLdapContext

Constructs an initial context using no environment properties or connection request controls.

InitialLdapContext(Hashtable, Control[]) - Constructor for class javax.naming.ldap.InitialLdapContext

Constructs an initial context using environment properties and connection request controls.

initialSelectionValue - Variable in class javax.swing.JOptionPane

Initial value to select in selectionValues.

initialValue - Variable in class javax.swing.JOptionPane

Value that should be initially selected in options.

initialValue() - Method in class java.lang.ThreadLocal

Returns the calling thread's initial value for this ThreadLocal variable.

initSign(PrivateKey) - Method in class java.security.Signature

Initialize this object for signing.

initSign(PrivateKey, SecureRandom) - Method in class java.security.Signature

Initialize this object for signing.

initSystemColorDefaults(UIDefaults) - Method in class javax.swing.plaf.basic.BasicLookAndFeel

Load the SystemColors into the defaults table.

initSystemColorDefaults(UIDefaults) - Method in class javax.swing.plaf.metal.MetalLookAndFeel

Load the SystemColors into the defaults table.

initVerify(Certificate) - Method in class java.security.Signature

Initializes this object for verification, using the public key from the given certificate.

initVerify(PublicKey) - Method in class java.security.Signature

Initializes this object for verification.

InlineView - class javax.swing.text.html.InlineView.

Displays the *inline element* styles based upon css attributes.

InlineView(Element) - Constructor for class javax.swing.text.html.InlineView

Constructs a new view wrapped on an element.

INPUT - Static variable in class javax.swing.text.html.HTML.Tag

INPUT_METHOD_EVENT_MASK - Static variable in class java.awt.AWTEvent

The event mask for selecting input method events.

INPUT_METHOD_FIRST - Static variable in class java.awt.event.InputMethodEvent

Marks the first integer id for the range of input method event ids.

INPUT_METHOD_HIGHLIGHT - Static variable in class java.awt.font.TextAttribute

Attribute key for input method highlight styles.

INPUT_METHOD_LAST - Static variable in class java.awt.event.InputMethodEvent

Marks the last integer id for the range of input method event ids.

INPUT_METHOD_SEGMENT - Static variable in class java.text.AttributedString.CharacterIterator.Attribute

Attribute key for input method segments.

INPUT_METHOD_TEXT_CHANGED - Static variable in class java.awt.event.InputMethodEvent

The event type indicating changed input method text.

INPUT_METHOD_UNDERLINE - Static variable in class java.awt.font.TextAttribute

Attribute key for input method underline adornments.

INPUT_VALUE_PROPERTY - Static variable in class javax.swing.JOptionPane

Bound property name for inputValue.

inputComponent - Variable in class javax.swing.plaf.basic.BasicOptionPaneUI

JComponent provide for input if optionPane.getWantsInput() returns true.

InputContext - class java.awt.im.InputContext.

An InputContext object manages the communication between text editing components and input methods.

InputContext() - Constructor for class java.awt.im.InputContext

Constructs an InputContext.

InputEvent - class java.awt.event.InputEvent.

The root event class for all component-level input events.

InputMap - class javax.swing.InputMap.

InputMap provides a binding between an input event (currently only KeyStrokes are used) and an Object.

InputMap() - Constructor for class javax.swing.InputMap

Creates an InputMap with no parent and no mappings.

InputMapUIResource - class javax.swing.plaf.InputMapUIResource.

A subclass of javax.swing.InputMap that implements UIResource.

InputMapUIResource() - Constructor for class javax.swing.plaf.InputMapUIResource

InputMethod - interface java.awt.im.spi.InputMethod.

Defines the interface for an input method that supports complex text input.

InputMethodContext - interface java.awt.im.spi.InputMethodContext.

Provides methods that input methods can use to communicate with their client components or to request other services.

InputMethodDescriptor - interface java.awt.im.spi.InputMethodDescriptor.

Defines methods that provide sufficient information about an input method to enable selection and loading of that input method.

InputMethodEvent - class java.awt.event.InputMethodEvent.

Input method events contain information about text that is being composed using an input method.

InputMethodEvent(Component, int, AttributedCharacterIterator, int, TextHitInfo, TextHitInfo) - Constructor for class java.awt.event.InputMethodEvent

Constructs an InputMethodEvent with the specified source component, type, text, caret, and visiblePosition.

InputMethodEvent(Component, int, TextHitInfo, TextHitInfo) - Constructor for class java.awt.event.InputMethodEvent

Constructs an InputMethodEvent with the specified source component, type, caret, and visiblePosition.

InputMethodHighlight - class java.awt.im.InputMethodHighlight.

An InputMethodHighlight is used to describe the highlight attributes of text being composed.

InputMethodHighlight(boolean, int) - Constructor for class java.awt.im.InputMethodHighlight

Constructs an input method highlight record.

InputMethodHighlight(boolean, int, int) - Constructor for class java.awt.im.InputMethodHighlight

Constructs an input method highlight record.

InputMethodHighlight(boolean, int, int, Map) - Constructor for class java.awt.im.InputMethodHighlight

Constructs an input method highlight record.

InputMethodListener - interface java.awt.event.InputMethodListener.

The listener interface for receiving input method events.

InputMethodRequests - interface java.awt.im.InputMethodRequests.

InputMethodRequests defines the requests that a text editing component has to handle in order to work with input methods.

inputMethodTextChanged(InputMethodEvent) - Method in class java.awt.AWTEventMulticaster

Handles the inputMethodTextChanged event by invoking the inputMethodTextChanged methods on listener-a and listener-b.

inputMethodTextChanged(InputMethodEvent) - Method in interface java.awt.event.InputMethodListener

Invoked when the text entered through an input method has changed.

InputStream - class java.io.InputStream.

This abstract class is the superclass of all classes representing an input stream of bytes.

InputStream - class org.omg.CORBA.portable.InputStream.

InputStream is the Java API for reading IDL types from CDR marshal streams.

InputStream - class org.omg.CORBA_2_3.portable.InputStream.

InputStream provides for the reading of all of the mapped IDL types from the stream.

InputStream() - Constructor for class java.io.InputStream

InputStream() - Constructor for class org.omg.CORBA.portable.InputStream

InputStream() - Constructor for class org.omg.CORBA_2_3.portable.InputStream

InputStreamReader - class java.io.InputStreamReader.

An InputStreamReader is a bridge from byte streams to character streams: It reads bytes and translates them into characters according to a specified character encoding.

InputStreamReader(InputStream) - Constructor for class java.io.InputStreamReader

Create an InputStreamReader that uses the default character encoding.

InputStreamReader(InputStream, String) - Constructor for class java.io.InputStreamReader

Create an InputStreamReader that uses the named character encoding.

InputSubset - class java.awt.im.InputSubset.

Defines additional Unicode subsets for use by input methods.

inputValue - Variable in class javax.swing.JOptionPane

Value the user has input.

InputVerifier - class javax.swing.InputVerifier.

The purpose of this class is to help clients support smooth focus navigation through GUIs with text fields.

InputVerifier() - Constructor for class javax.swing.InputVerifier

inRange(Element) - Method in class javax.swing.text.AbstractWriter

This method determines whether the current element is in the range specified.

INSERT - Static variable in class java.awt.Event

The Insert key, a non-ASCII action key.

INSERT - Static variable in interface javax.accessibility.AccessibleTableModelChange

Identifies the insertion of new rows and/or columns.

INSERT - Static variable in class javax.swing.event.DocumentEvent.EventType

Insert type.

INSERT - Static variable in class javax.swing.event.TableModelEvent
Identifies the addition of new rows or columns.

insert_any(Any) - Method in interface org.omg.CORBA.DynAny
Inserts the given org.omg.CORBA.Any object as the value for this DynAny object.

insert_any(Any) - Method in class org.omg.CORBA.Any
Inserts the given Any object into this Any object's value field.

insert_boolean(boolean) - Method in interface org.omg.CORBA.DynAny
Inserts the given boolean as the value for this DynAny object.

insert_boolean(boolean) - Method in class org.omg.CORBA.Any
Inserts the given boolean into this Any object's value field.

insert_char(char) - Method in interface org.omg.CORBA.DynAny
Inserts the given char as the value for this DynAny object.

insert_char(char) - Method in class org.omg.CORBA.Any
Inserts the given char into this Any object's value field.

insert_double(double) - Method in interface org.omg.CORBA.DynAny
Inserts the given double as the value for this DynAny object.

insert_double(double) - Method in class org.omg.CORBA.Any
Inserts the given double into this Any object's value field.

insert_fixed(BigDecimal) - Method in class org.omg.CORBA.Any
Inserts the given java.math.BigDecimal object into this Any object's value field.

insert_fixed(BigDecimal, TypeCode) - Method in class org.omg.CORBA.Any
Inserts the given java.math.BigDecimal object into this Any object's value field.

insert_float(float) - Method in interface org.omg.CORBA.DynAny
Inserts the given float as the value for this DynAny object.

insert_float(float) - Method in class org.omg.CORBA.Any
Inserts the given float into this Any object's value field.

insert_long(int) - Method in interface org.omg.CORBA.DynAny
Inserts the given int as the value for this DynAny object.

insert_long(int) - Method in class org.omg.CORBA.Any
Inserts the given int into this Any object's value field.

insert_longlong(long) - Method in interface org.omg.CORBA.DynAny
Inserts the given long as the value for this DynAny object.

insert_longlong(long) - Method in class org.omg.CORBA.Any
Inserts the given long into this Any object's value field.

insert_Object(Object) - Method in class org.omg.CORBA.Any
Inserts the given org.omg.CORBA.Object object into this Any object's value field.

insert_Object(Object, TypeCode) - Method in class org.omg.CORBA.Any
Inserts the given org.omg.CORBA.Object object into this Any object's value field.

insert_octet(byte) - Method in interface org.omg.CORBA.DynAny
Inserts the given byte as the value for this DynAny object.

insert_octet(byte) - Method in class org.omg.CORBA.Any
Inserts the given byte into this Any object's value field.

insert_Principal(Principal) - Method in class org.omg.CORBA.Any
Deprecated. *Deprecated by CORBA 2.2.*

insert_reference(Object) - Method in interface org.omg.CORBA.DynAny
Inserts the given org.omg.CORBA.Object as the value for this DynAny object.

insert_short(short) - Method in interface org.omg.CORBA.DynAny

Inserts the given short as the value for this DynAny object.

[insert_short\(short\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given short into this Any object's value field.

[insert_Streamable\(Streamable\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given Streamable object into this Any object's value field.

[insert_string\(String\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given String object as the value for this DynAny object.

[insert_string\(String\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given String object into this Any object's value field.

[insert_typecode\(TypeCode\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given org.omg.CORBA.TypeCode as the value for this DynAny object.

[insert_TypeCode\(TypeCode\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given TypeCode object into this Any object's value field.

[insert_ulong\(int\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given int as the value for this DynAny object.

[insert_ulong\(int\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given int into this Any object's value field.

[insert_ulonglong\(long\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given long as the value for this DynAny object.

[insert_ulonglong\(long\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given long into this Any object's value field.

[insert_ushort\(short\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given short as the value for this DynAny object.

[insert_ushort\(short\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given short into this Any object's value field.

[insert_val\(Serializable\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given java.io.Serializable object as the value for this DynAny object.

[insert_Value\(Serializable\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given java.io.Serializable object into this Any object's value field.

[insert_Value\(Serializable, TypeCode\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given java.io.Serializable object into this Any object's value field.

[insert_wchar\(char\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given char as the value for this DynAny object.

[insert_wchar\(char\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given char into this Any object's value field.

[insert_wstring\(String\)](#) - Method in interface org.omg.CORBA.DynAny
 Inserts the given String as the value for this DynAny object.

[insert_wstring\(String\)](#) - Method in class org.omg.CORBA.Any
 Inserts the given String object into this Any object's value field.

[insert\(Action, int\)](#) - Method in class javax.swing.JMenu
 Inserts a new menu item attached to the specified Action object at a given position.

[insert\(Action, int\)](#) - Method in class javax.swing.JPopupMenu
 Inserts a menu item for the specified Action object at a given position.

[insert\(Any, AlreadyBound\)](#) - Static method in class
 org.omg.CosNaming.NamingContextPackage.AlreadyBoundHelper

[insert\(Any, Any\[\]\)](#) - Static method in class org.omg.CORBA.AnySeqHelper

[insert\(Any, Binding\)](#) - Static method in class org.omg.CosNaming.[BindingHelper](#)

[insert\(Any, Binding\[\]\)](#) - Static method in class org.omg.CosNaming.[BindingListHelper](#)

[insert\(Any, BindingIterator\)](#) - Static method in class org.omg.CosNaming.[BindingIteratorHelper](#)

[insert\(Any, BindingType\)](#) - Static method in class org.omg.CosNaming.[BindingTypeHelper](#)

[insert\(Any, boolean\[\]\)](#) - Static method in class org.omg.CORBA.[BooleanSeqHelper](#)

[insert\(Any, byte\[\]\)](#) - Static method in class org.omg.CORBA.[OctetSeqHelper](#)

[insert\(Any, CannotProceed\)](#) - Static method in class
org.omg.CosNaming.NamingContextPackage.[CannotProceedHelper](#)

[insert\(Any, char\[\]\)](#) - Static method in class org.omg.CORBA.[CharSeqHelper](#)

[insert\(Any, char\[\]\)](#) - Static method in class org.omg.CORBA.[WCharSeqHelper](#)

[insert\(Any, CompletionStatus\)](#) - Static method in class org.omg.CORBA.[CompletionStatusHelper](#)

[insert\(Any, Current\)](#) - Static method in class org.omg.CORBA.[CurrentHelper](#)

[insert\(Any, DefinitionKind\)](#) - Static method in class org.omg.CORBA.[DefinitionKindHelper](#)

[insert\(Any, double\[\]\)](#) - Static method in class org.omg.CORBA.[DoubleSeqHelper](#)

[insert\(Any, float\[\]\)](#) - Static method in class org.omg.CORBA.[FloatSeqHelper](#)

[insert\(Any, IDLType\)](#) - Static method in class org.omg.CORBA.[IDLTypeHelper](#)

[insert\(Any, int\)](#) - Static method in class org.omg.CORBA.[PolicyTypeHelper](#)

[insert\(Any, int\[\]\)](#) - Static method in class org.omg.CORBA.[LongSeqHelper](#)

[insert\(Any, int\[\]\)](#) - Static method in class org.omg.CORBA.[ULongSeqHelper](#)

[insert\(Any, InvalidName\)](#) - Static method in class
org.omg.CosNaming.NamingContextPackage.[InvalidNameHelper](#)

[insert\(Any, long\[\]\)](#) - Static method in class org.omg.CORBA.[ULongLongSeqHelper](#)

[insert\(Any, long\[\]\)](#) - Static method in class org.omg.CORBA.[LongLongSeqHelper](#)

[insert\(Any, NameComponent\)](#) - Static method in class org.omg.CosNaming.[NameComponentHelper](#)

[insert\(Any, NameComponent\[\]\)](#) - Static method in class org.omg.CosNaming.[NameHelper](#)

[insert\(Any, NameValuePair\)](#) - Static method in class org.omg.CORBA.[NameValuePairHelper](#)

[insert\(Any, NamingContext\)](#) - Static method in class org.omg.CosNaming.[NamingContextHelper](#)

[insert\(Any, NotEmpty\)](#) - Static method in class
org.omg.CosNaming.NamingContextPackage.[NotEmptyHelper](#)

[insert\(Any, NotFound\)](#) - Static method in class org.omg.CosNaming.NamingContextPackage.[NotFoundHelper](#)

[insert\(Any, NotFoundReason\)](#) - Static method in class
org.omg.CosNaming.NamingContextPackage.[NotFoundReasonHelper](#)

[insert\(Any, Object\)](#) - Static method in class org.omg.CORBA.[ObjectHelper](#)

[insert\(Any, Policy\)](#) - Static method in class org.omg.CORBA.[PolicyHelper](#)

[insert\(Any, Policy\[\]\)](#) - Static method in class org.omg.CORBA.[PolicyListHelper](#)

[insert\(Any, Serializable\)](#) - Static method in class org.omg.CORBA.[ValueBaseHelper](#)

[insert\(Any, ServiceDetail\)](#) - Static method in class org.omg.CORBA.[ServiceDetailHelper](#)

[insert\(Any, ServiceInformation\)](#) - Static method in class org.omg.CORBA.[ServiceInformationHelper](#)

[insert\(Any, SetOverrideType\)](#) - Static method in class org.omg.CORBA.[SetOverrideTypeHelper](#)

[insert\(Any, short\)](#) - Static method in class org.omg.CORBA.[VisibilityHelper](#)

[insert\(Any, short\[\]\)](#) - Static method in class org.omg.CORBA.[UShortSeqHelper](#)

[insert\(Any, short\[\]\)](#) - Static method in class org.omg.CORBA.[ShortSeqHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[IdentifierHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[StringValueHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[VersionSpecHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[WStringValueHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[RepositoryIdHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CORBA.[FieldNameHelper](#)

[insert\(Any, String\)](#) - Static method in class org.omg.CosNaming.[IstringHelper](#)

insert(Any, StructMember) - Static method in class org.omg.CORBA.StructMemberHelper

insert(Any, UnionMember) - Static method in class org.omg.CORBA.UnionMemberHelper

insert(Any, ValueMember) - Static method in class org.omg.CORBA.ValueMemberHelper

insert(Component, int) - Method in class javax.swing.JPopupMenu

Inserts the specified component into the menu at a given position.

insert(int, boolean) - Method in class java.lang.StringBuffer

Inserts the string representation of the boolean argument into this string buffer.

insert(int, char) - Method in class java.lang.StringBuffer

Inserts the string representation of the char argument into this string buffer.

insert(int, char[]) - Method in class java.lang.StringBuffer

Inserts the string representation of the char array argument into this string buffer.

insert(int, char[], int, int) - Method in class java.lang.StringBuffer

Inserts the string representation of a subarray of the str array argument into this string buffer.

insert(int, DefaultStyledDocument.ElementSpec[]) - Method in class javax.swing.text.DefaultStyledDocument

Inserts new elements in bulk.

insert(int, DefaultStyledDocument.ElementSpec[]) - Method in class javax.swing.text.html.HTMLDocument

Inserts new elements in bulk.

insert(int, double) - Method in class java.lang.StringBuffer

Inserts the string representation of the double argument into this string buffer.

insert(int, float) - Method in class java.lang.StringBuffer

Inserts the string representation of the float argument into this string buffer.

insert(int, int) - Method in class java.lang.StringBuffer

Inserts the string representation of the second int argument into this string buffer.

insert(int, int, DefaultStyledDocument.ElementSpec[], AbstractDocument.DefaultDocumentEvent) - Method in class javax.swing.text.DefaultStyledDocument.ElementBuffer

Inserts new content.

insert(int, long) - Method in class java.lang.StringBuffer

Inserts the string representation of the long argument into this string buffer.

insert(int, Object) - Method in class java.lang.StringBuffer

Inserts the string representation of the Object argument into this string buffer.

insert(int, String) - Method in class java.lang.StringBuffer

Inserts the string into this string buffer.

insert(int, View) - Method in class javax.swing.text.View

Inserts a single child view.

insert(JMenuItem, int) - Method in class javax.swing.JMenu

Inserts the specified JMenuItem at a given position.

insert(MenuItems, int) - Method in class java.awt.Menu

Inserts a menu item into this menu at the specified position.

insert(MutableTreeNode, int) - Method in class javax.swing.tree.DefaultMutableTreeNode

Removes newChild from its present parent (if it has a parent), sets the child's parent to this node, and then adds the child to this node's child array at index childIndex.

insert(MutableTreeNode, int) - Method in interface javax.swing.tree.MutableTreeNode

Adds child to the receiver at index.

insert(String, int) - Method in class java.awt.Menu

Inserts a menu item with the specified label into this menu at the specified position.

insert(String, int) - Method in class java.awt.Choice

Inserts the item into this choice at the specified position.

insert(String, int) - Method in class java.awt.TextArea

Inserts the specified text at the specified position in this text area.

insert(String, int) - Method in class javax.swing.JMenu

Inserts a new menu item with the specified text at a given position.

insert(String, int) - Method in class javax.swing.JTextArea

Inserts the specified text at the specified position.

insertAfterEnd(Element, String) - Method in class javax.swing.text.html.HTMLDocument

Inserts the HTML specified as a string after the the end of the given element.

insertAfterStart(Element, String) - Method in class javax.swing.text.html.HTMLDocument

Inserts the HTML specified as a string at the start of the element.

insertAtBoundary(JEditorPane, HTMLDocument, int, Element, String, HTML.Tag, HTML.Tag) - Method in class javax.swing.text.html.HTMLEditorKit.InsertHTMLTextAction

This is invoked when inserting at a boundary.

insertAtBoundry(JEditorPane, HTMLDocument, int, Element, String, HTML.Tag, HTML.Tag) - Method in class javax.swing.text.html.HTMLEditorKit.InsertHTMLTextAction

Deprecated. *As of Java 2 platform v1.3, use insertAtBoundary*

insertBeforeEnd(Element, String) - Method in class javax.swing.text.html.HTMLDocument

Inserts the HTML specified as a string at the end of the element.

insertBeforeStart(Element, String) - Method in class javax.swing.text.html.HTMLDocument

Inserts the HTML specified as string before the start of the given element.

insertBreakAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the action to place a line/paragraph break into the document.

insertChar(AttributedCharacterIterator, int) - Method in class java.awt.font.LineBreakMeasurer

Updates this LineBreakMeasurer after a single character is inserted into the text, and sets the current position to the beginning of the paragraph.

insertChar(AttributedCharacterIterator, int) - Method in class java.awt.font.TextMeasurer

Updates the TextMeasurer after a single character has been inserted into the paragraph currently represented by this TextMeasurer.

insertComponent(Component) - Method in class javax.swing.JTextPane

Inserts a component into the document as a replacement for the currently selected content.

insertContentAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the action to place content into the associated document.

insertElementAt(Object, int) - Method in class java.util.Vector

Inserts the specified object as a component in this vector at the specified index.

insertElementAt(Object, int) - Method in class javax.swing.DefaultComboBoxModel

insertElementAt(Object, int) - Method in class javax.swing.DefaultListModel

Inserts the specified object as a component in this list at the specified index.

insertElementAt(Object, int) - Method in interface javax.swing.MutableComboBoxModel

Adds an item at a specific index

insertEntries(int, int, int) - Method in class javax.swing.SizeSequence

Adds a contiguous group of entries to this SizeSequence.

insertHTML(HTMLDocument, int, String, int, int, HTML.Tag) - Method in class

javax.swing.text.html.HTMLEditorKit

Inserts HTML into an existing document.

insertHTML(JEditorPane, HTMLDocument, int, String, int, HTML.Tag) - Method in class

javax.swing.text.html.HTMLEditorKit.InsertHTMLTextAction

A cover for HTMLEditorKit.insertHTML.

insertIcon(Icon) - Method in class javax.swing.JTextPane

Inserts an icon into the document as a replacement for the currently selected content.

insertIndexForLayer(int, int) - Method in class javax.swing.JLayeredPane

Primitive method that determines the proper location to insert a new child based on layer and position requests.

insertIndexInterval(int, int, boolean) - Method in class javax.swing.DefaultListSelectionModel

Insert length indices beginning before/after index.

insertIndexInterval(int, int, boolean) - Method in interface javax.swing.ListSelectionModel

Insert length indices beginning before/after index.

insertItemAt(Object, int) - Method in class javax.swing.JComboBox

Inserts an item into the item list at a given index.

insertNodeInto(MutableTreeNode, MutableTreeNode, int) - Method in class javax.swing.tree.DefaultTreeModel

Invoked this to insert newChild at location index in parents children.

insertProviderAt(Provider, int) - Static method in class java.security.Security

Adds a new provider, at a specified position.

insertRow() - Method in interface java.sql.ResultSet

Inserts the contents of the insert row into this ResultSet object and into the database.

insertRow(int, Object[]) - Method in class javax.swing.table.DefaultTableModel

Inserts a row at row in the model.

insertRow(int, Vector) - Method in class javax.swing.table.DefaultTableModel

Inserts a row at row in the model.

insertsAreDetected(int) - Method in interface java.sql.DatabaseMetaData

Indicates whether or not a visible row insert can be detected by calling ResultSet.rowInserted().

insertSeparator(int) - Method in class java.awt.Menu

Inserts a separator at the specified position.

insertSeparator(int) - Method in class javax.swing.JMenu

Inserts a separator at the specified position.

insertString(int, String) - Method in interface javax.swing.text.AbstractDocument.Content

Inserts a string of characters into the sequence.

insertString(int, String) - Method in class javax.swing.text.StringContent

Inserts a string into the content.

insertString(int, String) - Method in class javax.swing.text.GapContent

Inserts a string into the content.

insertString(int, String, AttributeSet) - Method in interface javax.swing.text.Document

Inserts a string of content.

insertString(int, String, AttributeSet) - Method in class javax.swing.text.AbstractDocument

Inserts some content into the document.

insertTab(String, Icon, Component, String, int) - Method in class javax.swing.JTabbedPane

Inserts a component, at index, represented by a title and/or icon, either of which may be null.

insertTabAction - Static variable in class javax.swing.text.DefaultEditorKit

Name of the action to place a tab character into the document.

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class java.awt.[Dialog.AccessibleAWTDialog](#)

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class java.awt.[Frame.AccessibleAWTFrame](#)

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class java.awt.[TextField.AccessibleAWTTextField](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class java.awt.[TextArea.AccessibleAWTTextArea](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.accessibility.[AccessibleContext](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JComponent.AccessibleJComponent](#)

Gets the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[AbstractButton.AccessibleAbstractButton](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JTextField.AccessibleJTextField](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JEditorPane.AccessibleJEditorPane](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JList.AccessibleJList](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JList.AccessibleJList.AccessibleJListChild](#)

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JFrame.AccessibleJFrame](#)

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JSplitPane.AccessibleJSplitPane](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JTree.AccessibleJTree.AccessibleJTreeNode](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JTable.AccessibleJTable.AccessibleJTableCell](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JToolBar.AccessibleJToolBar](#)

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JMenuBar.AccessibleJMenuBar](#)

Get the accessible state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[ImageIcon.AccessibleImageIcon](#)

Gets the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JTextArea.AccessibleJTextArea](#)

Gets the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JScrollBar.AccessibleJScrollBar](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JProgressBar.AccessibleJProgressBar](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JDialog.AccessibleJDialog](#)

Get the state of this object.

[getAccessibleStateSet\(\)](#) - Method in class javax.swing.[JSlider.AccessibleJSlider](#)

Get the state set of this object.

[getAccessibleStateSet\(\)](#) - Method in class

[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleStateSet\(\)](#) - Method in class [javax.swing.text.JTextComponent.AccessibleJTextComponent](#)

Gets the state set of the JTextComponent.

[getAccessibleStateSet\(Component\)](#) - Static method in class [javax.swing.SwingUtilities](#)

Get the state of this object.

[getAccessibleSummary\(\)](#) - Method in interface [javax.accessibility.AccessibleTable](#)

Returns the summary description of the table.

[getAccessibleSummary\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)

Returns the summary description of the table.

[getAccessibleTable\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the AccessibleTable associated with an object

[getAccessibleTable\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable](#)

Get the AccessibleTable associated with this object.

[getAccessibleText\(\)](#) - Method in class [java.awt.TextComponent.AccessibleAWTTextComponent](#)

Get the AccessibleText associated with this object.

[getAccessibleText\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the AccessibleText associated with this object presently editable text on the display.

[getAccessibleText\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)

[getAccessibleText\(\)](#) - Method in class [javax.swing.JEditorPane.AccessibleJEditorPaneHTML](#)

[getAccessibleText\(\)](#) - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

[getAccessibleText\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

Get the AccessibleText associated with this object if one exists.

[getAccessibleText\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)

Gets the AccessibleText associated with this object if one exists.

[getAccessibleText\(\)](#) - Method in class [javax.swing.JLabel.AccessibleJLabel](#)

[getAccessibleText\(\)](#) - Method in class

[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getAccessibleText\(\)](#) - Method in class [javax.swing.text.JTextComponent.AccessibleJTextComponent](#)

Get the AccessibleText associated with this object.

[getAccessibleValue\(\)](#) - Method in class [java.awt.Scrollbar.AccessibleAWTScrollBar](#)

Get the AccessibleValue associated with this object.

[getAccessibleValue\(\)](#) - Method in class [java.awt.MenuItem.AccessibleAWTMenuItem](#)

Get the AccessibleValue associated with this object.

[getAccessibleValue\(\)](#) - Method in class [java.awt.Checkbox.AccessibleAWTCheckbox](#)

Get the AccessibleValue associated with this object.

[getAccessibleValue\(\)](#) - Method in class [java.awt.Button.AccessibleAWTButton](#)

Get the AccessibleValue associated with this object.

[getAccessibleValue\(\)](#) - Method in class [java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem](#)

Get the AccessibleValue associated with this object.

[getAccessibleValue\(\)](#) - Method in class [javax.accessibility.AccessibleContext](#)

Gets the AccessibleValue associated with this object that supports a Numerical value.
getAccessibleValue() - Method in class javax.swing.AbstractButton.AccessibleAbstractButton
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getAccessibleValue() - Method in class javax.swing.JInternalFrame.AccessibleJInternalFrame
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JInternalFrame.JDesktopIcon.AccessibleJDesktopIcon
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JSplitPane.AccessibleJSplitPane
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode
 Get the AccessibleValue associated with this object if one exists.
getAccessibleValue() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
 Gets the AccessibleValue associated with this object if one exists.
getAccessibleValue() - Method in class javax.swing.JScrollBar.AccessibleJScrollBar
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JProgressBar.AccessibleJProgressBar
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class javax.swing.JSlider.AccessibleJSlider
 Get the AccessibleValue associated with this object.
getAccessibleValue() - Method in class
 javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getAccessory() - Method in class javax.swing.JFileChooser
 Returns the accessory component.
getAccessoryPanel() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getAction() - Method in class javax.swing.AbstractButton
 Returns the currently set Action for this ActionEvent source, or null if no Action is set.
getAction() - Method in class javax.swing.JTextField
 Returns the currently set Action for this ActionEvent source, or null if no Action is set.
getAction() - Method in class javax.swing.JComboBox
 Returns the currently set Action for this ActionEvent source, or null if no Action is set.
getAction(KeyStroke) - Method in interface javax.swing.text.Keymap
 Fetches the action appropriate for the given symbolic event sequence.
getActionCommand() - Method in class java.awt.MenuItem
 Gets the command name of the action event that is fired by this menu item.
getActionCommand() - Method in class java.awt.Button
 Returns the command name of the action event fired by this button.
getActionCommand() - Method in class java.awt.event.ActionEvent
 Returns the command string associated with this action.
getActionCommand() - Method in class javax.swing.AbstractButton
 Returns the action command for this button.
getActionCommand() - Method in interface javax.swing.ButtonModel
 Returns the action command for this button.
getActionCommand() - Method in class javax.swing.JComboBox

Returns the action command that is included in the event sent to action listeners.

[getActionCommand\(\)](#) - Method in class [javax.swing.DefaultButtonModel](#)
Returns the action command for this button.

[getActionForKeyStroke\(KeyStroke\)](#) - Method in class [javax.swing.JComponent](#)
Returns the object that will perform the action registered for a given keystroke.

[getActionMap\(\)](#) - Method in class [javax.swing.JComponent](#)
Returns the ActionMap used to determine what Action to fire for particular KeyStroke binding.

[getActionMap\(\)](#) - Method in class [javax.swing.plaf.metal.MetalFileChooserUI](#)

[getActions\(\)](#) - Method in class [java.io.FilePermission](#)
Returns the "canonical string representation" of the actions.

[getActions\(\)](#) - Method in class [java.net.SocketPermission](#)
Returns the canonical string representation of the actions.

[getActions\(\)](#) - Method in class [java.security.Permission](#)
Returns the actions as a String.

[getActions\(\)](#) - Method in class [java.security.BasicPermission](#)
Returns the canonical string representation of the actions, which currently is the empty string "", since there are no actions for a BasicPermission.

[getActions\(\)](#) - Method in class [java.security.UnresolvedPermission](#)
Returns the canonical string representation of the actions, which currently is the empty string "", since there are no actions for an UnresolvedPermission.

[getActions\(\)](#) - Method in class [java.security.AllPermission](#)
Returns the canonical string representation of the actions.

[getActions\(\)](#) - Method in class [java.util.PropertyPermission](#)
Returns the "canonical string representation" of the actions.

[getActions\(\)](#) - Method in class [javax.swing.JTextField](#)
Fetches the command list for the editor.

[getActions\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)
Fetches the command list for the editor.

[getActions\(\)](#) - Method in class [javax.swing.text.EditorKit](#)
Fetches the set of commands that can be used on a text component that is using a model and view produced by this kit.

[getActions\(\)](#) - Method in class [javax.swing.text.DefaultEditorKit](#)
Fetches the set of commands that can be used on a text component that is using a model and view produced by this kit.

[getActions\(\)](#) - Method in class [javax.swing.text.StyledEditorKit](#)
Fetches the command list for the editor.

[getActions\(\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit](#)
Fetches the command list for the editor.

[getActivationDesc\(ActivationID\)](#) - Method in interface [java.rmi.activation.ActivationSystem](#)
Returns the activation descriptor, for the object with the activation identifier, id.

[getActivationGroupDesc\(ActivationGroupID\)](#) - Method in interface [java.rmi.activation.ActivationSystem](#)
Returns the activation group descriptor, for the group with the activation group identifier, id.

[getActualMaximum\(int\)](#) - Method in class [java.util.Calendar](#)
Return the maximum value that this field could have, given the current date.

[getActualMaximum\(int\)](#) - Method in class [java.util.GregorianCalendar](#)
Return the maximum value that this field could have, given the current date.

getActualMinimum(int) - Method in class java.util.Calendar

Return the minimum value that this field could have, given the current date.

getActualMinimum(int) - Method in class java.util.GregorianCalendar

Return the minimum value that this field could have, given the current date.

getAdditionalBeanInfo() - Method in interface java.beans.BeanInfo

This method allows a BeanInfo object to return an arbitrary collection of other BeanInfo objects that provide additional information on the current bean.

getAdditionalBeanInfo() - Method in class java.beans.SimpleBeanInfo

Claim there are no other relevant BeanInfo objects.

getAdditionalHeight() - Method in class javax.swing.plaf.metal.MetalIconFactory.FolderIcon16

getAdditionalHeight() - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeFolderIcon

getAdditionalHeight() - Method in class javax.swing.plaf.metal.MetalIconFactory.FileIcon16

getAdditionalHeight() - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeLeafIcon

getAddListenerMethod() - Method in class java.beans.EventSetDescriptor

Gets the method used to add event listeners.

getAddress() - Method in class java.net.InetAddress

Returns the raw IP address of this InetAddress object.

getAddress() - Method in class java.net.DatagramPacket

Returns the IP address of the machine to which this datagram is being sent or from which the datagram was received.

getAdjustable() - Method in class java.awt.event.AdjustmentEvent

Returns the Adjustable object where this event originated.

getAdjustmentType() - Method in class java.awt.event.AdjustmentEvent

Returns the type of adjustment which caused the value changed event.

getAdler() - Method in class java.util.zip.Deflater

Returns the ADLER-32 value of the uncompressed data.

getAdler() - Method in class java.util.zip.Inflater

Returns the ADLER-32 value of the uncompressed data.

getAdvance() - Method in class java.awt.font.GlyphMetrics

Returns the advance width or height of the glyph.

getAdvance() - Method in class java.awt.font.TextLayout

Returns the advance of this TextLayout.

getAdvance() - Method in class java.awt.font.GraphicAttribute

Returns the advance of this GraphicAttribute.

getAdvance() - Method in class java.awt.font.ImageGraphicAttribute

Returns the advance of this ImageGraphicAttribute.

getAdvance() - Method in class java.awt.font.ShapeGraphicAttribute

Returns the advance of this ShapeGraphicAttribute.

getAdvanceBetween(int, int) - Method in class java.awt.font.TextMeasurer

Returns the graphical width of a line beginning at start and including characters up to limit.

getAfterIndex(int, int) - Method in class java.awt.TextComponent.AccessibleAWTTextComponent

Returns the String after a given index.

getAfterIndex(int, int) - Method in interface javax.accessibility.AccessibleText

Returns the String after a given index.
getAfterIndex(int, int) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton
 Returns the String after a given index.
getAfterIndex(int, int) - Method in class javax.swing.JLabel.AccessibleJLabel
 Returns the String after a given index.
getAfterIndex(int, int) - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent
 Returns the String after a given index.
getAlgorithm() - Method in class java.security.KeyFactory
 Gets the name of the algorithm associated with this KeyFactory.
getAlgorithm() - Method in class java.security.KeyPairGenerator
 Returns the standard name of the algorithm for this key pair generator.
getAlgorithm() - Method in interface java.security.Key
 Returns the standard algorithm name for this key.
getAlgorithm() - Method in class java.security.AlgorithmParameters
 Returns the name of the algorithm associated with this parameter object.
getAlgorithm() - Method in class java.security.AlgorithmParameterGenerator
 Returns the standard name of the algorithm this parameter generator is associated with.
getAlgorithm() - Method in class java.security.SignedObject
 Retrieves the name of the signature algorithm.
getAlgorithm() - Method in class java.security.MessageDigest
 Returns a string that identifies the algorithm, independent of implementation details.
getAlgorithm() - Method in class java.security.Signature
 Returns the name of the algorithm for this signature object.
getAlgorithmProperty(String, String) - Static method in class java.security.Security
Deprecated. This method used to return the value of a proprietary property in the master file of the "SUN" Cryptographic Service Provider in order to determine how to parse algorithm-specific parameters. Use the new provider-based and algorithm-independent AlgorithmParameters and KeyFactory engine classes (introduced in the Java 2 platform) instead.
getAlignedSizeRequirements(SizeRequirements[]) - Static method in class javax.swing.SizeRequirements
 Determines the total space necessary to align a set of components.
getAlignment() - Method in class java.awt.Label
 Gets the current alignment of this label.
getAlignment() - Method in class java.awt.FlowLayout
 Gets the alignment for this layout.
getAlignment() - Method in class java.awt.font.GraphicAttribute
 Returns the alignment of this GraphicAttribute.
getAlignment() - Method in class javax.swing.text.TabStop

getAlignment(AttributeSet) - Static method in class javax.swing.text.StyleConstants
 Gets the alignment setting.
getAlignment(int) - Method in class javax.swing.text.View
 Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.GlyphView
 Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.BoxView
 Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.ParagraphView

Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.ComponentView
 Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.IconView
 Determines the desired alignment for this view along an axis.
getAlignment(int) - Method in class javax.swing.text.html.BlockView
 Gets the alignment.
getAlignment(int) - Method in class javax.swing.text.html.ListView
 Calculates the desired shape of the list.
getAlignmentX() - Method in class java.awt.Component
 Returns the alignment along the x axis.
getAlignmentX() - Method in class java.awt.Container
 Returns the alignment along the x axis.
getAlignmentX() - Method in class javax.swing.JComponent
 Overrides Container.getAlignmentX to return the vertical alignment.
getAlignmentY() - Method in class java.awt.Component
 Returns the alignment along the y axis.
getAlignmentY() - Method in class java.awt.Container
 Returns the alignment along the y axis.
getAlignmentY() - Method in class javax.swing.JComponent
 Overrides Container.getAlignmentY to return the horizontal alignment.
getAll() - Method in class javax.naming.Reference
 Retrieves an enumeration of the addresses in this reference.
getAll() - Method in interface javax.naming.Name
 Retrieves the components of this name as an enumeration of strings.
getAll() - Method in class javax.naming.CompoundName
 Retrieves the components of this compound name as an enumeration of strings.
getAll() - Method in class javax.naming.CompositeName
 Retrieves the components of this composite name as an enumeration of strings.
getAll() - Method in class javax.naming.directory.BasicAttribute
 Retrieves an enumeration of this attribute's values.
getAll() - Method in interface javax.naming.directory.Attributes
 Retrieves an enumeration of the attributes in the attribute set.
getAll() - Method in interface javax.naming.directory.Attribute
 Retrieves an enumeration of the attribute's values.
getAll() - Method in class javax.naming.directory.BasicAttributes

getAllAttributeKeys() - Method in interface java.text.AttributedCharacterIterator
 Returns the keys of all attributes defined on the iterator's text range.
getAllAttributeKeys() - Static method in class javax.swing.text.html.HTML
 This is the set of html attributes recognized.
getAllAttributeKeys() - Static method in class javax.swing.text.html.CSS
 Return the set of all possible CSS attribute keys.
getAllByName(String) - Static method in class java.net.InetAddress
 Determines all the IP addresses of a host, given the host's name.
getAllFonts() - Method in class java.awt.GraphicsEnvironment
 Returns an array containing a one-point size instance of all fonts available in this `GraphicsEnvironment`.

getAllFrames() - Method in class javax.swing.JDesktopPane

Returns all JInternalFrames currently displayed in the desktop.

getAllFramesInLayer(int) - Method in class javax.swing.JDesktopPane

Returns all JInternalFrames currently displayed in the specified layer of the desktop.

getAllowsChildren() - Method in class javax.swing.text.AbstractDocument.AbstractElement

Returns true if the receiver allows children.

getAllowsChildren() - Method in class javax.swing.text.AbstractDocument.BranchElement

Returns true if the receiver allows children.

getAllowsChildren() - Method in class javax.swing.text.AbstractDocument.LeafElement

Returns true if the receiver allows children.

getAllowsChildren() - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns true if this node is allowed to have children.

getAllowsChildren() - Method in interface javax.swing.tree.TreeNode

Returns true if the receiver allows children.

getAllowUserInteraction() - Method in class java.net.URLConnection

Returns the value of the allowUserInteraction field for this object.

getAllTags() - Static method in class javax.swing.text.html.HTML

This is the set of actual html tags that are known about the the default html reader.

getAlpha() - Method in class java.awt.Color

Returns the alpha component in the range 0-255.

getAlpha() - Method in class java.awt.AlphaComposite

Returns the alpha value of thisAlphaComposite.

getAlpha(int) - Method in class java.awt.image.ColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(int) - Method in class java.awt.image.ComponentColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(int) - Method in class java.awt.image.DirectColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(int) - Method in class java.awt.image.IndexColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(Object) - Method in class java.awt.image.ColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(Object) - Method in class java.awt.image.ComponentColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlpha(Object) - Method in class java.awt.image.DirectColorModel

Returns the alpha component for the specified pixel, scaled from 0 to 255.

getAlphaMask() - Method in class java.awt.image.DirectColorModel

Returns the mask indicating which bits in an int pixel representation contain the alpha component.

getAlphaRaster() - Method in class java.awt.image.BufferedImage

Returns a WritableRaster representing the alpha channel for BufferedImage objects with ColorModel objects that support a separate spatial alpha channel, such as ComponentColorModel and DirectColorModel.

getAlphaRaster(WritableRaster) - Method in class java.awt.image.ColorModel

Returns a Raster representing the alpha channel of an image, extracted from the input Raster, provided that pixel values of this ColorModel represent color and alpha information as separate spatial bands (e.g.

getAlphaRaster(WritableRaster) - Method in class java.awt.image.PackedColorModel

Returns a WritableRaster representing the alpha channel of an image, extracted from the input

WritableRaster.

getAlphaRaster(WritableRaster) - Method in class java.awt.image.ComponentColorModel

Returns a Raster representing the alpha channel of an image, extracted from the input Raster.

getAlphas(byte[]) - Method in class java.awt.image.IndexColorModel

Copies the array of alpha transparency components into the specified array.

getAltName() - Method in class javax.naming.CannotProceedException

Retrieves the altName field of this exception.

getAltNameCtx() - Method in class javax.naming.CannotProceedException

Retrieves the altNameCtx field of this exception.

getAmountFull(Insets, int, int) - Method in class javax.swing.plaf.basic.BasicProgressBarUI

This determines the amount of the progress bar that should be filled based on the percent done gathered from the model.

getAmPmStrings() - Method in class java.text.DateFormatSymbols

Gets ampm strings.

getAncestor() - Method in class javax.swing.event.AncestorEvent

Returns the ancestor that the event actually occurred on.

getAncestorNamed(String, Component) - Static method in class javax.swing.SwingUtilities

Convenience method for searching above comp in the component hierarchy and returns the first object of name it finds.

getAncestorOfClass(Class, Component) - Static method in class javax.swing.SwingUtilities

Convenience method for searching above comp in the component hierarchy and returns the first object of class c it finds.

getAncestorParent() - Method in class javax.swing.event.AncestorEvent

Returns the parent of the ancestor the event actually occurred on.

getAnchorRect() - Method in class java.awt.TexturePaint

Returns a copy of the anchor rectangle which positions and sizes the textured image.

getAnchorSelectionIndex() - Method in class javax.swing.DefaultListSelectionModel

getAnchorSelectionIndex() - Method in class javax.swing.JList

Returns the first index argument from the most recent addSelectionModel or setSelectionInterval call.

getAnchorSelectionIndex() - Method in interface javax.swing.ListSelectionModel

Return the first index argument from the most recent call to setSelectionInterval(), addSelectionInterval() or removeSelectionInterval().

getAnchorSelectionPath() - Method in class javax.swing.JTree

Returns the path identified as the anchor.

getAngleExtent() - Method in class java.awt.geom.Arc2D

Returns the angular extent of the arc.

getAngleExtent() - Method in class java.awt.geom.Arc2D.Float

Returns the angular extent of the arc.

getAngleExtent() - Method in class java.awt.geom.Arc2D.Double

Returns the angular extent of the arc.

getAngleStart() - Method in class java.awt.geom.Arc2D

Returns the starting angle of the arc.

getAngleStart() - Method in class java.awt.geom.Arc2D.Float

Returns the starting angle of the arc.

getAngleStart() - Method in class java.awt.geom.Arc2D.Double

Returns the starting angle of the arc.

getApplet(String) - Method in interface java.applet.AppletContext

Finds and returns the applet in the document represented by this applet context with the given name.

getAppletContext() - Method in class java.applet.Applet

Determines this applet's context, which allows the applet to query and affect the environment in which it runs.

getAppletContext() - Method in interface java.applet.AppletStub

Gets a handler to the applet's context.

getAppletInfo() - Method in class java.applet.Applet

Returns information about this applet.

getApplets() - Method in interface java.applet.AppletContext

Finds all the applets in the document represented by this applet context.

getApproveButton(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getApproveButton(JFileChooser) - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getApproveButtonMnemonic() - Method in class javax.swing.JFileChooser

Returns the approve button's mnemonic.

getApproveButtonMnemonic(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getApproveButtonText() - Method in class javax.swing.JFileChooser

Returns the text used in the ApproveButton in the FileChooserUI.

getApproveButtonText(JFileChooser) - Method in class javax.swing.plaf.FileChooserUI

getApproveButtonText(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getApproveButtonText(JFileChooser) - Method in class javax.swing.plaf.multi.MultiFileChooserUI

Call getApproveButtonText on each UI handled by this MultiUI.

getApproveButtonToolTipText() - Method in class javax.swing.JFileChooser

Returns the tooltip text used in the ApproveButton.

getApproveButtonToolTipText(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getApproveSelectionAction() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getArcHeight() - Method in class java.awt.geom.RoundRectangle2D

Gets the height of the arc that rounds off the corners.

getArcHeight() - Method in class java.awt.geom.RoundRectangle2D.Float

Returns the height of the arc that rounds off the corners.

getArcHeight() - Method in class java.awt.geom.RoundRectangle2D.Double

Returns the height of the arc that rounds off the corners.

getArcType() - Method in class java.awt.geom.Arc2D

Returns the arc closure type of the arc: OPEN, CHORD, or PIE.

getArcWidth() - Method in class java.awt.geom.RoundRectangle2D

Gets the width of the arc that rounds off the corners.

getArcWidth() - Method in class java.awt.geom.RoundRectangle2D.Float

Returns the width of the arc that rounds off the corners.

getArcWidth() - Method in class java.awt.geom.RoundRectangle2D.Double

Returns the width of the arc that rounds off the corners.

getAreaOfInterest() - Method in class java.awt.image.renderable.RenderContext

Gets the area of interest currently contained in the RenderContext.

getArray() - Method in interface java.sql.Array

Retrieves the contents of the SQL ARRAY value designated by this Array object in the form of an array in the Java programming language.

getArray() - Method in class javax.swing.text.DefaultStyledDocument.ElementSpec

Gets the array of characters.

getArray(int) - Method in interface java.sql.CallableStatement

Gets the value of a JDBC ARRAY parameter as an Array object in the Java programming language.

getArray(int) - Method in interface java.sql.ResultSet

Returns the value of the designated column in the current row of this ResultSet object as an Array object in the Java programming language.

getArray(long, int) - Method in interface java.sql.Array

Returns an array containing a slice of the SQL ARRAY value designated by this Array object, beginning with the specified index and containing up to count successive elements of the SQL array.

getArray(long, int, Map) - Method in interface java.sql.Array

Returns an array containing a slice of the SQL array object designated by this Array object, beginning with the specified index and containing up to count successive elements of the SQL array.

getArray(Map) - Method in interface java.sql.Array

Retrieves the contents of the SQL array designated by this Array object.

getArray(String) - Method in interface java.sql.ResultSet

Returns the value of the designated column in the current row of this ResultSet object as an Array object in the Java programming language.

getArrayLength() - Method in class javax.swing.text.GapContent

Get the length of the allocated array.

getAscent() - Method in class java.awt.FontMetrics

Determines the *font ascent* of the Font described by this FontMetrics object.

getAscent() - Method in class java.awt.font.TextLayout

Returns the ascent of this TextLayout.

getAscent() - Method in class java.awt.font.GraphicAttribute

Returns the ascent of this GraphicAttribute.

getAscent() - Method in class java.awt.font.ImageGraphicAttribute

Returns the ascent of this ImageGraphicAttribute.

getAscent() - Method in class java.awt.font.LineMetrics

Returns the ascent of the text.

getAscent() - Method in class java.awt.font.ShapeGraphicAttribute

Returns the ascent of this ShapeGraphicAttribute.

getAscent(GlyphView) - Method in class javax.swing.text.GlyphView.GlyphPainter

getAsciiStream() - Method in interface java.sql.Clob

Gets the CLOB value designated by this Clob object as a stream of Ascii bytes.

getAsciiStream(int) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a stream of ASCII characters.

getAsciiStream(String) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a stream of ASCII characters.

getAsText() - Method in interface java.beans.PropertyEditor

Gets the property value as text.

getAsText() - Method in class java.beans.PropertyEditorSupport

Gets the property value as a string suitable for presentation to a human to edit.

getAsynchronousLoadPriority() - Method in class javax.swing.text.AbstractDocument

Get the asynchronous loading priority.

getAtIndex(int, int) - Method in class java.awt.TextComponent.AccessibleAWTTextComponent

Returns the String at a given index.

getAtIndex(int, int) - Method in interface javax.accessibility.AccessibleText

Returns the String at a given index.

getAtIndex(int, int) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton

Returns the String at a given index.

getAtIndex(int, int) - Method in class javax.swing.JLabel.AccessibleJLabel

Returns the String at a given index.

getAtIndex(int, int) - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent

Returns the String at a given index.

getAttribute() - Method in class javax.naming.directory.ModificationItem

Retrieves the attribute associated with this modification item.

getAttribute(AttributedCharacterIterator.Attribute) - Method in interface java.text.AttributedCharacterIterator

Returns the value of the named attribute for the current character.

getAttribute(Object) - Method in class javax.swing.text.SimpleAttributeSet

Gets the value of an attribute.

getAttribute(Object) - Method in class javax.swing.text.StyleContext.SmallAttributeSet

Gets the value of an attribute.

getAttribute(Object) - Method in class javax.swing.text.StyleContext.NamedStyle

Gets the value of an attribute.

getAttribute(Object) - Method in class javax.swing.text.AbstractDocument.AbstractElement

Gets the value of an attribute.

getAttribute(Object) - Method in interface javax.swing.text.AttributeSet

Fetches the value of the given attribute.

getAttribute(String) - Static method in class javax.swing.text.html.CSS

Translate a string to a CSS.Attribute object.

getAttribute(String) - Method in class javax.swing.text.html.parser.Element

Get an attribute by name.

getAttributeByValue(String) - Method in class javax.swing.text.html.parser.Element

Get an attribute by value.

getAttributeContext() - Method in class javax.swing.text.AbstractDocument

Fetches the context for managing attributes.

getAttributeCount() - Method in class javax.swing.text.SimpleAttributeSet

Gets a count of the number of attributes.

getAttributeCount() - Method in class javax.swing.text.StyleContext.SmallAttributeSet

Gets the number of attributes that are defined.

getAttributeCount() - Method in class javax.swing.text.StyleContext.NamedStyle

Gets the number of attributes that are defined.

getAttributeCount() - Method in class javax.swing.text.AbstractDocument.AbstractElement

Gets the number of attributes that are defined.

getAttributeCount() - Method in interface javax.swing.text.AttributeSet

Returns the number of attributes contained in this set.

[getAttributeDefinition\(\)](#) - Method in class javax.naming.directory.[BasicAttribute](#)
Retrieves this attribute's schema definition.

[getAttributeDefinition\(\)](#) - Method in interface javax.naming.directory.[Attribute](#)
Retrieves the attribute's schema definition.

[getAttributeKey\(String\)](#) - Static method in class javax.swing.text.html.[HTML](#)
Fetch an attribute constant for a well-known attribute name (i.e.

[getAttributeNames\(\)](#) - Method in class javax.swing.text.[SimpleAttributeSet](#)
Gets the names of the attributes in the set.

[getAttributeNames\(\)](#) - Method in class javax.swing.text.[StyleContext.SmallAttributeSet](#)
Gets the names of all attributes.

[getAttributeNames\(\)](#) - Method in class javax.swing.text.[StyleContext.NamedStyle](#)
Gets the names of all attributes.

[getAttributeNames\(\)](#) - Method in class javax.swing.text.[AbstractDocument.AbstractElement](#)
Gets the names of all attributes.

[getAttributeNames\(\)](#) - Method in interface javax.swing.text.[AttributeSet](#)
Returns an enumeration over the names of the attributes in the set.

[getAttributes\(\)](#) - Method in class java.awt.[Font](#)
Returns a map of font attributes available in this Font.

[getAttributes\(\)](#) - Method in class java.net.[JarURLConnection](#)
Return the Attributes object for this connection if the URL for it points to a JAR file entry, null otherwise.

[getAttributes\(\)](#) - Method in interface java.sql.[Struct](#)
Produces the ordered values of the attributes of the SQL structure type that this Struct object represents.

[getAttributes\(\)](#) - Method in interface java.text.[AttributedCharacterIterator](#)
Returns a map with the attributes defined on the current character.

[getAttributes\(\)](#) - Method in class java.util.jar.[JarEntry](#)
Returns the Manifest Attributes for this entry, or null if none.

[getAttributes\(\)](#) - Method in class javax.naming.directory.[SearchResult](#)
Retrieves the attributes in this search result.

[getAttributes\(\)](#) - Method in class javax.naming.spi.[DirStateFactory.Result](#)
Retrieves the attributes to be bound.

[getAttributes\(\)](#) - Method in class javax.swing.text.[View](#)
Fetches the attributes to use when rendering.

[getAttributes\(\)](#) - Method in interface javax.swing.text.[Element](#)
Fetches the collection of attributes this element contains.

[getAttributes\(\)](#) - Method in class javax.swing.text.[AbstractDocument.AbstractElement](#)
Gets the attributes for the element.

[getAttributes\(\)](#) - Method in class javax.swing.text.[DefaultStyledDocument.ElementSpec](#)
Gets the element attributes.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.[Option](#)
Fetch the attributes associated with this option.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.[ParagraphView](#)
Fetches the attributes to use when rendering.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.[BlockView](#)
Fetches the attributes to use when rendering.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.[InlineView](#)

Fetches the attributes to use when rendering.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.[HTMLDocument.Iterator](#)

Fetch the attributes for this tag.

[getAttributes\(\)](#) - Method in class javax.swing.text.html.parser.[Parser](#)

[getAttributes\(\)](#) - Method in class javax.swing.text.html.parser.[Element](#)

Get the attributes.

[getAttributes\(Map\)](#) - Method in interface java.sql.[Struct](#)

Produces the ordered values of the attributes of the SQL structure type that this Struct object represents.

[getAttributes\(Name\)](#) - Method in interface javax.naming.directory.[DirContext](#)

Retrieves all of the attributes associated with a named object.

[getAttributes\(Name\)](#) - Method in class javax.naming.directory.[InitialDirContext](#)

[getAttributes\(Name, String\[\]\)](#) - Method in interface javax.naming.directory.[DirContext](#)

Retrieves selected attributes associated with a named object.

[getAttributes\(Name, String\[\]\)](#) - Method in class javax.naming.directory.[InitialDirContext](#)

[getAttributes\(String\)](#) - Method in class java.util.jar.[Manifest](#)

Returns the Attributes for the specified entry name.

[getAttributes\(String\)](#) - Method in interface javax.naming.directory.[DirContext](#)

Retrieves all of the attributes associated with a named object.

[getAttributes\(String\)](#) - Method in class javax.naming.directory.[InitialDirContext](#)

[getAttributes\(String, String\[\]\)](#) - Method in interface javax.naming.directory.[DirContext](#)

Retrieves selected attributes associated with a named object.

[getAttributes\(String, String\[\]\)](#) - Method in class javax.naming.directory.[InitialDirContext](#)

[getAttributeSyntaxDefinition\(\)](#) - Method in class javax.naming.directory.[BasicAttribute](#)

Retrieves the syntax definition associated with this attribute.

[getAttributeSyntaxDefinition\(\)](#) - Method in interface javax.naming.directory.[Attribute](#)

Retrieves the syntax definition associated with the attribute.

[getAudioClip\(URL\)](#) - Method in interface java.applet.[AppletContext](#)

Creates an audio clip.

[getAudioClip\(URL\)](#) - Method in class java.applet.[Applet](#)

Returns the AudioClip object specified by the URL argument.

[getAudioClip\(URL, String\)](#) - Method in class java.applet.[Applet](#)

Returns the AudioClip object specified by the URL and name arguments.

[getAudioFileFormat\(File\)](#) - Static method in class javax.sound.sampled.[AudioSystem](#)

Obtains the audio file format of the specified File.

[getAudioFileFormat\(File\)](#) - Method in class javax.sound.sampled.spi.[AudioFileReader](#)

Obtains the audio file format of the File provided.

[getAudioFileFormat\(InputStream\)](#) - Static method in class javax.sound.sampled.[AudioSystem](#)

Obtains the audio file format of the provided input stream.

[getAudioFileFormat\(InputStream\)](#) - Method in class javax.sound.sampled.spi.[AudioFileReader](#)

Obtains the audio file format of the input stream provided.

[getAudioFormat\(URL\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains the audio file format of the specified URL.

[getAudioFormat\(URL\)](#) - Method in class `javax.sound.sampled.spi.AudioFileReader`
 Obtains the audio file format of the URL provided.

[getAudioFileTypes\(\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains the file types for which file writing support is provided by the system.

[getAudioFileTypes\(\)](#) - Method in class `javax.sound.sampled.spi.AudioFileWriter`
 Obtains the file types for which file writing support is provided by this audio file writer.

[getAudioFileTypes\(AudioInputStream\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains the file types that the system can write from the audio input stream specified.

[getAudioFileTypes\(AudioInputStream\)](#) - Method in class `javax.sound.sampled.spi.AudioFileWriter`
 Obtains the file types that this audio file writer can write from the audio input stream specified.

[getAudioInputStream\(AudioFormat.Encoding, AudioInputStream\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains an audio input stream of the indicated encoding, by converting the provided audio input stream.

[getAudioInputStream\(AudioFormat.Encoding, AudioInputStream\)](#) - Method in class `javax.sound.sampled.spi.FormatConversionProvider`
 Obtains an audio input stream with the specified encoding from the given audio input stream.

[getAudioInputStream\(AudioFormat, AudioInputStream\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains an audio input stream of the indicated format, by converting the provided audio input stream.

[getAudioInputStream\(AudioFormat, AudioInputStream\)](#) - Method in class `javax.sound.sampled.spi.FormatConversionProvider`
 Obtains an audio input stream with the specified format from the given audio input stream.

[getAudioInputStream\(File\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains an audio input stream from the provided File.

[getAudioInputStream\(File\)](#) - Method in class `javax.sound.sampled.spi.AudioFileReader`
 Obtains an audio input stream from the File provided.

[getAudioInputStream\(InputStream\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains an audio input stream from the provided input stream.

[getAudioInputStream\(InputStream\)](#) - Method in class `javax.sound.sampled.spi.AudioFileReader`
 Obtains an audio input stream from the input stream provided.

[getAudioInputStream\(URL\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
 Obtains an audio input stream from the URL provided.

[getAudioInputStream\(URL\)](#) - Method in class `javax.sound.sampled.spi.AudioFileReader`
 Obtains an audio input stream from the URL provided.

[getAuthority\(\)](#) - Method in class `java.net.URL`
 Returns the authority part of this URL.

[getAutoCommit\(\)](#) - Method in interface `java.sql.Connection`
 Gets the current auto-commit state.

[getAutoCreateColumnsFromModel\(\)](#) - Method in class `javax.swing.JTable`
 Determines whether the table will create default columns from the model.

[getAutoDelay\(\)](#) - Method in class `java.awt.Robot`
 Returns the number of milliseconds this Robot sleeps after generating an event.

[getAutoResizeMode\(\)](#) - Method in class `javax.swing.JTable`
 Returns the auto resize mode of the table.

[getAutoscrollInsets\(\)](#) - Method in interface `java.awt.dnd.Autoscroll`

This method returns the Insets describing the autoscrolling region or border relative to the geometry of the implementing Component.

getAutoscrolls() - Method in class javax.swing.JComponent

Returns *true* if this component automatically scrolls its contents when dragged (when contained in a component that supports scrolling, like JViewport).

getAuxiliaryLookAndFeels() - Static method in class javax.swing.UIManager

Return the list of auxiliary look and feels (can be null).

getAvailableAttributes() - Method in class java.awt.Font

Returns the keys of all the attributes supported by this Font.

getAvailableFontFamilyNames() - Method in class java.awt.GraphicsEnvironment

Returns an array containing the names of all font families available in this GraphicsEnvironment.

getAvailableFontFamilyNames(Locale) - Method in class java.awt.GraphicsEnvironment

Returns an array containing the localized names of all font families available in this GraphicsEnvironment.

getAvailableIDs() - Static method in class java.util.TimeZone

Gets all the available IDs supported.

getAvailableIDs(int) - Static method in class java.util.TimeZone

Gets the available IDs according to the given time zone offset.

getAvailableInstruments() - Method in interface javax.sound.midi.Synthesizer

Obtains a list of instruments that come with the synthesizer.

getAvailableLocales() - Method in interface java.awt.im.spi.InputMethodDescriptor

Returns the locales supported by the corresponding input method.

getAvailableLocales() - Static method in class java.text.NumberFormat

Get the set of Locales for which NumberFormats are installed

getAvailableLocales() - Static method in class java.text.Collator

Get the set of Locales for which Collators are installed.

getAvailableLocales() - Static method in class java.text.DateFormat

Gets the set of locales for which DateFormats are installed.

getAvailableLocales() - Static method in class java.text.BreakIterator

Get the set of Locales for which BreakIterators are installed

getAvailableLocales() - Static method in class java.util.Calendar

Gets the list of locales for which Calendars are installed.

getAvailableLocales() - Static method in class java.util.Locale

Returns a list of all installed locales.

getAvailableSize(Dimension, Insets) - Method in class

javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager

Returns the available width based on the container size and Insets.

getAxis() - Method in class javax.swing.text.BoxView

Fetch the axis property.

getBackground() - Method in class java.awt.Component

Gets the background color of this component.

getBackground() - Method in class java.awt.Component.AccessibleAWTComponent

Get the background color of this object.

getBackground() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Get the background color of this object.

getBackground() - Method in class java.awt.Graphics2D

Returns the background color used for clearing a region.

getBackground() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Get the background color of this object.

getBackground() - Method in class java.awt.TextComponent

Gets the background color of this text component.

getBackground() - Method in interface javax.accessibility.AccessibleComponent

Gets the background color of this object.

getBackground() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getBackground() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

Get the background color of this object.

getBackground() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Gets the background color of this object.

getBackground() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getBackground() - Method in class javax.swing.text.GlyphView

Fetch the background color to use to render the glyphs.

getBackground() - Method in class javax.swing.text.LabelView

Fetch the background color to use to render the glyphs.

getBackground(AttributeSet) - Method in class javax.swing.text.StyleContext

Takes a set of attributes and turn it into a background color specification.

getBackground(AttributeSet) - Static method in class javax.swing.text.StyleConstants

Gets the background color setting from the attribute list.

getBackground(AttributeSet) - Method in interface javax.swing.text.StyledDocument

Takes a set of attributes and turn it into a background color specification.

getBackground(AttributeSet) - Method in class javax.swing.text.DefaultStyledDocument

Gets the background color from an attribute set.

getBackground(AttributeSet) - Method in class javax.swing.text.html.StyleSheet

Takes a set of attributes and turn it into a background color specification.

getBackgroundAt(int) - Method in class javax.swing.JTabbedPane

Returns the tab background color at index.

getBackgroundNonSelectionColor() - Method in class javax.swing.tree.DefaultTreeCellRenderer

Returns the background color to be used for non selected nodes.

getBackgroundSelectionColor() - Method in class javax.swing.tree.DefaultTreeCellRenderer

Returns the color to use for the background if node is selected.

getBandOffsets() - Method in class java.awt.image.ComponentSampleModel

Returns the band offset for all bands.

getBank() - Method in class javax.sound.midi.Patch

Returns the number of the bank that contains the instrument whose location this Patch specifies.

getBankData() - Method in class java.awt.image.DataBufferUShort

Returns the data arrays for all banks.

getBankData() - Method in class java.awt.image.DataBufferByte

Returns the data arrays for all banks.

getBankData() - Method in class java.awt.image.DataBufferInt

Returns the data arrays for all banks.

getBankData() - Method in class java.awt.image.DataBufferShort

Returns the data arrays for all banks.

getBankIndices() - Method in class java.awt.image.ComponentSampleModel

Returns the bank indices for all bands.

getBase() - Method in class javax.swing.text.html.StyleSheet

Returns the base.

getBase() - Method in class javax.swing.text.html.HTMLDocument

Gets the location to resolve relative URLs against.

getBaseline() - Method in class java.awt.font.TextLayout

Returns the baseline for this TextLayout.

getBaselineFor(char) - Method in class java.awt.Font

Returns the baseline appropriate for displaying this character.

getBaselineIndex() - Method in class java.awt.font.LineMetrics

Returns the baseline index of the text.

getBaselineOffsets() - Method in class java.awt.font.TextLayout

Returns the offsets array for the baselines used for this TextLayout.

getBaselineOffsets() - Method in class java.awt.font.LineMetrics

Returns the baseline offsets of the text, relative to the baseline of the text.

getBaseType() - Method in interface java.sql.Array

Returns the JDBC type of the elements in the array designated by this Array object.

getBaseTypeName() - Method in interface java.sql.Array

Returns the SQL type name of the elements in the array designated by this Array object.

getBaseTypeName() - Method in interface java.sql.Ref

Retrieves the fully-qualified SQL name of the SQL structured type that this Ref object references.

getBasicConstraints() - Method in class java.security.cert.X509Certificate

Gets the certificate constraints path length from the critical BasicConstraints extension, (OID = 2.5.29.19).

getBasicSplitPaneUI() - Method in class javax.swing.plaf.basic.BasicSplitPaneDivider

Returns the SplitPaneUI the receiver is currently in.

getBeanClass() - Method in class java.beans.BeanDescriptor

Gets the bean's Class object.

getBeanContext() - Method in class java.beans.beancontext.BeanContextEvent

Gets the BeanContext associated with this event.

getBeanContext() - Method in interface java.beans.beancontext.BeanContextChild

Gets the BeanContext associated with this BeanContextChild.

getBeanContext() - Method in class java.beans.beancontext.BeanContextChildSupport

Gets the nesting BeanContext for this BeanContextChildSupport.

getBeanContextChildPeer() - Method in class java.beans.beancontext.BeanContextChildSupport

Gets the BeanContextChild associated with this BeanContextChildSupport.

getBeanContextPeer() - Method in class java.beans.beancontext.BeanContextSupport

Gets the instance of BeanContext that this object is providing the implementation for.

getBeanContextProxy() - Method in interface java.beans.beancontext.BeanContextProxy

Gets the BeanContextChild (or subinterface) associated with this object.

getBeanContextServicesPeer() - Method in class java.beans.beancontext.BeanContextServicesSupport

Gets the BeanContextServices associated with this BeanContextServicesSupport.

getBeanDescriptor() - Method in interface java.beans.BeanInfo

Gets the beans BeanDescriptor.

getBeanDescriptor() - Method in class java.beans.SimpleBeanInfo

Deny knowledge about the class and customizer of the bean.

getBeanInfo(Class) - Static method in class java.beans.Introspector

Introspect on a Java bean and learn about all its properties, exposed methods, and events.

getBeanInfo(Class, Class) - Static method in class java.beans.Introspector

Introspect on a Java bean and learn all about its properties, exposed methods, below a given "stop" point.

getBeanInfo(Class, int) - Static method in class java.beans.Introspector

Introspect on a Java bean and learn about all its properties, exposed methods, and events, subject to some control flags.

getBeanInfoSearchPath() - Static method in class java.beans.Introspector

Gets the list of package names that will be used for finding BeanInfo classes.

getBeforeIndex(int, int) - Method in class java.awt.TextComponent.AccessibleAWTTextComponent

Returns the String before a given index.

getBeforeIndex(int, int) - Method in interface javax.accessibility.AccessibleText

Returns the String before a given index.

getBeforeIndex(int, int) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton

Returns the String before a given index.

getBeforeIndex(int, int) - Method in class javax.swing.JLabel.AccessibleJLabel

Returns the String before a given index.

getBeforeIndex(int, int) - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent

Returns the String before a given index.

getBeginIndex() - Method in interface java.text.CharacterIterator

Returns the start index of the text.

getBeginIndex() - Method in class java.text.StringCharacterIterator

Implements CharacterIterator.getBeginIndex() for String.

getBeginIndex() - Method in class java.text.FieldPosition

Retrieves the index of the first character in the requested field.

getBeginIndex() - Method in class javax.swing.text.Segment

Returns the start index of the text.

getBestConfiguration(GraphicsConfigTemplate) - Method in class java.awt.GraphicsDevice

Returns the "best" configuration possible that passes the criteria defined in the GraphicsConfigTemplate.

getBestConfiguration(GraphicsConfiguration[]) - Method in class java.awt.GraphicsConfigTemplate

Returns the "best" configuration possible that passes the criteria defined in the GraphicsConfigTemplate.

getBestCursorSize(int, int) - Method in class java.awt.Toolkit

Returns the supported cursor dimension which is closest to the desired sizes.

getBestRowIdentifier(String, String, String, int, boolean) - Method in interface java.sql.DatabaseMetaData

Gets a description of a table's optimal set of columns that uniquely identifies a row.

getBevelType() - Method in class javax.swing.border.BevelBorder

Returns the type of the bevel border.

getBidiLevel(AttributeSet) - Static method in class javax.swing.text.StyleConstants

Gets the BidiLevel setting.

getBidiRootElement() - Method in class javax.swing.text.AbstractDocument

Returns the root element of the bidirectional structure for this document.

getBigDecimal(int) - Method in interface java.sql.CallableStatement

Gets the value of a JDBC NUMERIC parameter as a java.math.BigDecimal object with as many digits to the right of the decimal point as the value contains.

getBigDecimal(int) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a

`java.math.BigDecimal` with full precision.

`getBigDecimal(int, int)` - Method in interface `java.sql.CallableStatement`
 Deprecated.

`getBigDecimal(int, int)` - Method in interface `java.sql.ResultSet`
 Deprecated.

`getBigDecimal(String)` - Method in interface `java.sql.ResultSet`
 Gets the value of the designated column in the current row of this `ResultSet` object as a `java.math.BigDecimal` with full precision.

`getBigDecimal(String, int)` - Method in interface `java.sql.ResultSet`
 Deprecated.

`getBinaryStream()` - Method in interface `java.sql.Blob`
 Retrieves the BLOB designated by this `Blob` instance as a stream.

`getBinaryStream(int)` - Method in interface `java.sql.ResultSet`
 Gets the value of a column in the current row as a stream of Gets the value of the designated column in the current row of this `ResultSet` object as a binary stream of uninterpreted bytes.

`getBinaryStream(String)` - Method in interface `java.sql.ResultSet`
 Gets the value of the designated column in the current row of this `ResultSet` object as a stream of uninterpreted bytes.

`getBitMasks()` - Method in class `java.awt.image.SinglePixelPackedSampleModel`
 Returns the bit masks for all bands.

`getBitOffset(int)` - Method in class `java.awt.image.MultiPixelPackedSampleModel`
 Returns the offset, in bits, into the data element in which it is stored for the xth pixel of a scanline.

`getBitOffsets()` - Method in class `java.awt.image.SinglePixelPackedSampleModel`
 Returns the bit offsets into the data array element representing a pixel for all bands.

`getBlack()` - Static method in class `javax.swing.plaf.metal.MetalLookAndFeel`

`getBlack()` - Method in class `javax.swing.plaf.metal.MetalTheme`

`getBlackBoxBounds(int, int)` - Method in class `java.awt.font.TextLayout`
 Returns the black box bounds of the characters in the specified range.

`getBlackLineBorderUIResource()` - Static method in class `javax.swing.plaf.BorderUIResource`

`getBlinkRate()` - Method in class `javax.swing.text.DefaultCaret`
 Gets the caret blink rate.

`getBlinkRate()` - Method in interface `javax.swing.text.Caret`
 Gets the blink rate of the caret.

`getBlob(int)` - Method in interface `java.sql.CallableStatement`
 Gets the value of a JDBC BLOB parameter as a `Blob` object in the Java programming language.

`getBlob(int)` - Method in interface `java.sql.ResultSet`
 Returns the value of the designated column in the current row of this `ResultSet` object as a `Blob` object in the Java programming language.

`getBlob(String)` - Method in interface `java.sql.ResultSet`
 Returns the value of the designated column in the current row of this `ResultSet` object as a `Blob` object in the Java programming language.

`getBlockIncrement()` - Method in class `java.awt.Scrollbar`
 Gets the block increment of this scroll bar.

`getBlockIncrement()` - Method in interface `java.awt.Adjustable`

Gets the block value increment for the adjustable object.

[getBlockIncrement\(\)](#) - Method in class `javax.swing.JScrollBar`
 For backwards compatibility with `java.awt.Scrollbar`.

[getBlockIncrement\(int\)](#) - Method in class `javax.swing.JScrollBar`
 Returns the amount to change the scrollbar's value by, given a block (usually "page") up/down request.

[getBlockIncrement\(int\)](#) - Method in class `javax.swing.JScrollPane.ScrollBar`
 Computes the block increment for scrolling if the viewport's view is a `Scrollable` object.

[getBlue\(\)](#) - Method in class `java.awt.Color`
 Returns the blue component in the range 0-255 in the default sRGB space.

[getBlue\(int\)](#) - Method in class `java.awt.image.ColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(int\)](#) - Method in class `java.awt.image.ComponentColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(int\)](#) - Method in class `java.awt.image.DirectColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(int\)](#) - Method in class `java.awt.image.IndexColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(Object\)](#) - Method in class `java.awt.image.ColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(Object\)](#) - Method in class `java.awt.image.ComponentColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlue\(Object\)](#) - Method in class `java.awt.image.DirectColorModel`
 Returns the blue color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getBlueMask\(\)](#) - Method in class `java.awt.image.DirectColorModel`
 Returns the mask indicating which bits in an `int` pixel representation contain the blue color component.

[getBlues\(byte\[\]\)](#) - Method in class `java.awt.image.IndexColorModel`
 Copies the array of blue color components into the specified array.

[getBoolean\(int\)](#) - Method in interface `java.sql.CallableStatement`
 Gets the value of a JDBC BIT parameter as a `boolean` in the Java programming language.

[getBoolean\(int\)](#) - Method in interface `java.sql.ResultSet`
 Gets the value of the designated column in the current row of this `ResultSet` object as a `boolean` in the Java programming language.

[getBoolean\(Object\)](#) - Method in class `java.lang.reflect.Field`
 Gets the value of a field as a `boolean` on the specified object.

[getBoolean\(Object, int\)](#) - Static method in class `java.lang.reflect.Array`
 Returns the value of the indexed component in the specified array object, as a `boolean`.

[getBoolean\(String\)](#) - Static method in class `java.lang.Boolean`
 Returns `true` if and only if the system property named by the argument exists and is equal to the string `"true"`.

[getBoolean\(String\)](#) - Method in interface `java.sql.ResultSet`

Gets the value of the designated column in the current row of this `ResultSet` object as a boolean in the Java programming language.

`getBorder()` - Method in class `javax.swing.JComponent`

Returns the border of this component or null if no border is currently set.

`getBorder()` - Method in class `javax.swing.border.TitledBorder`

Returns the border of the titled border.

`getBorder()` - Method in class `javax.swing.tree.DefaultTreeCellEditor.DefaultTextField`

Overrides `JComponent.getBorder` to returns the current border.

`getBorder()` - Method in class `javax.swing.plaf.basic.BasicSplitPaneDivider`

Returns the border of this component or null if no border is currently set.

`getBorder(Object)` - Method in class `javax.swing.UIManagerDefaults`

If the value of key is a `Border` return it, otherwise return null.

`getBorder(Object)` - Static method in class `javax.swing.UIManager`

Returns a border from the defaults table.

`getBorderColor()` - Method in class `javax.swing.plaf.basic.BasicToolBarUI.DragWindow`

`getBorderInsets()` - Method in class `javax.swing.border.EmptyBorder`

Returns the insets of the border.

`getBorderInsets()` - Method in class `javax.swing.border.MatteBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.AbstractBorder`

This default implementation returns the value of `getBorderMargins`.

`getBorderInsets(Component)` - Method in class `javax.swing.border.BevelBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.SoftBevelBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.EmptyBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.MatteBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.CompoundBorder`

Returns the insets of the composite border by adding the insets of the outside border to the insets of the inside border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.LineBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.TitledBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.border.EtchedBorder`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in interface `javax.swing.border.Border`

Returns the insets of the border.

`getBorderInsets(Component)` - Method in class `javax.swing.plaf.BorderUIResource`

`getBorderInsets(Component)` - Method in class `javax.swing.plaf.basic.BasicBorders.ButtonBorder`

`getBorderInsets(Component)` - Method in class `javax.swing.plaf.basic.BasicBorders.ToggleButtonBorder`

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.basic.[BasicBorders.RadioButtonBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.basic.[BasicBorders.MenuBarBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.basic.[BasicBorders.MarginBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.basic.[BasicBorders.FieldBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.basic.[BasicBorders.SplitPaneBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.Flush3DBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.ButtonBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.InternalFrameBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.PaletteBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.OptionDialogBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.MenuBarBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.MenuItemBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.PopupMenuBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.ToolBarBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.ScrollPaneBorder](#)

[getBorderInsets\(Component\)](#) - Method in class javax.swing.plaf.metal.[MetalBorders.TableHeaderBorder](#)

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[AbstractBorder](#)

Reinitializes the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[BevelBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[EmptyBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[MatteBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[CompoundBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[LineBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[TitledBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

[getBorderInsets\(Component, Insets\)](#) - Method in class javax.swing.border.[EtchedBorder](#)

Reinitialize the insets parameter with this Border's current Insets.

getBorderSelectionColor() - Method in class `javax.swing.tree.DefaultTreeCellRenderer`
Returns the color the border is drawn.

getBorderSelectionColor() - Method in class `javax.swing.tree.DefaultTreeCellEditor`
Returns the color the border is drawn.

getBorderTitle(Border) - Method in class `javax.swing.JComponent.AccessibleJComponent`
Recursively search through the border hierarchy (if it exists) for a `TitledBorder` with a non-null title.

getBottomComponent() - Method in class `javax.swing.JSplitPane`
Returns the component below, or to the right of the divider.

getBottomInset() - Method in class `javax.swing.text.CompositeView`
Gets the bottom inset.

getBottomInset() - Method in class `javax.swing.text.AsyncBoxView`
Get the bottom part of the margin around the view.

getBottomPanel() - Method in class `javax.swing.plaf.metal.MetalFileChooserUI`

getBoundActions() - Method in interface `javax.swing.text.Keymap`
Fetches all of the actions defined in this keymap.

getBoundedPosition(GlyphView, int, float, float) - Method in class `javax.swing.text.GlyphView.GlyphPainter`
Determines the model location that represents the maximum advance that fits within the given span.

getBoundingBox() - Method in class `java.awt.Polygon`
Deprecated. *As of JDK version 1.1, replaced by `getBounds()`.*

getBoundKeyStrokes() - Method in interface `javax.swing.text.Keymap`
Fetches all of the keystrokes in this map that are bound to some action.

getBounds() - Method in class `java.awt.Component`
Gets the bounds of this component in the form of a `Rectangle` object.

getBounds() - Method in class `java.awt.Component.AccessibleAWTComponent`
Gets the bounds of this object in the form of a `Rectangle` object.

getBounds() - Method in class `java.awt.Polygon`
Gets the bounding box of this `Polygon`.

getBounds() - Method in class `java.awt.GraphicsConfiguration`
Returns the bounds of the `GraphicsConfiguration` in the device coordinates.

getBounds() - Method in class `java.awt.MenuComponent.AccessibleAWTMenuComponent`
Gets the bounds of this object in the form of a `Rectangle` object.

getBounds() - Method in interface `java.awt.Shape`
Returns an integer `Rectangle` that completely encloses the `Shape`.

getBounds() - Method in class `java.awt.List.AccessibleAWTList.AccessibleAWTListChild`
Gets the bounds of this object in the form of a `Rectangle` object.

getBounds() - Method in class `java.awt.Rectangle`
Gets the bounding `Rectangle` of this `Rectangle`.

getBounds() - Method in class `java.awt.font.TextLayout`
Returns the bounds of this `TextLayout`.

getBounds() - Method in class `java.awt.font.GraphicAttribute`
Returns a `Rectangle2D` that encloses all of the bits drawn by this `GraphicAttribute` relative to the rendering position.

getBounds() - Method in class `java.awt.font.ImageGraphicAttribute`
Returns a `Rectangle2D` that encloses all of the bits rendered by this `ImageGraphicAttribute`, relative to the rendering position.

getBounds() - Method in class java.awt.font.ShapeGraphicAttribute

Returns a Rectangle2D that encloses all of the bits drawn by this ShapeGraphicAttribute relative to the rendering position.

getBounds() - Method in class java.awt.geom.RectangularShape

Returns the bounding box of the Shape.

getBounds() - Method in class java.awt.geom.Area

Returns a bounding Rectangle that completely encloses this Area.

getBounds() - Method in class java.awt.geom.Line2D

Returns the bounding box of this Line2D.

getBounds() - Method in class java.awt.geom.GeneralPath

Return the bounding box of the path.

getBounds() - Method in class java.awt.geom.QuadCurve2D

Returns the bounding box of this QuadCurve2D.

getBounds() - Method in class java.awt.geom.CubicCurve2D

Returns the bounding box of the shape.

getBounds() - Method in class java.awt.image.Raster

Returns the bounding Rectangle of this Raster.

getBounds() - Method in interface javax.accessibility.AccessibleComponent

Gets the bounds of this object in the form of a Rectangle object.

getBounds() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getBounds() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

getBounds() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

getBounds() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getBounds(Rectangle) - Method in class java.awt.Component

Store the bounds of this component into "return value" rv and return rv.

getBounds(Rectangle) - Method in class javax.swing.JComponent

Stores the bounds of this component into "return value" rv and returns rv.

getBounds(TreePath, Rectangle) - Method in class javax.swing.tree.AbstractLayoutCache

Returns a rectangle giving the bounds needed to draw path.

getBounds(TreePath, Rectangle) - Method in class javax.swing.tree.VariableHeightLayoutCache

Returns the Rectangle enclosing the label portion that the item identified by row will be drawn into.

getBounds(TreePath, Rectangle) - Method in class javax.swing.tree.FixedHeightLayoutCache

Returns a rectangle giving the bounds needed to draw path.

getBounds2D() - Method in class java.awt.Polygon

Returns the high precision bounding box of the Shape.

getBounds2D() - Method in interface java.awt.Shape

Returns a high precision and more accurate bounding box of the Shape than the getBounds method.

getBounds2D() - Method in class java.awt.Rectangle

Return the high precision bounding box of this rectangle.

getBounds2D() - Method in class java.awt.font.GlyphMetrics

Returns the black box bounds of the glyph.

getBounds2D() - Method in class java.awt.geom.Rectangle2D

Returns the high precision bounding box of this `Rectangle2D`.

`getBounds2D()` - Method in class `java.awt.geom.RoundRectangle2D.Float`

Returns the high precision bounding box of this `RoundRectangle2D`.

`getBounds2D()` - Method in class `java.awt.geom.RoundRectangle2D.Double`

Returns the high precision bounding box of this `RoundRectangle2D`.

`getBounds2D()` - Method in class `java.awt.geom.Area`

Returns a high precision bounding `Rectangle2D` that completely encloses this `Area`.

`getBounds2D()` - Method in class `java.awt.geom.Rectangle2D.Float`

Returns the high precision bounding box of this `Rectangle2D`.

`getBounds2D()` - Method in class `java.awt.geom.Rectangle2D.Double`

Returns the high precision bounding box of this `Rectangle2D`.

`getBounds2D()` - Method in class `java.awt.geom.Line2D.Float`

Returns the high-precision bounding box of this `Line2D`.

`getBounds2D()` - Method in class `java.awt.geom.Line2D.Double`

Returns the high-precision bounding box of this `Line2D`.

`getBounds2D()` - Method in class `java.awt.geom.Arc2D`

Returns the high-precision bounding box of the arc.

`getBounds2D()` - Method in class `java.awt.geom.Ellipse2D.Float`

Returns the high precision bounding box of this `Ellipse2D`.

`getBounds2D()` - Method in class `java.awt.geom.Ellipse2D.Double`

Returns the high precision bounding box of this `Ellipse2D`.

`getBounds2D()` - Method in class `java.awt.geom.GeneralPath`

Returns the bounding box of the path.

`getBounds2D()` - Method in class `java.awt.geom.QuadCurve2D.Float`

Returns the bounding box of this `QuadCurve2D`.

`getBounds2D()` - Method in class `java.awt.geom.QuadCurve2D.Double`

Returns the bounding box of this `QuadCurve2D`.

`getBounds2D()` - Method in class `java.awt.geom.CubicCurve2D.Float`

Returns the bounding box of the shape.

`getBounds2D()` - Method in class `java.awt.geom.CubicCurve2D.Double`

Returns the bounding box of the shape.

`getBounds2D(BufferedImage)` - Method in class `java.awt.image.LookupOp`

Returns the bounding box of the filtered destination image.

`getBounds2D(BufferedImage)` - Method in interface `java.awt.image.BufferedImageOp`

Returns the bounding box of the filtered destination image.

`getBounds2D(BufferedImage)` - Method in class `java.awt.image.ConvolveOp`

Returns the bounding box of the filtered destination image.

`getBounds2D(BufferedImage)` - Method in class `java.awt.image.AffineTransformOp`

Returns the bounding box of the transformed destination.

`getBounds2D(BufferedImage)` - Method in class `java.awt.image.ColorConvertOp`

Returns the bounding box of the destination, given this source.

`getBounds2D(BufferedImage)` - Method in class `java.awt.image.RescaleOp`

Returns the bounding box of the rescaled destination image.

`getBounds2D(ParameterBlock)` - Method in interface `java.awt.image.renderable.ContextualRenderedImageFactory`

Returns the bounding box for the output of the operation, performed on a given set of sources, in rendering-independent space.

getBounds2D(Raster) - Method in class java.awt.image.LookupOp
Returns the bounding box of the filtered destination Raster.

getBounds2D(Raster) - Method in class java.awt.image.ConvolveOp
Returns the bounding box of the filtered destination Raster.

getBounds2D(Raster) - Method in class java.awt.image.BandCombineOp
Returns the bounding box of the transformed destination.

getBounds2D(Raster) - Method in class java.awt.image.AffineTransformOp
Returns the bounding box of the transformed destination.

getBounds2D(Raster) - Method in interface java.awt.image.RasterOp
Returns the bounding box of the filtered destination Raster.

getBounds2D(Raster) - Method in class java.awt.image.ColorConvertOp
Returns the bounding box of the destination, given this source.

getBounds2D(Raster) - Method in class java.awt.image.RescaleOp
Returns the bounding box of the rescaled destination Raster.

getBoundsAt(int) - Method in class javax.swing.JTabbedPane
Returns the tab bounds at index.

getBoundsForIconOf(JInternalFrame) - Method in class javax.swing.DefaultDesktopManager
The iconifyFrame() code calls this to determine the proper bounds for the desktopIcon.

getBoxPainter(AttributeSet) - Method in class javax.swing.text.html.StyleSheet
Fetches the box formatter to use for the given set of CSS attributes.

getBreakLocation(Segment, FontMetrics, int, int, TabExpander, int) - Static method in class javax.swing.text.Utilities
Determine where to break the given text to fit within the the given span.

getBreakWeight(int, float) - Method in class javax.swing.text.ParagraphView
Gets the break weight for a given location.

getBreakWeight(int, float, float) - Method in class javax.swing.text.View
Determines how attractive a break opportunity in this view is.

getBreakWeight(int, float, float) - Method in class javax.swing.text.GlyphView
Determines how attractive a break opportunity in this view is.

getBreakWeight(int, float, float) - Method in class javax.swing.text.html.InlineView
Determines how attractive a break opportunity in this view is.

getBuffer() - Method in class java.io.StringWriter
Return the string buffer itself.

getBufferedImageOp() - Method in class java.awt.image.BufferedImageFilter
Returns the BufferedImageOp.

getBufferSize() - Method in interface javax.sound.sampled.DataLine
Obtains the maximum number of bytes of data that will fit in the data line's internal buffer.

getBundle(String) - Static method in class java.util.ResourceBundle
Get the appropriate ResourceBundle subclass.

getBundle(String, Locale) - Static method in class java.util.ResourceBundle
Get the appropriate ResourceBundle subclass.

getBundle(String, Locale, ClassLoader) - Static method in class java.util.ResourceBundle
Get the appropriate ResourceBundle subclass.

getButtonBorder() - Static method in class javax.swing.plaf.basic.BasicBorders

getButtonBorder() - Static method in class javax.swing.plaf.metal.MetalBorders
Returns a border instance for a JButton

getButtonCount() - Method in class javax.swing.ButtonGroup

Returns the number of buttons in the group.

getButtonPanel() - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getButtons() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI

Returns the buttons to display from the JOptionPane the receiver is providing the look and feel for.

getButtonWidth() - Method in class javax.swing.plaf.metal.MetalScrollbar

getByName(String) - Static method in class java.net.InetAddress

Determines the IP address of a host, given the host's name.

getBytes(int) - Method in interface java.sql.CallableStatement

Gets the value of a JDBC TINYINT parameter as a byte in the Java programming language.

getBytes(int) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a byte in the Java programming language.

getBytes(Object) - Method in class java.lang.reflect.Field

Gets the value of a field as a byte on the specified object.

getBytes(Object, int) - Static method in class java.lang.reflect.Array

Returns the value of the indexed component in the specified array object, as a byte.

getBytes(String) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a byte in the Java programming language.

getBytesLength() - Method in class javax.sound.sampled.AudioFileFormat

Obtains the size in bytes of the entire audio file (not just its audio data).

getBytesLength() - Method in class javax.sound.midi.MidiFileFormat

Obtains the length of the MIDI file, expressed in 8-bit bytes.

getBytesParameter(int) - Method in class java.awt.image.renderable.ParameterBlock

A convenience method to return a parameter as a byte.

getBytes() - Method in class java.lang.String

Convert this String into bytes according to the platform's default character encoding, storing the result into a new byte array.

getBytes(int) - Method in interface java.sql.CallableStatement

Gets the value of a JDBC BINARY or VARBINARY parameter as an array of byte values in the Java programming language.

getBytes(int) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this ResultSet object as a byte array in the Java programming language.

getBytes(int, int, byte[], int) - Method in class java.lang.String

Deprecated. *This method does not properly convert characters into bytes. As of JDK 1.1, the preferred way to do this is via the `getBytes(String enc)` method, which takes a character-encoding name, or the `getBytes()` method, which uses the platform's default encoding.*

getBytes(long, int) - Method in interface java.sql.Blob

Returns as an array of bytes, part or all of the BLOB value that this Blob object designates.

getBytes(String) - Method in class java.lang.String

Convert this String into bytes according to the specified character encoding, storing the result into a new byte array.

getBytes(String) - Method in interface java.sql.ResultSet

Gets the value of the designated column in the current row of this `ResultSet` object as a byte array in the Java programming language.

`getCachedIcon(File)` - Method in class `javax.swing.plaf.basic.BasicFileChooserUI`. `BasicFileView`

`getCalendar()` - Method in class `java.text.DateFormat`

Gets the calendar associated with this date/time formatter.

`getCancelSelectionAction()` - Method in class `javax.swing.plaf.basic.BasicFileChooserUI`

`getCanonicalFile()` - Method in class `java.io.File`

Returns the canonical form of this abstract pathname.

`getCanonicalPath()` - Method in class `java.io.File`

Returns the canonical pathname string of this abstract pathname.

`getCanWrapLines()` - Method in class `javax.swing.text.AbstractWriter`

Returns whether or not the lines can be wrapped.

`getCaret()` - Method in class `java.awt.event.InputMethodEvent`

Gets the caret.

`getCaret()` - Method in class `javax.swing.text.JTextComponent`

Fetches the caret that allows text-oriented navigation over the view.

`getCaretColor()` - Method in class `javax.swing.text.JTextComponent`

Fetches the current color used to render the caret.

`getCaretInfo(TextHitInfo)` - Method in class `java.awt.font.TextLayout`

Returns information about the caret corresponding to `hit`.

`getCaretInfo(TextHitInfo, Rectangle2D)` - Method in class `java.awt.font.TextLayout`

Returns information about the caret corresponding to `hit`.

`getCaretPosition()` - Method in class `java.awt.TextComponent`

Gets the position of the text insertion caret for this text component.

`getCaretPosition()` - Method in class `java.awt.TextComponent.AccessibleAWTTextComponent`

Returns the zero-based offset of the caret.

`getCaretPosition()` - Method in interface `javax.accessibility.AccessibleText`

Returns the zero-based offset of the caret.

`getCaretPosition()` - Method in class `javax.swing.AbstractButton.AccessibleAbstractButton`

Return the zero-based offset of the caret.

`getCaretPosition()` - Method in class `javax.swing.JLabel.AccessibleJLabel`

Return the zero-based offset of the caret.

`getCaretPosition()` - Method in class `javax.swing.text.JTextComponent`

Returns the position of the text insertion caret for the text component.

`getCaretPosition()` - Method in class `javax.swing.text.JTextComponent.AccessibleJTextComponent`

Returns the zero-based offset of the caret.

`getCaretShape(TextHitInfo)` - Method in class `java.awt.font.TextLayout`

Returns a `Shape` representing the caret at the specified hit inside the natural bounds of this `TextLayout`.

`getCaretShape(TextHitInfo, Rectangle2D)` - Method in class `java.awt.font.TextLayout`

Returns a `Shape` representing the caret at the specified hit inside the specified bounds.

`getCaretShapes(int)` - Method in class `java.awt.font.TextLayout`

Returns two paths corresponding to the strong and weak caret.

`getCaretShapes(int, Rectangle2D)` - Method in class `java.awt.font.TextLayout`

Returns two paths corresponding to the strong and weak caret.

`getCaretShapes(int, Rectangle2D, TextLayout.CaretPolicy)` - Method in class `java.awt.font.TextLayout`

Returns two paths corresponding to the strong and weak caret.

[getCatalog\(\)](#) - Method in interface [java.sql.Connection](#)
Returns the Connection's current catalog name.

[getCatalogName\(int\)](#) - Method in interface [java.sql.ResultSetMetaData](#)
Gets the designated column's table's catalog name.

[getCatalogs\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
Gets the catalog names available in this database.

[getCatalogSeparator\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
What's the separator between catalog and table name?

[getCatalogTerm\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
What's the database vendor's preferred term for "catalog"?

[getCellBounds\(int, int\)](#) - Method in class [javax.swing.JList](#)
Returns the bounds of the specified range of items in [JList](#) coordinates.

[getCellBounds\(JList, int, int\)](#) - Method in class [javax.swing.plaf.ListUI](#)
Returns the bounds of the specified item in [JList](#) coordinates, null if index isn't valid.

[getCellBounds\(JList, int, int\)](#) - Method in class [javax.swing.plaf.basic.BasicListUI](#)

[getCellBounds\(JList, int, int\)](#) - Method in class [javax.swing.plaf.multi.MultiListUI](#)
Call [getCellBounds](#) on each UI handled by this [MultiUI](#).

[getCellEditor\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the editor used to edit entries in the tree.

[getCellEditor\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the cell editor.

[getCellEditor\(\)](#) - Method in class [javax.swing.table.TableColumn](#)
Returns the [TableCellEditor](#) used by the [JTable](#) to edit values for this column.

[getCellEditor\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)

[getCellEditor\(int, int\)](#) - Method in class [javax.swing.JTable](#)
Returns an appropriate editor for the cell specified by `row` and `column`.

[getCellEditorValue\(\)](#) - Method in interface [javax.swing.CellEditor](#)
Returns the value contained in the editor

[getCellEditorValue\(\)](#) - Method in class [javax.swing.DefaultCellEditor](#)

[getCellEditorValue\(\)](#) - Method in class [javax.swing.DefaultCellEditor.EditorDelegate](#)

[getCellEditorValue\(\)](#) - Method in class [javax.swing.tree.DefaultTreeCellEditor](#)
Returns the value currently being edited.

[getCellLength\(\)](#) - Method in class [javax.swing.plaf.basic.BasicProgressBarUI](#)
Returns the width (if `HORIZONTAL`) or height (if `VERTICAL`) of each of the individual cells/units to be rendered in the progress bar.

[getCellRect\(int, int, boolean\)](#) - Method in class [javax.swing.JTable](#)
Returns a rectangle for the cell that lies at the intersection of `row` and `column`.

[getCellRenderer\(\)](#) - Method in class [javax.swing.JList](#)
Returns the object that renders the list items.

[getCellRenderer\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the current [TreeCellRenderer](#) that is rendering each cell.

[getCellRenderer\(\)](#) - Method in class [javax.swing.table.TableColumn](#)

Returns the `TableCellRenderer` used by the `JTable` to draw values for this column.

`getCellRenderer()` - Method in class `javax.swing.plaf.basic.BasicTreeUI`
 Return current `CellRenderer`, which will either be the trees renderer, or default `CellRenderer`, which ever wasn't null.

`getCellRenderer(int, int)` - Method in class `javax.swing.JTable`
 Returns an appropriate renderer for the cell specified by this row and column.

`getCellSelectionEnabled()` - Method in class `javax.swing.JTable`
 Returns true if both row and column selection models are enabled.

`getCellSpacing()` - Method in class `javax.swing.plaf.basic.BasicProgressBarUI`
 Returns the spacing between each of the cells/units in the progress bar.

`getCentersChildren()` - Method in class `javax.swing.plaf.basic.BasicOptionPaneUI.ButtonAreaLayout`

`getCenterX()` - Method in class `java.awt.geom.RectangularShape`
 Returns the X coordinate of the center of the framing rectangle of the `Shape` in double precision.

`getCenterY()` - Method in class `java.awt.geom.RectangularShape`
 Returns the Y coordinate of the center of the framing rectangle of the `Shape` in double precision.

`getCertificate(String)` - Method in class `java.security.KeyStore`
 Returns the certificate associated with the given alias.

`getCertificateAlias(Certificate)` - Method in class `java.security.KeyStore`
 Returns the (alias) name of the first keystore entry whose certificate matches the given certificate.

`getCertificateChain(String)` - Method in class `java.security.KeyStore`
 Returns the certificate chain associated with the given alias.

`getCertificates()` - Method in class `java.net.JarURLConnection`
 Return the `Certificate` object for this connection if the URL for it points to a JAR file entry, null otherwise.

`getCertificates()` - Method in class `java.security.CodeSource`
 Returns the certificates associated with this `CodeSource`.

`getCertificates()` - Method in class `java.util.jar.JarEntry`
 Returns the `Certificate` objects for this entry, or null if none.

`getChange(Element)` - Method in interface `javax.swing.event.DocumentEvent`
 Gets the change information for the given element.

`getChange(Element)` - Method in class `javax.swing.text.AbstractDocument.DefaultDocumentEvent`
 Gets the changes for an element.

`getChanged()` - Method in class `java.awt.event.HierarchyEvent`
 Returns the `Component` at the top of the hierarchy which was changed.

`getChangedParent()` - Method in class `java.awt.event.HierarchyEvent`
 Returns the parent of the `Component` returned by `getChanged()`.

`getChangeFlags()` - Method in class `java.awt.event.HierarchyEvent`
 Returns a bitmask which indicates the type(s) of `HIERARCHY_CHANGED` events represented in this event object.

`getChangeInfo()` - Method in class `javax.naming.event.NamingEvent`
 Retrieves the change information for this event.

`getChangeToParentDirectoryAction()` - Method in class `javax.swing.plaf.basic.BasicFileChooserUI`

`getChannel()` - Method in class `javax.sound.midi.ShortMessage`
 Obtains the MIDI channel associated with this event.

`getChannelPressure()` - Method in interface `javax.sound.midi.MidiChannel`

Obtains the channel's keyboard pressure.

getChannels() - Method in class `javax.sound.sampled.AudioFormat`
Obtains the number of channels.

getChannels() - Method in interface `javax.sound.midi.Synthesizer`
Obtains the set of MIDI channels controlled by this synthesizer.

getChar(Object) - Method in class `java.lang.reflect.Field`
Gets the value of a field as a char on the specified object.

getChar(Object, int) - Static method in class `java.lang.reflect.Array`
Returns the value of the indexed component in the specified array object, as a char.

getCharacterAttribute(int) - Method in class `java.awt.TextComponent.AccessibleAWTTextComponent`
Returns the AttributeSet for a given character (at a given index).

getCharacterAttribute(int) - Method in interface `javax.accessibility.AccessibleText`
Returns the AttributeSet for a given character at a given index

getCharacterAttribute(int) - Method in class `javax.swing.AbstractButton.AccessibleAbstractButton`
Return the AttributeSet for a given character at a given index

getCharacterAttribute(int) - Method in class `javax.swing.JLabel.AccessibleJLabel`
Return the AttributeSet for a given character at a given index

getCharacterAttribute(int) - Method in class `javax.swing.text.JTextComponent.AccessibleJTextComponent`
Returns the AttributeSet for a given character (at a given index).

getCharacterAttributeRun() - Method in class `javax.swing.text.StyledEditorKit`
Fetches the element representing the current run of character attributes for the caret.

getCharacterAttributes() - Method in class `javax.swing.JTextPane`
Fetches the character attributes in effect at the current location of the caret, or null.

getCharacterBounds(int) - Method in class `java.awt.TextComponent.AccessibleAWTTextComponent`
Determines the bounding box of the character at the given index into the string.

getCharacterBounds(int) - Method in interface `javax.accessibility.AccessibleText`
Determines the bounding box of the character at the given index into the string.

getCharacterBounds(int) - Method in class `javax.swing.AbstractButton.AccessibleAbstractButton`
Determine the bounding box of the character at the given index into the string.

getCharacterBounds(int) - Method in class `javax.swing.JLabel.AccessibleJLabel`
Determine the bounding box of the character at the given index into the string.

getCharacterBounds(int) - Method in class `javax.swing.text.JTextComponent.AccessibleJTextComponent`
Determines the bounding box of the character at the given index into the string.

getCharacterCount() - Method in class `java.awt.font.TextLayout`
Returns the number of characters represented by this TextLayout.

getCharacterElement(int) - Method in interface `javax.swing.text.StyledDocument`
Gets the element that represents the character that is at the given offset within the document.

getCharacterElement(int) - Method in class `javax.swing.text.DefaultStyledDocument`
Gets a character element based on a position.

getCharacterInstance() - Static method in class `java.text.BreakIterator`
Create BreakIterator for character-breaks using default locale Returns an instance of a BreakIterator implementing character breaks.

getCharacterInstance(Locale) - Static method in class `java.text.BreakIterator`
Create BreakIterator for character-breaks using specified locale Returns an instance of a BreakIterator implementing character breaks.

getCharacterLevel(int) - Method in class `java.awt.font.TextLayout`
Returns the level of the character at index.

getCharacterStream() - Method in interface [java.sql.Clob](#)

Gets the CLOB value designated by this Clob object as a Unicode stream.

getCharacterStream(int) - Method in interface [java.sql.ResultSet](#)

Gets the value of the designated column in the current row of this ResultSet object as a [java.io.Reader](#) object.

getCharacterStream(String) - Method in interface [java.sql.ResultSet](#)

Gets the value of the designated column in the current row of this ResultSet object as a [java.io.Reader](#) object.

getCharCount() - Method in class [java.awt.TextComponent.AccessibleAWTTextComponent](#)

Returns the number of characters (valid indices)

getCharCount() - Method in interface [javax.accessibility.AccessibleText](#)

Returns the number of characters (valid indices)

getCharCount() - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)

Return the number of characters (valid indices)

getCharCount() - Method in class [javax.swing.JLabel.AccessibleJLabel](#)

Return the number of characters (valid indices)

getCharCount() - Method in class [javax.swing.text.JTextComponent.AccessibleJTextComponent](#)

Returns the number of characters (valid indices)

getCharIndex() - Method in class [java.awt.font.TextHitInfo](#)

Returns the index of the character hit.

getCharParameter(int) - Method in class [java.awt.image.renderable.ParameterBlock](#)

A convenience method to return a parameter as a char.

getChars(int, int, char[], int) - Method in class [java.lang.String](#)

Copies characters from this string into the destination character array.

getChars(int, int, char[], int) - Method in class [java.lang.StringBuffer](#)

Characters are copied from this string buffer into the destination character array *dst*.

getChars(int, int, Segment) - Method in interface [javax.swing.text.AbstractDocument.Content](#)

Gets a sequence of characters and copies them into a Segment.

getChars(int, int, Segment) - Method in class [javax.swing.text.StringContent](#)

Retrieves a portion of the content.

getChars(int, int, Segment) - Method in class [javax.swing.text.GapContent](#)

Retrieves a portion of the content.

getCharSetSpec() - Method in class [javax.swing.text.ChangedCharSetException](#)

getCheckboxGroup() - Method in class [java.awt.Checkbox](#)

Determines this check box's group.

getCheckBoxIcon() - Static method in class [javax.swing.plaf.basic.BasicIconFactory](#)

getCheckBoxIcon() - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

Returns a checkbox icon

getCheckBoxMenuItemIcon() - Static method in class [javax.swing.plaf.basic.BasicIconFactory](#)

getCheckBoxMenuItemIcon() - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

getChecksum() - Method in class [java.util.zip.CheckedInputStream](#)

Returns the Checksum for this input stream.

getChecksum() - Method in class [java.util.zip.CheckedOutputStream](#)

Returns the Checksum for this output stream.

[getChild\(\)](#) - Method in class java.awt.event.[ContainerEvent](#)
Returns the component that was affected by the event.

[getChild\(Object, int\)](#) - Method in interface javax.swing.tree.[TreeModel](#)
Returns the child of *parent* at index *index* in the parent's child array.

[getChild\(Object, int\)](#) - Method in class javax.swing.tree.[DefaultTreeModel](#)
Returns the child of *parent* at index *index* in the parent's child array.

[getChildAfter\(TreeNode\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the child in this node's child array that immediately follows aChild, which must be a child of this node.

[getChildAllocation\(int\)](#) - Method in class javax.swing.text.[AsyncBoxView.ChildLocator](#)
Fetch the allocation to use for a child view.

[getChildAllocation\(int, Shape\)](#) - Method in class javax.swing.text.[View](#)
Fetches the allocation for the given child view.

[getChildAllocation\(int, Shape\)](#) - Method in class javax.swing.text.[CompositeView](#)
Fetches the allocation for the given child view.

[getChildAllocation\(int, Shape\)](#) - Method in class javax.swing.text.[BoxView](#)
Fetches the allocation for the given child view.

[getChildAllocation\(int, Shape\)](#) - Method in class javax.swing.text.[AsyncBoxView](#)
Fetches the allocation for the given child view.

[getChildAllocation\(int, Shape\)](#) - Method in class javax.swing.text.[AsyncBoxView.ChildLocator](#)
Fetch the allocation to use for a child view.

[getChildAt\(int\)](#) - Method in class javax.swing.JTree.[DynamicUtilTreeNode](#)
Subclassed to load the children, if necessary.

[getChildAt\(int\)](#) - Method in class javax.swing.text.[AbstractDocument.AbstractElement](#)
Returns the child *TreeNode* at index *childIndex*.

[getChildAt\(int\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the child at the specified index in this node's child array.

[getChildAt\(int\)](#) - Method in interface javax.swing.tree.[TreeNode](#)
Returns the child *TreeNode* at index *childIndex*.

[getChildBeanContextChild\(Object\)](#) - Static method in class java.beans.beancontext.[BeanContextSupport](#)
Gets the *BeanContextChild* (if any) of the specified child

[getChildBeanContextMembershipListener\(Object\)](#) - Static method in class java.beans.beancontext.[BeanContextSupport](#)
Gets the *BeanContextMembershipListener* (if any) of the specified child

[getChildBeanContextServicesListener\(Object\)](#) - Static method in class java.beans.beancontext.[BeanContextServicesSupport](#)
Gets the *BeanContextServicesListener* (if any) of the specified child.

[getChildBefore\(TreeNode\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the child in this node's child array that immediately precedes aChild, which must be a child of this node.

[getChildCount\(\)](#) - Method in class javax.swing.JTree.[DynamicUtilTreeNode](#)
Returns the number of child nodes.

[getChildCount\(\)](#) - Method in class javax.swing.text.[AbstractDocument.AbstractElement](#)
Returns the number of children *TreeNodes* the receiver contains.

[getChildCount\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the number of children of this node.

getChildCount() - Method in interface javax.swing.tree.TreeNode
Returns the number of children TreeNodes the receiver contains.

getChildCount(Object) - Method in interface javax.swing.tree.TreeModel
Returns the number of children of *parent*.

getChildCount(Object) - Method in class javax.swing.tree.DefaultTreeModel
Returns the number of children of *parent*.

getChildIndices() - Method in class javax.swing.event.TreeModelEvent
Returns the values of the child indexes.

getChildPropertyChangeListener(Object) - Static method in class java.beans.beancontext.BeanContextSupport
Gets the PropertyChangeListener (if any) of the specified child

getChildren() - Method in class javax.swing.event.TreeModelEvent
Returns the objects that are children of the node identified by getPath at the locations specified by getChildIndices.

getChildrenAdded() - Method in interface javax.swing.event.DocumentEvent.ElementChange
Gets the child elements that were added to the given parent element.

getChildrenAdded() - Method in class javax.swing.text.AbstractDocument.ElementEdit
Gets a list of children that were added.

getChildrenRemoved() - Method in interface javax.swing.event.DocumentEvent.ElementChange
Gets the child elements that were removed from the given parent element.

getChildrenRemoved() - Method in class javax.swing.text.AbstractDocument.ElementEdit
Gets a list of children that were removed.

getChildSerializable(Object) - Static method in class java.beans.beancontext.BeanContextSupport
Gets the Serializable (if any) associated with the specified Child

getChildState(int) - Method in class javax.swing.text.AsyncBoxView
Fetch the object representing the layout state of of the child at the given index.

getChildVetoableChangeListener(Object) - Static method in class java.beans.beancontext.BeanContextSupport
Gets the VetoableChangeListener (if any) of the specified child

getChildView() - Method in class javax.swing.text.AsyncBoxView.ChildState
Fetch the child view this record represents

getChildVisibility(Object) - Static method in class java.beans.beancontext.BeanContextSupport
Gets the Component (if any) associated with the specified child.

getChoosableFileFilters() - Method in class javax.swing.JFileChooser
Gets the list of user choosable file filters.

getChooserPanels() - Method in class javax.swing.JColorChooser
Returns the specified color panels.

getClass() - Method in class java.lang.Object
Returns the runtime class of an object.

getClassAnnotation(Class) - Static method in class java.rmi.server.RMIClassLoader
Returns the class annotation (representing the location for a class) that RMI will use to annotate the call stream when marshalling objects of the given class.

getClassContext() - Method in class java.lang.SecurityManager
Returns the current execution stack as an array of classes.

getClasses() - Method in class java.lang.Class
Returns an array containing Class objects representing all the public classes and interfaces that are members of the class represented by this Class object.

getClassLoader() - Method in class java.lang.Class
Returns the class loader for the class.

[getClassLoader\(String\)](#) - Static method in class java.rmi.server.[RMIClassLoader](#)

Returns a class loader that loads classes from the given codebase URL path.

[getClassName\(\)](#) - Method in class java.rmi.activation.[ActivationGroupDesc](#)

Returns the group's class name (possibly null).

[getClassName\(\)](#) - Method in class java.rmi.activation.[ActivationDesc](#)

Returns the class name for the object specified by this descriptor.

[getClassName\(\)](#) - Method in class java.util.[MissingResourceException](#)

Gets parameter passed by constructor.

[getClassName\(\)](#) - Method in class javax.naming.[Reference](#)

Retrieves the class name of the object to which this reference refers.

[getClassName\(\)](#) - Method in class javax.naming.[NameClassPair](#)

Retrieves the class name of the object bound to the name of this binding.

[getClassName\(\)](#) - Method in class javax.naming.[Binding](#)

Retrieves the class name of the object bound to the name of this binding.

[getClassName\(\)](#) - Method in class javax.swing.[UIManager.LookAndFeelInfo](#)

Returns the name of the class that implements this look and feel.

[getClickCount\(\)](#) - Method in class java.awt.event.[MouseEvent](#)

Return the number of mouse clicks associated with this event.

[getClickCountToStart\(\)](#) - Method in class javax.swing.[DefaultCellEditor](#)

ClickCountToStart controls the number of clicks required to start editing.

[getClientHost\(\)](#) - Static method in class java.rmi.server.[RemoteServer](#)

Return the hostname of the current client.

[getClientHost\(\)](#) - Method in interface java.rmi.server.[ServerRef](#)

Returns the hostname of the current client.

[getClientProperty\(Object\)](#) - Method in class javax.swing.[JComponent](#)

Returns the value of the property with the specified key.

[getClip\(\)](#) - Method in class java.awt.[Graphics](#)

Gets the current clipping area.

[getClip\(\)](#) - Method in class javax.swing.[DebugGraphics](#)

Overrides [Graphics.getClip\(\)](#).

[getClipBounds\(\)](#) - Method in class java.awt.[Graphics](#)

Returns the bounding rectangle of the current clipping area.

[getClipBounds\(\)](#) - Method in class javax.swing.[DebugGraphics](#)

Overrides [Graphics.getClipBounds\(\)](#).

[getClipBounds\(Rectangle\)](#) - Method in class java.awt.[Graphics](#)

Returns the bounding rectangle of the current clipping area.

[getClipRect\(\)](#) - Method in class java.awt.[Graphics](#)

Deprecated. *As of JDK version 1.1, replaced by [getClipBounds\(\)](#).*

[getClob\(int\)](#) - Method in interface java.sql.[CallableStatement](#)

Gets the value of a JDBC CLOB parameter as a Clob object in the Java programming language.

[getClob\(int\)](#) - Method in interface java.sql.[ResultSet](#)

Returns the value of the designated column in the current row of this [ResultSet](#) object as a Clob object in the Java programming language.

[getClob\(String\)](#) - Method in interface java.sql.[ResultSet](#)

Returns the value of the designated column in the current row of this [ResultSet](#) object as a Clob object in the Java programming language.

[getClosedIcon\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellRenderer](#)

Returns the icon used to represent non-leaf nodes that are not expanded.
[getClosestPathForLocation\(int, int\)](#) - Method in class javax.swing.JTree
 Returns the path to the node that is closest to x,y.
[getClosestPathForLocation\(JTree, int, int\)](#) - Method in class javax.swing.plaf.TreeUI
 Returns the path to the node that is closest to x,y.
[getClosestPathForLocation\(JTree, int, int\)](#) - Method in class javax.swing.plaf.basic.BasicTreeUI
 Returns the path to the node that is closest to x,y.
[getClosestPathForLocation\(JTree, int, int\)](#) - Method in class javax.swing.plaf.multi.MultiTreeUI
 Call getClosestPathForLocation on each UI handled by this MultiUI.
[getClosestPositionTo\(int, Position.Bias, Shape, int, Position.Bias\[\], int, int\)](#) - Method in class javax.swing.text.ParagraphView
 Returns the closest model position to x.
[getClosestRowForLocation\(int, int\)](#) - Method in class javax.swing.JTree
 Returns the row to the node that is closest to x,y.
[getCodeBase\(\)](#) - Method in class java.applet.Applet
 Gets the base URL.
[getCodeBase\(\)](#) - Method in interface java.applet.AppletStub
 Gets the base URL.
[getCodebase\(Class\)](#) - Static method in class javax.rmi.CORBA.Util
 Returns the codebase, if any, for the given class.
[getCodebase\(Class\)](#) - Method in interface javax.rmi.CORBA.UtilDelegate
 Delegation call for Util.getCodebase(java.lang.Class).
[getCodeSource\(\)](#) - Method in class java.security.ProtectionDomain
 Returns the CodeSource of this domain.
[getCollapsedIcon\(\)](#) - Method in class javax.swing.plaf.basic.BasicTreeUI

[getCollationElementIterator\(CharacterIterator\)](#) - Method in class java.text.RuleBasedCollator
 Return a CollationElementIterator for the given String.
[getCollationElementIterator\(String\)](#) - Method in class java.text.RuleBasedCollator
 Return a CollationElementIterator for the given String.
[getCollationKey\(String\)](#) - Method in class java.text.Collator
 Transforms the String into a series of bits that can be compared bitwise to other CollationKeys.
[getCollationKey\(String\)](#) - Method in class java.text.RuleBasedCollator
 Transforms the string into a series of characters that can be compared with CollationKey.compareTo.
[getColor\(\)](#) - Method in class java.awt.Graphics
 Gets this graphics context's current color.
[getColor\(\)](#) - Method in class java.awt.PageAttributes
 Returns whether pages using these attributes will be rendered in color or monochrome.
[getColor\(\)](#) - Method in class javax.swing.JColorChooser
 Gets the current color value from the color chooser.
[getColor\(\)](#) - Method in class javax.swing.DebugGraphics
 Returns the Color used for text drawing operations.
[getColor\(\)](#) - Method in class javax.swing.text.DefaultHighlighter.DefaultHighlightPainter
 Returns the color of the highlight.
[getColor\(Object\)](#) - Method in class javax.swing.UIManager
 If the value of key is a Color return it, otherwise return null.
[getColor\(Object\)](#) - Static method in class javax.swing.UIManager

Returns a drawing color from the defaults table.

getColor(String) - Static method in class java.awt.Color
 Finds a color in the system properties.

getColor(String, Color) - Static method in class java.awt.Color
 Finds a color in the system properties.

getColor(String, int) - Static method in class java.awt.Color
 Finds a color in the system properties.

getColor1Q - Method in class java.awt.GradientPaint
 Returns the color C1 anchored by the point P1.

getColor2Q - Method in class java.awt.GradientPaint
 Returns the color C2 anchored by the point P2.

getColorComponents(ColorSpace, float[]) - Method in class java.awt.Color
 Returns a float array containing only the color components of the Color in the ColorSpace specified by the cspace parameter.

getColorComponents(float[]) - Method in class java.awt.Color
 Returns a float array containing only the color components of the Color, in the ColorSpace of the Color.

getColorForGap(int, int, int) - Method in class javax.swing.plaf.metal.MetalTabbedPaneUI

getColorFromModelQ - Method in class javax.swing.colorchooser.AbstractColorChooserPanel
 Returns the color that is currently selected.

getColorModelQ - Method in class java.awt.Component
 Gets the instance of ColorModel used to display the component on the output device.

getColorModelQ - Method in class java.awt.GraphicsConfiguration
 Returns the ColorModel associated with this GraphicsConfiguration.

getColorModelQ - Method in interface java.awt.PaintContext
 Returns the ColorModel of the output.

getColorModelQ - Method in class java.awt.Toolkit
 Determines the color model of this toolkit's screen.

getColorModelQ - Method in class java.awt.image.PixelGrabber
 Get the ColorModel for the pixels stored in the array.

getColorModelQ - Method in interface java.awt.image.RenderedImage
 Returns the ColorModel associated with this image.

getColorModelQ - Method in class java.awt.image.BufferedImage
 Returns the ColorModel.

getColorModel(int) - Method in class java.awt.GraphicsConfiguration
 Returns the ColorModel associated with this GraphicsConfiguration that supports the specified transparency.

getColorSelectionModelQ - Method in class javax.swing.colorchooser.AbstractColorChooserPanel
 Returns the model that the chooser panel is editing.

getColorSpaceQ - Method in class java.awt.Color
 Returns the ColorSpace of this Color.

getColorSpaceQ - Method in class java.awt.image.ColorModel
 Returns the ColorSpace associated with this ColorModel.

getColorSpaceTypeQ - Method in class java.awt.color.ICC_Profile
 Returns the color space type.

getColumnQ - Method in class javax.swing.event.TableModelEvent

Returns the column for the event.

[getColumn\(int\)](#) - Method in class javax.swing.table.[DefaultTableColumnModel](#)

Returns the TableColumn object for the column at columnIndex.

[getColumn\(int\)](#) - Method in interface javax.swing.table.[TableColumnModel](#)

Returns the TableColumn object for the column at columnIndex.

[getColumn\(Object\)](#) - Method in class javax.swing.[JTable](#)

Returns the TableColumn object for the column in the table whose identifier is equal to identifier, when compared using equals.

[getColumnClass\(int\)](#) - Method in class javax.swing.[JTable](#)

Returns the type of the column appearing in the view at column position column.

[getColumnClass\(int\)](#) - Method in class javax.swing.table.[AbstractTableModel](#)

Returns Object.class regardless of columnIndex.

[getColumnClass\(int\)](#) - Method in interface javax.swing.table.[TableModel](#)

Returns the most specific superclass for all the cell values in the column.

[getColumnClassName\(int\)](#) - Method in interface java.sql.[ResultSetMetaData](#)

Returns the fully-qualified name of the Java class whose instances are manufactured if the method ResultSet.getObject is called to retrieve a value from the column.

[getColumnCount\(\)](#) - Method in interface java.sql.[ResultSetMetaData](#)

Returns the number of columns in this ResultSet object.

[getColumnCount\(\)](#) - Method in class javax.swing.[JTable](#)

Returns the number of columns in the column model.

[getColumnCount\(\)](#) - Method in class javax.swing.table.[DefaultTableModel](#)

Returns the number of columns in this data table.

[getColumnCount\(\)](#) - Method in class javax.swing.table.[DefaultTableColumnModel](#)

Returns the number of columns in the tableColumns array.

[getColumnCount\(\)](#) - Method in interface javax.swing.table.[TableModel](#)

Returns the number of columns in the model.

[getColumnCount\(\)](#) - Method in interface javax.swing.table.[TableColumnModel](#)

Returns the number of columns in the model.

[getColumnCount\(\)](#) - Method in class javax.swing.text.[TableView.TableCell](#)

Deprecated. Gets the number of columns this cell spans (e.g.

[getColumnDisplaySize\(int\)](#) - Method in interface java.sql.[ResultSetMetaData](#)

Indicates the designated column's normal maximum width in characters.

[getColumnHeader\(\)](#) - Method in class javax.swing.[ScrollPaneLayout](#)

Returns the JViewport object that is the column header.

[getColumnHeader\(\)](#) - Method in class javax.swing.[JScrollPane](#)

Returns the column header.

[getColumnIndex\(Object\)](#) - Method in class javax.swing.table.[DefaultTableColumnModel](#)

Returns the index of the first column in the tableColumns array whose identifier is equal to identifier, when compared using equals.

[getColumnIndex\(Object\)](#) - Method in interface javax.swing.table.[TableColumnModel](#)

Returns the index of the first column in the table whose identifier is equal to identifier, when compared using equals.

[getColumnIndexAtX\(int\)](#) - Method in class javax.swing.table.[DefaultTableColumnModel](#)

Returns the index of the column that lies at position x, or -1 if no column covers this point.

[getColumnIndexAtX\(int\)](#) - Method in interface javax.swing.table.[TableColumnModel](#)

Returns the index of the column that lies on the horizontal point, xPosition; or -1 if it lies outside the

any of the column's bounds.

[getColumnLabel\(int\)](#) - Method in interface [java.sql.ResultSetMetaData](#)

Gets the designated column's suggested title for use in printouts and displays.

[getColumnMargin\(\)](#) - Method in class [javax.swing.table.DefaultTableColumnModel](#)

Returns the width margin for [TableColumn](#).

[getColumnMargin\(\)](#) - Method in interface [javax.swing.table.TableColumnModel](#)

Returns the width between the cells in each column.

[getColumnModel\(\)](#) - Method in class [javax.swing.JTable](#)

Returns the [TableColumnModel](#) that contains all column information of this table.

[getColumnModel\(\)](#) - Method in class [javax.swing.table.JTableHeader](#)

Returns the [TableColumnModel](#) that contains all column information of this table header.

[getColumnName\(int\)](#) - Method in interface [java.sql.ResultSetMetaData](#)

Get the designated column's name.

[getColumnName\(int\)](#) - Method in class [javax.swing.JTable](#)

Returns the name of the column appearing in the view at column position [column](#).

[getColumnName\(int\)](#) - Method in class [javax.swing.table.AbstractTableModel](#)

Returns a default name for the column using spreadsheet conventions: A, B, C, ...

[getColumnName\(int\)](#) - Method in class [javax.swing.table.DefaultTableModel](#)

Returns the column name.

[getColumnName\(int\)](#) - Method in interface [javax.swing.table.TableModel](#)

Returns the name of the column at [columnIndex](#).

[getColumnPrivileges\(String, String, String, String\)](#) - Method in interface [java.sql.DatabaseMetaData](#)

Gets a description of the access rights for a table's columns.

[getColumns\(\)](#) - Method in class [java.awt.GridLayout](#)

Gets the number of columns in this layout.

[getColumns\(\)](#) - Method in class [java.awt.TextField](#)

Gets the number of columns in this text field.

[getColumns\(\)](#) - Method in class [java.awt.TextArea](#)

Gets the number of columns in this text area.

[getColumns\(\)](#) - Method in class [javax.swing.JTextField](#)

Returns the number of columns in this [TextField](#).

[getColumns\(\)](#) - Method in class [javax.swing.JTextArea](#)

Returns the number of columns in the [TextArea](#).

[getColumns\(\)](#) - Method in class [javax.swing.table.DefaultTableColumnModel](#)

Returns an [Enumeration](#) of all the columns in the model.

[getColumns\(\)](#) - Method in interface [javax.swing.table.TableColumnModel](#)

Returns an [Enumeration](#) of all the columns in the model.

[getColumns\(String, String, String, String\)](#) - Method in interface [java.sql.DatabaseMetaData](#)

Gets a description of table columns available in the specified catalog.

[getColumnSelectionAllowed\(\)](#) - Method in class [javax.swing.JTable](#)

Returns true if columns can be selected.

[getColumnSelectionAllowed\(\)](#) - Method in class [javax.swing.table.DefaultTableColumnModel](#)

Returns true if column selection is allowed, otherwise false.

[getColumnSelectionAllowed\(\)](#) - Method in interface [javax.swing.table.TableColumnModel](#)

Returns true if columns may be selected.

[getColumnType\(int\)](#) - Method in interface [java.sql.ResultSetMetaData](#)

Retrieves the designated column's SQL type.

isSubscript(AttributeSet) - Static method in class javax.swing.text.StyleConstants

Checks whether the subscript attribute is set.

isSuperscript() - Method in class javax.swing.text.GlyphView

Determine if the glyphs should be rendered as subscript.

isSuperscript() - Method in class javax.swing.text.LabelView

Determine if the glyphs should be rendered as subscript.

isSuperscript(AttributeSet) - Static method in class javax.swing.text.StyleConstants

Checks whether the superscript attribute is set.

isSupportedLookAndFeel() - Method in class javax.swing.LookAndFeel

Return true if the underlying platform supports and or permits this look and feel.

isSupportedLookAndFeel() - Method in class javax.swing.plaf.metal.MetalLookAndFeel

isSupportedLookAndFeel() - Method in class javax.swing.plaf.multi.MultiLookAndFeel

isSynchronizationSupported(Line[], boolean) - Method in interface javax.sound.sampled.Mixer

Reports whether this mixer supports synchronization of the specified set of lines.

isSynchronized(int) - Static method in class java.lang.reflect.Modifier

Return true if the specified integer includes the synchronized modifier.

isTargetEncodingSupported(AudioFormat.Encoding) - Method in class javax.sound.sampled.spi.FormatConversionProvider

Indicates whether the format converter supports conversion to the specified target format encoding.

isTearOff() - Method in class java.awt.Menu

Indicates whether this menu is a tear-off menu.

isTearOff() - Method in class javax.swing.JMenu

Returns true if the menu can be torn off.

isTemporary() - Method in class java.awt.event.FocusEvent

Identifies the focus change event as temporary or permanent.

isText(Element) - Method in class javax.swing.text.html.MinimalHTMLWriter

Returns true if the element is a text element.

isTileWritable(int, int) - Method in class java.awt.image.BufferedImage

Returns whether or not a tile is currently checked out for writing.

isTileWritable(int, int) - Method in interface java.awt.image.WritableRenderedImage

Returns whether a tile is currently checked out for writing.

isTimeSet - Variable in class java.util.Calendar

True if then the value of time is valid.

isTitleCase(char) - Static method in class java.lang.Character

Determines if the specified character is a titlecase character.

isToggleEvent(MouseEvent) - Method in class javax.swing.plaf.basic.BasicTreeUI

Returning true indicates the row under the mouse should be toggled based on the event.

isToggleSelectionEvent(MouseEvent) - Method in class javax.swing.plaf.basic.BasicTreeUI

Returning true signifies a mouse event on the node should toggle the selection of only the row under mouse.

isTopLevelMenu() - Method in class javax.swing.JMenu

Returns true if the menu is a 'top-level menu', that is, if it is the direct child of a menubar.

isTransient(int) - Static method in class java.lang.reflect.Modifier

Return true if the specifier integer includes the transient modifier.

isTraversable(File) - Method in class javax.swing.JFileChooser

Returns true if the file (directory) can be visited.

isTraversable(File) - Method in class javax.swing.filechooser.FileView
Whether the directory is traversable or not.

isTraversable(File) - Method in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

IstringHelper - class org.omg.CosNaming.IstringHelper.

isUnderline() - Method in class javax.swing.text.GlyphView
Determine if the glyphs should be underlined.

isUnderline() - Method in class javax.swing.text.LabelView
Determine if the glyphs should be underlined.

isUnderline(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Checks whether the underline attribute is set.

isUnicast() - Method in class java.beans.EventSetDescriptor
Normally event sources are multicast.

isUnicodeIdentifierPart(char) - Static method in class java.lang.Character
Determines if the specified character may be part of a Unicode identifier as other than the first character.

isUnicodeIdentifierStart(char) - Static method in class java.lang.Character
Determines if the specified character is permissible as the first character in a Unicode identifier.

isUnique() - Static method in class java.rmi.dgc.VMID
Deprecated.

isUpperCase(char) - Static method in class java.lang.Character
Determines if the specified character is an uppercase character.

isValid() - Method in class java.awt.Component
Determines whether this component is valid.

isValid() - Method in class java.awt.image.IndexColorModel
Returns whether or not all of the pixels are valid.

isValid() - Method in class javax.accessibility.AccessibleHyperlink
Since the document a link is associated with may have changed, this method returns whether or not this Link is still valid (with respect to the document it references).

isValid() - Method in class javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.HTMLLink
Since the document a link is associated with may have changed, this method returns whether this Link is valid anymore (with respect to the document it references).

isValid() - Method in class javax.swing.text.html.HTMLDocument.Iterator
Indicates if the iterator is currently representing an occurrence of a tag.

isValid() - Method in class javax.swing.plaf.basic.BasicSplitPaneDivider.DragController
Returns true if the dragging session is valid.

isValid(int) - Method in class java.awt.image.IndexColorModel
Returns whether or not the pixel is valid.

isValidRoot() - Method in class javax.swing.JComponent
If this method returns true, revalidate() calls by descendants of this component will cause the entire tree beginning with this root to be validated.

isValidRoot() - Method in class javax.swing.JTextField
Calls to revalidate that come from within the textfield itself will be handled by validating the textfield, unless the receiver is contained within a JViewport, in which case this returns false.

isValidRoot() - Method in class javax.swing.JSplitPane

Returns true, so that calls to `revalidate` on any descendant of this `JScrollPane` will cause a request to be queued that will validate the `JScrollPane` and all its descendants.

`isValidRoot()` - Method in class `javax.swing.JScrollPane`

Calls `revalidate` on any descendant of this `JScrollPane`.

`isValidRoot()` - Method in class `javax.swing.JRootPane`

If a descendant of this `JRootPane` calls `revalidate`, validate from here on down.

`isVertical()` - Method in class `java.awt.font.TextLayout`

Returns true if this `TextLayout` is vertical.

`isViewSizeSet` - Variable in class `javax.swing.JViewport`

True when the viewport dimensions have been determined.

`isVisible()` - Method in class `java.awt.Component`

Determines whether this component should be visible when its parent is visible.

`isVisible()` - Method in class `java.awt.Component.AccessibleAWTComponent`

Determine if the object is visible.

`isVisible()` - Method in class `java.awt.MenuComponent.AccessibleAWTMenuComponent`

Determine if the object is visible.

`isVisible()` - Method in class `java.awt.List.AccessibleAWTList.AccessibleAWTListChild`

Determine if the object is visible.

`isVisible()` - Method in interface `javax.accessibility.AccessibleComponent`

Determines if the object is visible.

`isVisible()` - Method in class `javax.swing.JPopupMenu`

Returns true if the popup menu is visible (currently being displayed).

`isVisible()` - Method in class `javax.swing.JList.AccessibleJList.AccessibleJListChild`

`isVisible()` - Method in class `javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode`

`isVisible()` - Method in class `javax.swing.JTable.AccessibleJTable.AccessibleJTableCell`

Determines if this object is visible.

`isVisible()` - Method in class

`javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry`

`isVisible()` - Method in class `javax.swing.text.View`

Returns a boolean that indicates whether the view is visible or not.

`isVisible()` - Method in class `javax.swing.text.DefaultCaret`

Determines if the caret is currently visible.

`isVisible()` - Method in interface `javax.swing.text.Caret`

Determines if the caret is currently visible.

`isVisible()` - Method in class `javax.swing.text.html.ParagraphView`

Indicates whether or not this view should be displayed.

`isVisible()` - Method in interface `javax.swing.plaf.basic.ComboPopup`

Returns whether or not the popup is visible

`isVisible(TreePath)` - Method in class `javax.swing.JTree`

Returns true if the value identified by path is currently viewable, which means it is either the root or all of its parents are expanded.

`isVolatile(int)` - Static method in class `java.lang.reflect.Modifier`

Return true if the specified integer includes the `volatile` modifier.

`isWhitespace()` - Method in class `java.awt.font.GlyphMetrics`

Returns `true` if this is a whitespace glyph.

isWhitespace(char) - Static method in class `java.lang.Character`
 Determines if the specified character is white space according to Java.

isWritable(int) - Method in interface `java.sql.ResultSetMetaData`
 Indicates whether it is possible for a write on the designated column to succeed.

isZoneLoaded(View) - Method in class `javax.swing.text.ZoneView`
 Determine if a zone is in the loaded state.

ITALIAN - Static variable in class `java.util.Locale`
 Useful constant for language.

Italic - Static variable in class `javax.swing.text.StyleConstants`
 Name of the italic attribute.

Italic - Static variable in class `javax.swing.text.StyleConstants.CharacterConstants`
 Name of the italic attribute.

Italic - Static variable in class `javax.swing.text.StyleConstants.FontConstants`
 Name of the italic attribute.

ITALIC - Static variable in class `java.awt.Font`
 The italicized style constant.

ITALIC_ACTION - Static variable in class `javax.swing.text.html.HTMLEditorKit`
 The italic action identifier

ITALY - Static variable in class `java.awt.PageAttributes.MediaType`
 An alias for `ITALY_ENVELOPE`.

ITALY - Static variable in class `java.util.Locale`
 Useful constant for country.

ITALY_ENVELOPE - Static variable in class `java.awt.PageAttributes.MediaType`
 The `MediaType` instance for Italy Envelope, 110 x 230 mm.

ITEM_EVENT_MASK - Static variable in class `java.awt.AWTEvent`
 The event mask for selecting item events.

ITEM_FIRST - Static variable in class `java.awt.event.ItemEvent`
 The first number in the range of ids used for item events.

ITEM_LAST - Static variable in class `java.awt.event.ItemEvent`
 The last number in the range of ids used for item events.

ITEM_STATE_CHANGED - Static variable in class `java.awt.event.ItemEvent`
 This event id indicates that an item's state changed.

item(int) - Method in class `org.omg.CORBA.ContextList`
 Returns the `String` object at the given index.

item(int) - Method in class `org.omg.CORBA.ExceptionList`
 Returns the `TypeCode` object at the given index.

item(int) - Method in class `org.omg.CORBA.NVList`
 Retrieves the `NamedValue` object at the given index.

ItemEvent - class `java.awt.event.ItemEvent`.
 A semantic event which indicates that an item was selected or deselected.

ItemEvent(ItemSelectable, int, Object, int) - Constructor for class `java.awt.event.ItemEvent`
 Constructs an `ItemEvent` object.

itemListener - Variable in class `javax.swing.AbstractButton`
 The button model's `ItemListener`.

itemListener - Variable in class `javax.swing.plaf.basic.BasicComboPopup`

itemListener - Variable in class javax.swing.plaf.basic.BasicComboBoxUI

ItemListener - interface java.awt.event.ItemListener.

The listener interface for receiving item events.

ItemSelectable - interface java.awt.ItemSelectable.

The interface for objects which contain a set of items for which zero or more can be selected.

itemStateChanged(ItemEvent) - Method in class java.awt.Checkbox.AccessibleAWTCheckbox

Fire accessible property change events when the state of the toggle button changes.

itemStateChanged(ItemEvent) - Method in class java.awt.AWTEventMulticaster

Handles the itemStateChanged event by invoking the itemStateChanged methods on listener-a and listener-b.

itemStateChanged(ItemEvent) - Method in class java.awt.List.AccessibleAWTList

itemStateChanged(ItemEvent) - Method in interface java.awt.event.ItemListener

Invoked when an item has been selected or deselected.

itemStateChanged(ItemEvent) - Method in class javax.swing.JToggleButton.AccessibleJToggleButton

Fire accessible property change events when the state of the toggle button changes.

itemStateChanged(ItemEvent) - Method in class javax.swing.DefaultCellEditor.EditorDelegate

itemStateChanged(ItemEvent) - Method in class javax.swing.plaf.basic.BasicComboPopup.ItemHandler

itemStateChanged(ItemEvent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI.ItemHandler

Iterator - interface java.util.Iterator.

An iterator over a collection.

iterator() - Method in class java.awt.dnd.DragGestureEvent

This method returns an Iterator for the events comprising the gesture.

iterator() - Method in class java.beans.beancontext.BeanContextMembershipEvent

Gets the array of children affected by this event.

iterator() - Method in class java.beans.beancontext.BeanContextSupport

Gets all JavaBean or BeanContext instances currently nested in this BeanContext.

iterator() - Method in class java.util.AbstractCollection

Returns an iterator over the elements contained in this collection.

iterator() - Method in class java.util.TreeSet

Returns an iterator over the elements in this set.

iterator() - Method in class java.util.AbstractList

Returns an iterator over the elements in this list in proper sequence.

iterator() - Method in interface java.util.Collection

Returns an iterator over the elements in this collection.

iterator() - Method in class java.util.AbstractSequentialList

Returns an iterator over the elements in this list (in proper sequence).

iterator() - Method in class java.util.HashSet

Returns an iterator over the elements in this set.

iterator() - Method in interface java.util.Set

Returns an iterator over the elements in this set.

iterator() - Method in interface java.util.List

Returns an iterator over the elements in this list in proper sequence.

[Submit a bug or feature](#)

For further API reference and developer documentation, see [Java 2 SDK SE Developer Documentation](#). That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Java, Java 2D, and JDBC are trademarks or registered trademarks of Sun Microsystems, Inc. in the US and other countries.
Copyright 1993-2001 Sun Microsystems, Inc. 901 San Antonio Road
Palo Alto, California, 94303, U.S.A. All Rights Reserved.

O

OBJ_ADAPTER - exception org.omg.CORBA.OBJ_ADAPTER.

The CORBA OBJ_ADAPTER exception, which is thrown by the object adapter on the server to indicate some error.

OBJ_ADAPTER() - Constructor for class org.omg.CORBA.OBJ_ADAPTER

Constructs an OBJ_ADAPTER exception with a default minor code of 0, a completion state of CompletionStatus.COMPLETED_NO, and a null description.

OBJ_ADAPTER(int, CompletionStatus) - Constructor for class org.omg.CORBA.OBJ_ADAPTER

Constructs an OBJ_ADAPTER exception with the specified minor code and completion status.

OBJ_ADAPTER(String) - Constructor for class org.omg.CORBA.OBJ_ADAPTER

Constructs an OBJ_ADAPTER exception with the specified description, a minor code of 0, and a completion state of COMPLETED_NO.

OBJ_ADAPTER(String, int, CompletionStatus) - Constructor for class org.omg.CORBA.OBJ_ADAPTER

Constructs an OBJ_ADAPTER exception with the specified description message, minor code, and completion status.

object - Variable in class javax.swing.undo.StateEdit

The object being edited

Object - class java.lang.Object.

Class Object is the root of the class hierarchy.

Object - interface org.omg.CORBA.Object.

The definition for a CORBA object reference.

OBJECT - Static variable in class javax.swing.text.html.HTML.Tag

OBJECT_ADDED - Static variable in class javax.naming.event.NamingEvent

Naming event type for indicating that a new object has been added.

OBJECT_CHANGED - Static variable in class javax.naming.event.NamingEvent

Naming event type for indicating that an object has been changed.

OBJECT_FACTORIES - Static variable in interface javax.naming.Context

Constant that holds the name of the environment property for specifying the list of object factories to use.

OBJECT_NOT_EXIST - exception org.omg.CORBA.OBJECT_NOT_EXIST.

The CORBA OBJECT_NOT_EXIST exception, which is usually thrown from the server to indicate that the target object does not exist.

OBJECT_NOT_EXIST() - Constructor for class org.omg.CORBA.OBJECT_NOT_EXIST

Constructs an OBJECT_NOT_EXIST exception with a default minor code of 0, a completion state of CompletionStatus.COMPLETED_NO, and a null description.

OBJECT_NOT_EXIST(int, CompletionStatus) - Constructor for class org.omg.CORBA.OBJECT_NOT_EXIST

Constructs an OBJECT_NOT_EXIST exception with the specified minor code and completion status.

OBJECT_NOT_EXIST(String) - Constructor for class org.omg.CORBA.OBJECT_NOT_EXIST

Constructs an `OBJECT_NOT_EXIST` exception with the specified description, a minor code of 0, and a completion state of `COMPLETED_NO`.

`OBJECT_NOT_EXIST(String, int, CompletionStatus)` - Constructor for class `org.omg.CORBA.OBJECT_NOT_EXIST`

Constructs an `OBJECT_NOT_EXIST` exception with the specified description message, minor code, and completion status.

`OBJECT_REMOVED` - Static variable in class `javax.naming.event.NamingEvent`
Naming event type for indicating that an object has been removed.

`OBJECT_RENAMED` - Static variable in class `javax.naming.event.NamingEvent`
Naming event type for indicating that an object has been renamed.

`OBJECT_SCOPE` - Static variable in class `javax.naming.directory.SearchControls`
Search the named object.

`OBJECT_SCOPE` - Static variable in interface `javax.naming.event.EventContext`
Constant for expressing interest in events concerning the object named by the target.

`object_to_string(Object)` - Method in class `org.omg.CORBA.ORB`
Converts the given CORBA object reference to a string.

`Object()` - Constructor for class `java.lang.Object`

`objectAdded(NamingEvent)` - Method in interface `javax.naming.event.NamespaceChangeListener`
Called when an object has been added.

`objectChanged(NamingEvent)` - Method in interface `javax.naming.event.ObjectChangeListener`
Called when an object has been changed.

`ObjectChangeListener` - interface `javax.naming.event.ObjectChangeListener`.
Specifies the method that a listener of a `NamingEvent` with event type of `OBJECT_CHANGED` must implement.

`ObjectFactory` - interface `javax.naming.spi.ObjectFactory`.
This interface represents a factory for creating an object.

`ObjectFactoryBuilder` - interface `javax.naming.spi.ObjectFactoryBuilder`.
This interface represents a builder that creates object factories.

`ObjectHelper` - class `org.omg.CORBA.ObjectHelper`.

`ObjectHelper()` - Constructor for class `org.omg.CORBA.ObjectHelper`

`ObjectHolder` - class `org.omg.CORBA.ObjectHolder`.
A Holder class for a CORBA object reference (a value of type `org.omg.CORBA.Object`).

`ObjectHolder()` - Constructor for class `org.omg.CORBA.ObjectHolder`
Constructs a new `ObjectHolder` object with its `value` field initialized to `null`.

`ObjectHolder(Object)` - Constructor for class `org.omg.CORBA.ObjectHolder`
Constructs a new `ObjectHolder` object with its `value` field initialized to the given `Object`.

`ObjectImpl` - class `org.omg.CORBA.portable.ObjectImpl`.
The common base class for all stub classes; provides default implementations of the `org.omg.CORBA.Object` methods.

`ObjectImpl` - class `org.omg.CORBA_2_3.portable.ObjectImpl`.
`ObjectImpl` class is the base class for all stubs.

`ObjectImpl()` - Constructor for class `org.omg.CORBA.portable.ObjectImpl`

`ObjectImpl()` - Constructor for class `org.omg.CORBA_2_3.portable.ObjectImpl`

ObjectInput - interface java.io.ObjectInput.

ObjectInput extends the DataInput interface to include the reading of objects.

ObjectInputStream - class java.io.ObjectInputStream.

An ObjectInputStream deserializes primitive data and objects previously written using an ObjectOutputStream.

ObjectInputStream.GetField - class java.io.ObjectInputStream.GetField.

Provide access to the persistent fields read from the input stream.

ObjectInputStream.GetField() - Constructor for class java.io.ObjectInputStream.GetField

ObjectInputStream() - Constructor for class java.io.ObjectInputStream

Provide a way for subclasses that are completely reimplementing ObjectInputStream to not have to allocate private data just used by this implementation of ObjectInputStream.

ObjectInputStream(InputStream) - Constructor for class java.io.ObjectInputStream

Create an ObjectInputStream that reads from the specified InputStream.

ObjectInputValidation - interface java.io.ObjectInputValidation.

Callback interface to allow validation of objects within a graph.

ObjectOutput - interface java.io.ObjectOutput.

ObjectOutput extends the DataOutput interface to include writing of objects.

ObjectOutputStream - class java.io.ObjectOutputStream.

An ObjectOutputStream writes primitive data types and graphs of Java objects to an OutputStream.

ObjectOutputStream.PutField - class java.io.ObjectOutputStream.PutField.

Provide programmatic access to the persistent fields to be written to ObjectOutput.

ObjectOutputStream.PutField() - Constructor for class java.io.ObjectOutputStream.PutField

ObjectOutputStream() - Constructor for class java.io.ObjectOutputStream

Provide a way for subclasses that are completely reimplementing ObjectOutputStream to not have to allocate private data just used by this implementation of ObjectOutputStream.

ObjectOutputStream(OutputStream) - Constructor for class java.io.ObjectOutputStream

Creates an ObjectOutputStream that writes to the specified OutputStream.

objectRemoved(NamingEvent) - Method in interface javax.naming.event.NamespaceChangeListener

Called when an object has been removed.

objectRenamed(NamingEvent) - Method in interface javax.naming.event.NamespaceChangeListener

Called when an object has been renamed.

ObjectStreamClass - class java.io.ObjectStreamClass.

Serialization's descriptor for classes.

ObjectStreamConstants - interface java.io.ObjectStreamConstants.

Constants written into the Object Serialization Stream.

ObjectStreamException - exception java.io.ObjectStreamException.

Superclass of all exceptions specific to Object Stream classes.

ObjectStreamException() - Constructor for class java.io.ObjectStreamException

Create an ObjectStreamException.

ObjectStreamException(String) - Constructor for class java.io.ObjectStreamException

Create an ObjectStreamException with the specified argument.

ObjectStreamField - class java.io.ObjectStreamField.

A description of a Serializable field from a Serializable class.

ObjectStreamField(String, Class) - Constructor for class java.io.ObjectStreamField

Create a Serializable field with the specified type.

ObjectView - class javax.swing.text.html.ObjectView.

Component decorator that implements the view interface for <object> elements.

ObjectView(Element) - Constructor for class javax.swing.text.html.ObjectView

Creates a new ObjectView object.

ObjID - class java.rmi.server.ObjID.

An Obj ID is used to identify remote objects uniquely in a VM over time.

ObjID() - Constructor for class java.rmi.server.ObjID

Generates a unique object identifier.

ObjID(int) - Constructor for class java.rmi.server.ObjID

Generates a "well-known" object ID.

Observable - class java.util.Observable.

This class represents an observable object, or "data" in the model-view paradigm.

Observable() - Constructor for class java.util.Observable

Construct an Observable with zero Observers.

Observer - interface java.util.Observer.

A class can implement the Observer interface when it wants to be informed of changes in observable objects.

OctetSeqHelper - class org.omg.CORBA.OctetSeqHelper.

org/omg/CORBA/OctetSeqHelper.java Generated by the IDL-to-Java compiler (portable), version "3.0"
from streams.idl 13 May 1999 22:41:36 o'clock GMT+00:00

OctetSeqHelper() - Constructor for class org.omg.CORBA.OctetSeqHelper

OctetSeqHolder - class org.omg.CORBA.OctetSeqHolder.

org/omg/CORBA/OctetSeqHolder.java Generated by the IDL-to-Java compiler (portable), version "3.0"
from streams.idl 13 May 1999 22:41:36 o'clock GMT+00:00

OctetSeqHolder() - Constructor for class org.omg.CORBA.OctetSeqHolder

OctetSeqHolder(byte[]) - Constructor for class org.omg.CORBA.OctetSeqHolder

OCTOBER - Static variable in class java.util.Calendar

Value of the MONTH field indicating the tenth month of the year.

oEnd - Variable in class javax.swing.text.html.parser.Element

of(char) - Static method in class java.lang.Character.UnicodeBlock

Returns the object representing the Unicode block containing the given character, or null if the character is not a member of a defined block.

offset - Variable in class java.awt.image.DataBuffer

Offset into default (first) bank from which to get the first element.

offset - Variable in class javax.swing.text.Segment

This is the offset into the array that the desired text begins.

offset - Variable in class javax.swing.tree.DefaultTreeCellEditor

Used in editing.

offset - Variable in class javax.swing.plaf.basic.BasicScrollBarUI.TrackListener

offset - Variable in class javax.swing.plaf.basic.BasicSliderUI.TrackListener

offset - Variable in class org.omg.CORBA.portable.IndirectionException

Points to the stream's offset.

offsetRequested() - Method in class javax.swing.text.BadLocationException

Returns the offset into the document that was not legal.

offsets - Variable in class java.awt.image.DataBuffer

Offsets into all banks.

OK_CANCEL_OPTION - Static variable in class javax.swing.JOptionPane

Type used for showConfirmDialog.

OK_OPTION - Static variable in class javax.swing.JOptionPane

Return value form class method if OK is chosen.

okToUseGui - Variable in class java.beans.beancontext.BeanContextSupport

A boolean indicating if this instance may now render a GUI.

okToUseGui() - Method in interface java.beans.Visibility

This method instructs the bean that it is OK to use the Gui.

okToUseGui() - Method in class java.beans.beancontext.BeanContextSupport

Notify this instance that it may now render a GUI

OL - Static variable in class javax.swing.text.html.HTML.Tag

oldBinding - Variable in class javax.naming.event.NamingEvent

Contains information about the object before the change.

oldBorderPainted - Variable in class javax.swing.plaf.basic.BasicMenuItemUI

oldLeadSelectionPath - Variable in class javax.swing.event.TreeSelectionEvent

leadSelectionPath before the paths changed, may be null.

OMGVMCID - interface org.omg.CORBA.OMGVMCID.

The vendor minor code ID reserved for OMG.

omitEnd() - Method in class javax.swing.text.html.parser.Element

Return true if the end tag can be omitted.

omitStart() - Method in class javax.swing.text.html.parser.Element

Return true if the start tag can be omitted.

on(boolean) - Method in class java.security.DigestOutputStream

Turns the digest function on or off.

on(boolean) - Method in class java.security.DigestInputStream

Turns the digest function on or off.

ONE - Static variable in class java.math.BigInteger

The BigInteger constant one.

ONE_SIDED - Static variable in class java.awt.JobAttributes.SidesType

The SidesType instance to use for specifying that consecutive job pages should be printed upon the same side of consecutive media sheets.

ONE_TOUCH_EXPANDABLE_PROPERTY - Static variable in class javax.swing.JSplitPane

Bound property for oneTouchExpandable.

ONE_TOUCH_OFFSET - Static variable in class javax.swing.plaf.basic.BasicSplitPaneDivider

ONE_TOUCH_SIZE - Static variable in class javax.swing.plaf.basic.BasicSplitPaneDivider

Width or height of the divider based on orientation BasicSplitPaneUI adds two to this.

ONELEVEL_SCOPE - Static variable in class javax.naming.directory.SearchControls

Search one level of the named context.

ONELEVEL_SCOPE - Static variable in interface [javax.naming.event.EventContext](#)

Constant for expressing interest in events concerning objects in the context named by the target, excluding the context named by the target.

oneTouchExpandable - Variable in class [javax.swing.JSplitPane](#)

Is a little widget provided to quickly expand/collapse the split pane?

oneTouchExpandableChanged() - Method in class [javax.swing.plaf.basic.BasicSplitPaneDivider](#)

Messaged when the oneTouchExpandable value of the JSplitPane the receiver is contained in changes.

op_name() - Method in class [org.omg.CORBA.ServerRequest](#)

Deprecated. *use operation()*

OPAQUE - Static variable in interface [java.awt.Transparency](#)

Represents image data that is guaranteed to be completely opaque, meaning that all pixels have an alpha value of 1.0.

OPAQUE - Static variable in class [javax.accessibility.AccessibleState](#)

Indicates this object paints every pixel within its rectangular region.

OPEN - Static variable in class [java.awt.geom.Arc2D](#)

The closure type for an open arc with no path segments connecting the two ends of the arc segment.

OPEN - Static variable in class [javax.sound.sampled.LineEvent.Type](#)

A type of event that is sent when a line opens, reserving system resources for itself.

OPEN_DELETE - Static variable in class [java.util.zip.ZipFile](#)

Mode flag to open a zip file and mark it for deletion.

OPEN_DIALOG - Static variable in class [javax.swing.JFileChooser](#)

Type value indicating that the JFileChooser supports an "Open" file operation.

OPEN_READ - Static variable in class [java.util.zip.ZipFile](#)

Mode flag to open a zip file for reading.

open() - Method in interface [javax.sound.sampled.Line](#)

Opens the line, indicating that it should acquire any required system resources and become operational.

open() - Method in interface [javax.sound.midi.MidiDevice](#)

Opens the device, indicating that it should now acquire any system resources it requires and become operational.

open(AudioFormat) - Method in interface [javax.sound.sampled.TargetDataLine](#)

Opens the line with the specified format, causing the line to acquire any required system resources and become operational.

open(AudioFormat) - Method in interface [javax.sound.sampled.SourceDataLine](#)

Opens the line with the specified format, causing the line to acquire any required system resources and become operational.

open(AudioFormat, byte[], int, int) - Method in interface [javax.sound.sampled.Clip](#)

Opens the clip, meaning that it should acquire any required system resources and become operational.

open(AudioFormat, int) - Method in interface [javax.sound.sampled.TargetDataLine](#)

Opens the line with the specified format and requested buffer size, causing the line to acquire any required system resources and become operational.

open(AudioFormat, int) - Method in interface [javax.sound.sampled.SourceDataLine](#)

Opens the line with the specified format and suggested buffer size, causing the line to acquire any required system resources and become operational.

open(AudioInputStream) - Method in interface [javax.sound.sampled.Clip](#)

Opens the clip with the format and audio data present in the provided audio input stream.

openButtonMnemonic - Variable in class [javax.swing.plaf.basic.BasicFileChooserUI](#)

openButtonText - Variable in class javax.swing.plaf.basic.BasicFileChooserUI

openButtonToolTipText - Variable in class javax.swing.plaf.basic.BasicFileChooserUI

openConnection() - Method in class java.net.URL

Returns a URLConnection object that represents a connection to the remote object referred to by the URL.

openConnection(URL) - Method in class java.net.URLStreamHandler

Opens a connection to the object referenced by the URL argument.

openFrame(JInternalFrame) - Method in interface javax.swing.DesktopManager

If possible, display this frame in an appropriate location.

openFrame(JInternalFrame) - Method in class javax.swing.DefaultDesktopManager

Normally this method will not be called.

openIcon - Variable in class javax.swing.tree.DefaultTreeCellRenderer

Icon used to show non-leaf nodes that are expanded.

openMenuKey - Variable in class javax.swing.plaf.basic.BasicInternalFrameUI

Deprecated. *As of Java 2 platform v1.3.*

openStream() - Method in class java.net.URL

Opens a connection to this URL and returns an InputStream for reading from that connection.

OpenType - interface java.awt.font.OpenType.

The OpenType interface represents OpenType and TrueType fonts.

Operation - class java.rmi.server.Operation.

Deprecated. *no replacement*

operation() - Method in class org.omg.CORBA.ServerRequest

Retrieves the name of the operation being invoked.

operation() - Method in class org.omg.CORBA.Request

Retrieves the name of the method to be invoked.

Operation(String) - Constructor for class java.rmi.server.Operation

Deprecated. *no replacement*

OperationNotSupportedException - exception javax.naming.OperationNotSupportedException.

This exception is thrown when a context implementation does not support the operation being invoked.

OperationNotSupportedException() - Constructor for class javax.naming.OperationNotSupportedException

Constructs a new instance of OperationNotSupportedException.

OperationNotSupportedException(String) - Constructor for class

javax.naming.OperationNotSupportedException

Constructs a new instance of OperationNotSupportedException using an explanation.

OPTICAL_CHARACTER_RECOGNITION - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

Option - class javax.swing.text.html.Option.

Value for the ListModel used to represent <option> elements.

OPTION - Static variable in class javax.swing.text.html.HTML.Tag

OPTION_PANE - Static variable in class javax.accessibility.AccessibleRole

A specialized pane whose primary use is inside a DIALOG

OPTION_TYPE_PROPERTY - Static variable in class javax.swing.JOptionPane

Bound property name for optionType.

Option(AttributeSet) - Constructor for class javax.swing.text.html.Option

Creates a new Option object.

OptionalDataException - exception java.io.OptionalDataException.

Unexpected data appeared in an ObjectInputStream trying to read an Object.

optionPane - Variable in class javax.swing.plaf.basic.BasicOptionPaneUI

JOptionPane that the receiver is providing the look and feel for.

OptionPaneUI - class javax.swing.plaf.OptionPaneUI.

Pluggable look and feel interface for JOptionPane.

OptionPaneUI() - Constructor for class javax.swing.plaf.OptionPaneUI

options - Variable in class javax.swing.JOptionPane

Options to display to the user.

OPTIONS_PROPERTY - Static variable in class javax.swing.JOptionPane

Bounds property name for option.

optionType - Variable in class javax.swing.JOptionPane

Option type, one of DEFAULT_OPTION, YES_NO_OPTION, YES_NO_CANCEL_OPTION or OK_CANCEL_OPTION.

or(BigInteger) - Method in class java.math.BigInteger

Returns a BigInteger whose value is (this | val).

or(BitSet) - Method in class java.util.BitSet

Performs a logical OR of this bit set with the bit set argument.

orange - Static variable in class java.awt.Color

The color orange.

ORB - class org.omg.CORBA.ORB.

A class providing APIs for the CORBA Object Request Broker features.

ORB - class org.omg.CORBA_2_3.ORB.

A class extending org.omg.CORBA.ORB to make the ORB portable under the OMG CORBA version 2.3 specification.

orb() - Method in interface javax.rmi.CORBA.Tie

Returns the ORB for this tie.

orb() - Method in class org.omg.CORBA.portable.OutputStream

Returns the ORB that created this OutputStream.

orb() - Method in class org.omg.CORBA.portable.InputStream

Returns the ORB that created this InputStream.

ORB() - Constructor for class org.omg.CORBA.ORB

ORB() - Constructor for class org.omg.CORBA_2_3.ORB

orb(Object) - Method in class org.omg.CORBA.portable.Delegate

Provides a reference to the orb associated with its parameter.

orb(ORB) - Method in interface javax.rmi.CORBA.Tie

Sets the ORB for this tie.

ordered - Variable in class javax.naming.directory.BasicAttribute

A flag for recording whether this attribute's values are ordered.

ordinaryChar(int) - Method in class java.io.StreamTokenizer

Specifies that the character argument is "ordinary" in this tokenizer.

ordinaryChars(int, int) - Method in class java.io.StreamTokenizer

Specifies that all characters *c* in the range low <= *c* <= high are "ordinary" in this tokenizer.

org.omg.CORBA - package org.omg.CORBA

Provides the mapping of the OMG CORBA APIs to the Java™ programming language, including the class ORB, which is implemented so that a programmer can use it as a fully-functional Object Request Broker (ORB).

org.omg.CORBA_2_3 - package org.omg.CORBA_2_3

The CORBA_2_3 package defines additions to existing CORBA interfaces in the Java 2 Standard Edition. These changes occurred in recent revisions to the CORBA API defined by the OMG. The new methods were added to interfaces derived from the corresponding interfaces in the CORBA package. This provides backward compatibility and avoids breaking the JCK tests.

org.omg.CORBA_2_3.portable - package org.omg.CORBA_2_3.portable

Provides methods for the input and output of value types, and contains other updates to the org/omg/CORBA/portable package.

org.omg.CORBA.DynAnyPackage - package org.omg.CORBA.DynAnyPackage

Provides the exceptions used with the DynAny interface (InvalidValue, Invalid, InvalidSeq, and TypeMismatch).

org.omg.CORBA.ORBPackage - package org.omg.CORBA.ORBPackage

Provides the exception InvalidName, which is thrown by the method ORB.resolve_initial_references and the exception InconsistentTypeCode, which is thrown by the Dynamic Any creation methods in the ORB class.

org.omg.CORBA.portable - package org.omg.CORBA.portable

Provides a portability layer, that is, a set of ORB APIs that makes it possible for code generated by one vendor to run on another vendor's ORB.

org.omg.CORBA.TypeCodePackage - package org.omg.CORBA.TypeCodePackage

Provides the user-defined exceptions BadKind and Bounds, which are thrown by methods in the class TypeCode.

org.omg.CosNaming - package org.omg.CosNaming

Provides the naming service for Java IDL.

org.omg.CosNaming.NamingContextPackage - package org.omg.CosNaming.NamingContextPackage

Provides the exceptions used in the package org.omg.CosNaming (AlreadyBound, CannotProceed, InvalidName, NotEmpty, and NotFound) and also the Helper and Holder classes for those exceptions.

org.omg.SendingContext - package org.omg.SendingContext

Provides support for the marshalling of value types.

org.omg.stub.java.rmi - package org.omg.stub.java.rmi

Contains RMI-IIOP Stubs for the Remote types that occur in the java.rmi package.

orientation - Variable in class javax.swing.JSplitPane

How the views are split.

orientation - Variable in class javax.swing.JScrollBar

orientation - Variable in class javax.swing.JProgressBar

The orientation to display the progress bar.

orientation - Variable in class javax.swing.JSlider

orientation - Variable in class javax.swing.plaf.basic.BasicSplitPaneDivider

Orientation of the JSplitPane.

Orientation - Static variable in class javax.swing.text.StyleConstants

Orientation for a paragraph.

Orientation - Static variable in class javax.swing.text.StyleConstants.ParagraphConstants

Orientation for the paragraph.

ORIENTATION_PROPERTY - Static variable in class `javax.swing.JSplitPane`

Bound property name for orientation (horizontal or vertical).

origin - Variable in class `javax.swing.plaf.basic.BasicToolBarUI.DockingListener`

originalEx - Variable in class `org.omg.CORBA.portable.UnknownException`

A throwable--the original exception that was wrapped in a CORBA `UnknownException`.

OriginateDirection - Static variable in class `javax.swing.text.DefaultStyledDocument.ElementSpec`

A possible value for `getDirection`.

origmodel - Variable in class `java.awt.image.RGBImageFilter`

The `ColorModel` to be replaced by `newmodel` when the user calls `substituteColorModel`.

ORIYA - Static variable in class `java.lang.Character.UnicodeBlock`

Constant for the Unicode character block of the same name.

oStart - Variable in class `javax.swing.text.html.parser.Element`

OTHER - Static variable in class `java.sql.Types`

The constant in the Java programming language that indicates that the SQL type is database-specific and gets mapped to a Java object that can be accessed via the methods `getObject` and `setObject`.

OTHER_LETTER - Static variable in class `java.lang.Character`

Public data for enumerated Unicode general category types.

OTHER_NUMBER - Static variable in class `java.lang.Character`

Public data for enumerated Unicode general category types.

OTHER_PUNCTUATION - Static variable in class `java.lang.Character`

Public data for enumerated Unicode general category types.

OTHER_SYMBOL - Static variable in class `java.lang.Character`

Public data for enumerated Unicode general category types.

othersDeletesAreVisible(int) - Method in interface `java.sql.DatabaseMetaData`

Indicates whether deletes made by others are visible.

othersInsertsAreVisible(int) - Method in interface `java.sql.DatabaseMetaData`

Indicates whether inserts made by others are visible.

othersUpdatesAreVisible(int) - Method in interface `java.sql.DatabaseMetaData`

Indicates whether updates made by others are visible.

out - Variable in class `java.io.FilterWriter`

The underlying character-output stream.

out - Variable in class `java.io.FilterOutputStream`

The underlying output stream to be filtered.

out - Variable in class `java.io.PipedInputStream`

The index of the position in the circular buffer at which the next byte of data will be read by this piped input stream.

out - Variable in class `java.io.PrintWriter`

The underlying character-output stream of this `PrintWriter`.

out - Static variable in class `java.io.FileDescriptor`

A handle to the standard output stream.

out - Static variable in class `java.lang.System`

The "standard" output stream.

OUT_BOTTOM - Static variable in class `java.awt.geom.Rectangle2D`

The bitmask that indicates that a point lies below this `Rectangle2D`.

OUT_LEFT - Static variable in class `java.awt.geom.Rectangle2D`

getColumnTypeName(int) - Method in interface java.sql.ResultSetMetaData

Retrieves the designated column's database-specific type name.

getColumnWidth() - Method in class javax.swing.JTextField

Gets the column width.

getColumnWidth() - Method in class javax.swing.JTextArea

Gets column width.

getComboBox() - Method in class javax.swing.plaf.metal.MetalComboBoxButton

getComboIcon() - Method in class javax.swing.plaf.metal.MetalComboBoxButton

getCommand() - Method in class javax.sound.midi.ShortMessage

Obtains the MIDI command associated with this event.

getCommandEnvironment() - Method in class java.rmi.activation.ActivationGroupDesc

Returns the group's command-environment control object.

getCommandOptions() - Method in class java.rmi.activation.ActivationGroupDesc.CommandEnvironment

Fetch the configured java command options.

getCommandPath() - Method in class java.rmi.activation.ActivationGroupDesc.CommandEnvironment

Fetch the configured path-qualified java command name.

getComment() - Method in class java.util.zip.ZipEntry

Returns the comment string for the entry, or null if none.

getCommittedCharacterCount() - Method in class java.awt.event.InputMethodEvent

Gets the number of committed characters in the text.

getCommittedText(int, int, AttributedCharacterIterator.Attribute[]) - Method in interface java.awt.im.InputMethodRequests

Gets an iterator providing access to the entire text and attributes contained in the text editing component except for uncommitted text.

getCommittedTextLength() - Method in interface java.awt.im.InputMethodRequests

Gets the length of the entire text contained in the text editing component except for uncommitted (composed) text.

getComponent() - Method in class java.awt.dnd.DropTargetContext

This method returns the Component associated with this DropTargetContext.

getComponent() - Method in class java.awt.dnd.DragGestureRecognizer

This method returns the Component that is to be "observed" by the DragGestureRecognizer for drag initiating gestures.

getComponent() - Method in class java.awt.dnd.DragSourceContext

This method returns the Component associated with this DragSourceContext.

getComponent() - Method in class java.awt.dnd.DragGestureEvent

This method returns the Component associated with this DragGestureEvent.

getComponent() - Method in class java.awt.dnd.DropTarget

This method returns the Component associated with this DropTarget.

getComponent() - Method in class java.awt.event.HierarchyEvent

Returns the originator of the event.

getComponent() - Method in class java.awt.event.ComponentEvent

Returns the originator of the event.

getComponent() - Method in interface java.beans.beancontext.BeanContextChildComponentProxy

Gets the java.awt.Component associated with this BeanContextChild.

getComponent() - Method in class javax.swing.JMenuItem

This method returns the `java.awt.Component` used to paint this object.

`getComponent()` - Method in class `javax.swing.JMenu`
Returns the `java.awt.Component` used to paint this `MenuItem`.

`getComponent()` - Method in class `javax.swing.ComponentInputMap`
Returns the component the `InputMap` was created for.

`getComponent()` - Method in class `javax.swing.DefaultCellEditor`
Returns the a reference to the editor component.

`getComponent()` - Method in class `javax.swing.JPopupMenu`
Returns this `JPopupMenu` component.

`getComponent()` - Method in interface `javax.swing.Renderer`
Returns the component used to render the value.

`getComponent()` - Method in class `javax.swing.JToolTip`
Returns the component the tooltip applies to.

`getComponent()` - Method in class `javax.swing.JMenuBar`
Implemented to be a `MenuItem`.

`getComponent()` - Method in interface `javax.swing.MenuItem`
This method should return the `java.awt.Component` used to paint the receiving element.

`getComponent()` - Method in class `javax.swing.event.AncestorEvent`
Returns the component that the listener was added to.

`getComponent()` - Method in class `javax.swing.text.DefaultCaret`
Gets the text editor component that this caret is is bound to.

`getComponent()` - Method in class `javax.swing.text.ComponentView`
Fetch the component associated with the view.

`getComponent()` - Method in class `javax.swing.plaf.basic.BasicTextUI`
Fetches the text component associated with this UI implementation.

`getComponent(AttributeSet)` - Static method in class `javax.swing.text.StyleConstants`
Gets the component setting from the attribute list.

`getComponent(int)` - Method in class `java.awt.Container`
Gets the `nth` component in this container.

`getComponentAfter(Container, Component)` - Method in class `javax.swing.DefaultFocusManager`
Return the component the should receive the focus after a `Component`

`getComponentAt(int)` - Method in class `javax.swing.JTabbedPane`
Returns the component at `index`.

`getComponentAt(int, int)` - Method in class `java.awt.Component`
Determines if this component or one of its immediate subcomponents contains the (x, y) location, and if so, returns the containing component.

`getComponentAt(int, int)` - Method in class `java.awt.Container`
Locates the component that contains the `x,y` position.

`getComponentAt(Point)` - Method in class `java.awt.Component`
Returns the component or subcomponent that contains the specified point.

`getComponentAt(Point)` - Method in class `java.awt.Container`
Gets the component that contains the specified point.

`getComponentAtIndex(int)` - Method in class `javax.swing.JPopupMenu`
Deprecated. replaced by `getComponent(int i)`

`getComponentAtIndex(int)` - Method in class `javax.swing.JToolBar`
Returns the component at the specified index.

`getComponentAtIndex(int)` - Method in class `javax.swing.JMenuBar`

Deprecated. *replaced by `getComponent(int i)`*

`getComponentBefore(Container, Component)` - Method in class `javax.swing.DefaultFocusManager`

Return the component that should receive the focus before aComponent

`getComponentCount()` - Method in class `java.awt.Container`

Gets the number of components in this panel.

`getComponentCountInLayer(int)` - Method in class `javax.swing.JLayeredPane`

Returns the number of children currently in the specified layer.

`getComponentGraphics(Graphics)` - Method in class `javax.swing.JComponent`

Returns the graphics object used to paint this component.

`getComponentIndex(Component)` - Method in class `javax.swing.JPopupMenu`

Returns the index of the specified component.

`getComponentIndex(Component)` - Method in class `javax.swing.JToolBar`

Returns the index of the specified component.

`getComponentIndex(Component)` - Method in class `javax.swing.JMenuBar`

Returns the index of the specified component.

`getComponentOrientation()` - Method in class `java.awt.Component`

Retrieve the language-sensitive orientation that is to be used to order the elements or text within this component.

`getComponents()` - Method in class `java.awt.Container`

Gets all the components in this container.

`getComponents(ColorSpace, float[])` - Method in class `java.awt.Color`

Returns a float array containing the color and alpha components of the Color, in the ColorSpace specified by the cspace parameter.

`getComponents(float[])` - Method in class `java.awt.Color`

Returns a float array containing the color and alpha components of the Color, in the ColorSpace of the Color.

`getComponents(int, int[], int)` - Method in class `java.awt.image.ColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(int, int[], int)` - Method in class `java.awt.image.ComponentColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(int, int[], int)` - Method in class `java.awt.image.DirectColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(int, int[], int)` - Method in class `java.awt.image.IndexColorModel`

Returns an array of unnormalized color/alpha components for a specified pixel in this ColorModel.

`getComponents(Object, int[], int)` - Method in class `java.awt.image.ColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(Object, int[], int)` - Method in class `java.awt.image.ComponentColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(Object, int[], int)` - Method in class `java.awt.image.DirectColorModel`

Returns an array of unnormalized color/alpha components given a pixel in this ColorModel.

`getComponents(Object, int[], int)` - Method in class `java.awt.image.IndexColorModel`

Returns an array of unnormalized color/alpha components for a specified pixel in this ColorModel.

`getComponentsInLayer(int)` - Method in class `javax.swing.JLayeredPane`

Returns an array of the components in the specified layer.

`getComponentSize()` - Method in class `java.awt.image.ColorModel`

Returns an array of the number of bits per color/alpha component.

`getComponentSize()` - Method in class `java.awt.image.IndexColorModel`

Returns an array of the number of bits for each color/alpha component.

[getComponentSize\(int\)](#) - Method in class java.awt.image.[ColorModel](#)

Returns the number of bits for the specified color/alpha component.

[getComponentToLayer\(\)](#) - Method in class javax.swing.[JLayeredPane](#)

Returns the hashtable that maps components to layers.

[getComponentType\(\)](#) - Method in class java.lang.[Class](#)

Returns the [Class](#) representing the component type of an array.

[getComposite\(\)](#) - Method in class java.awt.[Graphics2D](#)

Returns the current [Composite](#) in the [Graphics2D](#) context.

[getCompressedSize\(\)](#) - Method in class java.util.zip.[ZipEntry](#)

Returns the size of the compressed entry data, or -1 if not known.

[getCompressionThreshold\(\)](#) - Method in class javax.swing.text.[StyleContext](#)

Returns the maximum number of key/value pairs to try and compress into unique/immutable sets.

[getConcurrency\(\)](#) - Method in interface java.sql.[ResultSet](#)

Returns the concurrency mode of this [ResultSet](#) object.

[getConditionForKeyStroke\(KeyStroke\)](#) - Method in class javax.swing.[JComponent](#)

Returns the condition that determines whether a registered action occurs in response to the specified keystroke.

[getConfigurations\(\)](#) - Method in class java.awt.[GraphicsDevice](#)

Returns all of the [GraphicsConfiguration](#) objects associated with this [GraphicsDevice](#).

[getConnectControls\(\)](#) - Method in class javax.naming.ldap.[InitialLdapContext](#)

[getConnectControls\(\)](#) - Method in interface javax.naming.ldap.[LdapContext](#)

Retrieves the connection request controls in effect for this context.

[getConnection\(\)](#) - Method in interface java.sql.[Statement](#)

Returns the [Connection](#) object that produced this [Statement](#) object.

[getConnection\(\)](#) - Method in interface java.sql.[DatabaseMetaData](#)

Retrieves the connection that produced this metadata object.

[getConnection\(String\)](#) - Static method in class java.sql.[DriverManager](#)

Attempts to establish a connection to the given database URL.

[getConnection\(String, Properties\)](#) - Static method in class java.sql.[DriverManager](#)

Attempts to establish a connection to the given database URL.

[getConnection\(String, String, String\)](#) - Static method in class java.sql.[DriverManager](#)

Attempts to establish a connection to the given database URL.

[getConstraints\(Component\)](#) - Method in class java.awt.[GridBagLayout](#)

Gets the constraints for the specified component.

[getConstructor\(Class\[\]\)](#) - Method in class java.lang.[Class](#)

Returns a [Constructor](#) object that reflects the specified public constructor of the class represented by this [Class](#) object.

[getConstructors\(\)](#) - Method in class java.lang.[Class](#)

Returns an array containing [Constructor](#) objects reflecting all the public constructors of the class represented by this [Class](#) object.

[getContainer\(\)](#) - Method in class java.awt.event.[ContainerEvent](#)

Returns the originator of the event.

[getContainer\(\)](#) - Method in interface java.beans.beancontext.[BeanContextContainerProxy](#)

Gets the java.awt.[Container](#) associated with this [BeanContext](#).

[getContainer\(\)](#) - Method in class javax.swing.text.[View](#)

Fetches the container hosting the view.

[getContent\(\)](#) - Method in class [java.net.URLConnection](#)
Retrieves the contents of this URL connection.

[getContent\(\)](#) - Method in class [java.net.URL](#)
Returns the contents of this URL.

[getContent\(\)](#) - Method in class [javax.naming.RefAddr](#)
Retrieves the contents of this address.

[getContent\(\)](#) - Method in class [javax.naming.BinaryRefAddr](#)
Retrieves the contents of this address as an Object.

[getContent\(\)](#) - Method in class [javax.naming.StringRefAddr](#)
Retrieves the contents of this address.

[getContent\(\)](#) - Method in class [javax.swing.text.AbstractDocument](#)
Gets the content for the document.

[getContent\(\)](#) - Method in class [javax.swing.text.html.parser.Element](#)
Get content model

[getContent\(Class\[\]\)](#) - Method in class [java.net.URLConnection](#)
Retrieves the contents of this URL connection.

[getContent\(Class\[\]\)](#) - Method in class [java.net.URL](#)
Returns the contents of this URL.

[getContent\(URLConnection\)](#) - Method in class [java.net.ContentHandler](#)
Given a URL connect stream positioned at the beginning of the representation of an object, this method reads that stream and creates an object from it.

[getContent\(URLConnection, Class\[\]\)](#) - Method in class [java.net.ContentHandler](#)
Given a URL connect stream positioned at the beginning of the representation of an object, this method reads that stream and creates an object that matches one of the types specified.

[getContentBorderInsets\(int\)](#) - Method in class [javax.swing.plaf.basic.BasicTabbedPaneUI](#)

[getContentEncoding\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of the content-encoding header field.

[getContentLength\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of the content-length header field.

[getContentPane\(\)](#) - Method in class [javax.swing.JWindow](#)
Returns the Container which is the contentPane for this window.

[getContentPane\(\)](#) - Method in class [javax.swing.JApplet](#)
Returns the contentPane object for this applet.

[getContentPane\(\)](#) - Method in class [javax.swing.JInternalFrame](#)

[getContentPane\(\)](#) - Method in class [javax.swing.JFrame](#)
Returns the contentPane object for this frame.

[getContentPane\(\)](#) - Method in interface [javax.swing.RootPaneContainer](#)
Returns the contentPane.

[getContentPane\(\)](#) - Method in class [javax.swing.JRootPane](#)
Returns the content pane -- the container that holds the components parented by the root pane.

[getContentPane\(\)](#) - Method in class [javax.swing.JDialog](#)
Returns the contentPane object for this dialog.

[getContents\(\)](#) - Method in class [java.util.ListResourceBundle](#)
See class description.

getContents() - Method in class javax.accessibility.AccessibleResourceBundle

Deprecated. Returns the mapping between the programmatic keys and the localized display strings.

getContents(Object) - Method in class java.awt.datatransfer.Clipboard

Returns a transferable object representing the current contents of the clipboard.

getContentType() - Method in class java.net.URLConnection

Returns the value of the content-type header field.

getContentType() - Method in class javax.swing.JEditorPane

Gets the type of content that this editor is currently set to deal with.

getContentType() - Method in class javax.swing.text.EditorKit

Gets the MIME type of the data that this kit represents support for.

getContentType() - Method in class javax.swing.text.DefaultEditorKit

Gets the MIME type of the data that this kit represents support for.

getContentType() - Method in class javax.swing.text.html.HTMLEditorKit

Get the MIME type of the data that this kit represents support for.

getContentType() - Method in class javax.swing.text.rtf.RTFEditorKit

Get the MIME type of the data that this kit represents support for.

getContentTypeFor(String) - Method in interface java.net.FileNameMap

Gets the MIME type for the specified file name.

getContext() - Static method in class java.security.AccessController

This method takes a "snapshot" of the current calling context, which includes the current Thread's inherited AccessControlContext, and places it in an AccessControlContext object.

getContextClassLoader() - Method in class java.lang.Thread

Returns the context ClassLoader for this Thread.

getContinuationContext(CannotProceedException) - Static method in class javax.naming.spi.NamingManager

Creates a context in which to continue a context operation.

getContinuationDirContext(CannotProceedException) - Static method in class javax.naming.spi.DirectoryManager

Creates a context in which to continue a DirContext operation.

getControl() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControl() - Method in class javax.swing.plaf.metal.MetalTheme

getControl(Control.Type) - Method in interface javax.sound.sampled.Line

Obtains a control of the specified type, if there is any.

getControlButtonsAreShown() - Method in class javax.swing.JFileChooser

Returns a boolean indicating whether the accept and cancel buttons are shown in the file chooser.

getControlDarkShadow() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlDarkShadow() - Method in class javax.swing.plaf.metal.MetalTheme

getControlDisabled() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlDisabled() - Method in class javax.swing.plaf.metal.MetalTheme

getControlHighlight() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlHighlight() - Method in class javax.swing.plaf.metal.MetalTheme

getControlInfo() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlInfo() - Method in class javax.swing.plaf.metal.MetalTheme

getControlInstance(Control) - Method in class javax.naming.ldap.ControlFactory

Creates a control using this control factory.

getControlInstance(Control, Context, Hashtable) - Static method in class javax.naming.ldap.ControlFactory

Creates a control using known control factories.

getController(int) - Method in interface javax.sound.midi.MidiChannel

Obtains the current value of the specified controller.

getControlObject() - Method in interface java.awt.im.spi.InputMethod

Returns a control object from this input method, or null.

getControls() - Method in interface javax.sound.sampled.Line

Obtains the set of controls associated with this line.

getControls() - Method in interface javax.naming.ldap.HasControls

Retrieves an array of Controls from the object that implements this interface.

getControlShadow() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlShadow() - Method in class javax.swing.plaf.metal.MetalTheme

getControlSize() - Method in class javax.swing.plaf.metal.MetalCheckBoxIcon

getControlTextColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlTextColor() - Method in class javax.swing.plaf.metal.MetalTheme

getControlTextFont() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getControlTextFont() - Method in class javax.swing.plaf.metal.MetalTheme

getControlTextFont() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getCopies() - Method in class java.awt.JobAttributes

Returns the number of copies the application should render for jobs using these attributes.

getCopies() - Method in class java.awt.print.PrinterJob

Gets the number of copies to be printed.

getCorner(String) - Method in class javax.swing.ScrollPaneLayout

Returns the Component at the specified corner.

getCorner(String) - Method in class javax.swing.JScrollPane

Returns the component at the specified corner.

getCountLimit() - Method in class javax.naming.directory.SearchControls

Retrieves the maximum number of entries that will be returned as a result of the search.

getCountry() - Method in class java.util.Locale

Returns the country/region code for this locale, which will either be the empty string or an upcase ISO 3166 2-letter code.

getCrc() - Method in class java.util.zip.ZipEntry

Returns the CRC-32 checksum of the uncompressed entry data, or -1 if not known.

getCreationDate(String) - Method in class java.security.KeyStore
Returns the creation date of the entry identified by the given alias.

getCriticalExtensionOIDs() - Method in interface java.security.cert.X509Extension
Gets a Set of the OID strings for the extension(s) marked CRITICAL in the certificate/CRL managed by the object implementing this interface.

getCrossPlatformLookAndFeelClassName() - Static method in class javax.swing.UIManager
Returns the name of the LookAndFeel class that implements the default cross platform look and feel -- the Java Look and Feel (JLF).

getCrossReference(String, String, String, String, String, String) - Method in interface java.sql.DatabaseMetaData
Gets a description of the foreign key columns in the foreign key table that reference the primary key columns of the primary key table (describe how one table imports another's key.) This should normally return a single foreign key/primary key pair (most tables only import a foreign key from a table once.) They are ordered by FKTABLE_CAT, FKTABLE_SCHEM, FKTABLE_NAME, and KEY_SEQ.

getCrtCoefficient() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the crtCoefficient.

getCrtCoefficient() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the crtCoefficient.

getCtrlP1() - Method in class java.awt.geom.CubicCurve2D
Returns the first control point.

getCtrlP1() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the first control point.

getCtrlP1() - Method in class java.awt.geom.CubicCurve2D.Double
Returns the first control point.

getCtrlP2() - Method in class java.awt.geom.CubicCurve2D
Returns the second control point.

getCtrlP2() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the second control point.

getCtrlP2() - Method in class java.awt.geom.CubicCurve2D.Double
Returns the second control point.

getCtrlPt() - Method in class java.awt.geom.QuadCurve2D
Returns the control point.

getCtrlPt() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the control point.

getCtrlPt() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the control point.

getCtrlX() - Method in class java.awt.geom.QuadCurve2D
Returns the x coordinate of the control point in double precision.

getCtrlX() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the x coordinate of the control point in double precision.

getCtrlX() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the x coordinate of the control point in double precision.

getCtrlX1() - Method in class java.awt.geom.CubicCurve2D
Returns the X coordinate of the first control point in double precision.

getCtrlX1() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the X coordinate of the first control point in double precision.

getCtrlX1Q - Method in class java.awt.geom.CubicCurve2D.Double
Returns the X coordinate of the first control point in double precision.

getCtrlX2Q - Method in class java.awt.geom.CubicCurve2D
Returns the X coordinate of the second control point in double precision.

getCtrlX2Q - Method in class java.awt.geom.CubicCurve2D.Float
Returns the X coordinate of the second control point in double precision.

getCtrlX2Q - Method in class java.awt.geom.CubicCurve2D.Double
Returns the X coordinate of the second control point in double precision.

getCtrlYQ - Method in class java.awt.geom.QuadCurve2D
Returns the y coordinate of the control point in double precision.

getCtrlYQ - Method in class java.awt.geom.QuadCurve2D.Float
Returns the y coordinate of the control point in double precision.

getCtrlYQ - Method in class java.awt.geom.QuadCurve2D.Double
Returns the y coordinate of the control point in double precision.

getCtrlY1Q - Method in class java.awt.geom.CubicCurve2D
Returns the Y coordinate of the first control point in double precision.

getCtrlY1Q - Method in class java.awt.geom.CubicCurve2D.Float
Returns the Y coordinate of the first control point in double precision.

getCtrlY1Q - Method in class java.awt.geom.CubicCurve2D.Double
Returns the Y coordinate of the first control point in double precision.

getCtrlY2Q - Method in class java.awt.geom.CubicCurve2D
Returns the Y coordinate of the second control point in double precision.

getCtrlY2Q - Method in class java.awt.geom.CubicCurve2D.Float
Returns the Y coordinate of the second control point in double precision.

getCtrlY2Q - Method in class java.awt.geom.CubicCurve2D.Double
Returns the Y coordinate of the second control point in double precision.

getCurrencyInstanceQ - Static method in class java.text.NumberFormat
Returns a currency format for the current default locale.

getCurrencyInstance(Locale) - Static method in class java.text.NumberFormat
Returns a currency format for the specified locale.

getCurrencySymbolQ - Method in class java.text.DecimalFormatSymbols
Return the string denoting the local currency.

getCurrentQ - Method in class java.awt.CheckboxGroup
Deprecated. *As of JDK version 1.1, replaced by `getSelectedCheckbox()`.*

getCurrentAccessibleValueQ - Method in class java.awt.Scrollbar.AccessibleAWTScrollBar
Get the accessible value of this object.

getCurrentAccessibleValueQ - Method in class java.awt.MenuItem.AccessibleAWTMenuItem
Get the value of this object as a Number.

getCurrentAccessibleValueQ - Method in class java.awt.Checkbox.AccessibleAWTCheckbox
Get the value of this object as a Number.

getCurrentAccessibleValueQ - Method in class java.awt.Button.AccessibleAWTButton
Get the value of this object as a Number.

getCurrentAccessibleValueQ - Method in class java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem
Get the value of this object as a Number.

getCurrentAccessibleValueQ - Method in interface javax.accessibility.AccessibleValue
Get the value of this object as a Number.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)

Get the value of this object as a Number.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JInternalFrame.AccessibleJInternalFrame](#)

Get the value of this object as a Number.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JInternalFrame.JDesktopIcon.AccessibleJDesktopIcon](#)

Get the value of this object as a Number.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JSplitPane.AccessibleJSplitPane](#)

Gets the accessible value of this object.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JScrollBar.AccessibleJScrollBar](#)

Get the accessible value of this object.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JProgressBar.AccessibleJProgressBar](#)

Get the accessible value of this object.

[getCurrentAccessibleValue\(\)](#) - Method in class [javax.swing.JSlider.AccessibleJSlider](#)

Get the accessible value of this object.

[getCurrentDataFlavors\(\)](#) - Method in class [java.awt.dnd.DropTargetContext](#)

get the available DataFlavors of the Transferable operand of this operation.

[getCurrentDataFlavors\(\)](#) - Method in class [java.awt.dnd.DropTargetDropEvent](#)

This method returns the current DataFlavors.

[getCurrentDataFlavors\(\)](#) - Method in class [java.awt.dnd.DropTargetDragEvent](#)

This method returns the current DataFlavors from the DropTargetContext.

[getCurrentDataFlavorsAsList\(\)](#) - Method in class [java.awt.dnd.DropTargetContext](#)

This method returns a the currently available DataFlavors of the Transferable operand as a [java.util.List](#).

[getCurrentDataFlavorsAsList\(\)](#) - Method in class [java.awt.dnd.DropTargetDropEvent](#)

This method returns the currently available DataFlavors as a [java.util.List](#).

[getCurrentDataFlavorsAsList\(\)](#) - Method in class [java.awt.dnd.DropTargetDragEvent](#)

This method returns the current DataFlavors as a [java.util.List](#)

[getCurrentDirectory\(\)](#) - Method in class [javax.swing.JFileChooser](#)

Returns the current directory.

[getCurrentLine\(\)](#) - Method in class [javax.swing.text.html.parser.Parser](#)

[getCurrentLineLength\(\)](#) - Method in class [javax.swing.text.AbstractWriter](#)

Returns the current line length.

[getCurrentManager\(\)](#) - Static method in class [javax.swing.FocusManager](#)

Return the FocusManager for the calling thread There is one FocusManager per thread group

[getCurrentPoint\(\)](#) - Method in class [java.awt.geom.GeneralPath](#)

Returns the coordinates most recently added to the end of the path as a [Point2D](#) object.

[getCurrentPos\(\)](#) - Method in class [javax.swing.text.html.parser.Parser](#)

[getCurrentServiceClasses\(\)](#) - Method in class [java.beans.beancontext.BeanContextServicesSupport](#)

[getCurrentServiceClasses\(\)](#) - Method in interface [java.beans.beancontext.BeanContextServices](#)

Gets the currently available services for this context.

[getCurrentServiceSelectors\(\)](#) - Method in class [java.beans.beancontext.BeanContextServiceAvailableEvent](#)

Gets the list of service dependent selectors.

[getCurrentServiceSelectors\(BeanContextServices, Class\)](#) - Method in class

java.beans.beancontext.BeanContextServicesSupport.BCSSProxyServiceProvider

getCurrentServiceSelectors(BeanContextServices, Class) - Method in interface

java.beans.beancontext.BeanContextServiceProvider

Invoked by BeanContextServices, this method gets the current service selectors for the specified service.

getCurrentServiceSelectors(Class) - Method in class java.beans.beancontext.BeanContextServicesSupport

getCurrentServiceSelectors(Class) - Method in interface java.beans.beancontext.BeanContextServices

Gets the list of service dependent service parameters (Service Selectors) for the specified service, by calling getCurrentServiceSelectors() on the underlying BeanContextServiceProvider.

getCurrentWriter() - Method in class javax.swing.text.AbstractDocument

Fetches the current writing thread if there is one.

getCursor() - Method in class java.awt.Component

Gets the cursor set in the component.

getCursor() - Method in class java.awt.Component.AccessibleAWTComponent

Get the Cursor of this object.

getCursor() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Get the Cursor of this object.

getCursor() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Get the Cursor of this object.

getCursor() - Method in class java.awt.dnd.DragSourceContext

This method returns the current drag Cursor.

getCursor() - Method in interface javax.accessibility.AccessibleComponent

Gets the Cursor of this object.

getCursor() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getCursor() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

getCursor() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Gets the Cursor of this object.

getCursor() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getCursorName() - Method in interface java.sql.ResultSet

Gets the name of the SQL cursor used by this ResultSet object.

getCursorType() - Method in class java.awt.Frame

Deprecated. *As of JDK version 1.1, replaced by Component.setCursor().*

getCustomEditor() - Method in interface java.beans.PropertyEditor

A PropertyEditor may choose to make available a full custom Component that edits its property value.

getCustomEditor() - Method in class java.beans.PropertyEditorSupport

A PropertyEditor may chose to make available a full custom Component that edits its property value.

getCustomizerClass() - Method in class java.beans.BeanDescriptor

Gets the Class object for the bean's customizer.

getDashArray() - Method in class java.awt.BasicStroke

Returns the array representing the lengths of the dash segments.

getDashPhase() - Method in class java.awt.BasicStroke

Returns the current dash phase.

[getData\(\)](#) - Method in class java.awt.color.[ICC_Profile](#)

Returns a byte array corresponding to the data of this ICC_Profile.

[getData\(\)](#) - Method in class java.awt.image.[DataBufferUShort](#)

Returns the default (first) unsigned-short data array.

[getData\(\)](#) - Method in interface java.awt.image.[RenderedImage](#)

Returns the image as one large tile (for tile based images this will require fetching the whole image and copying the image data over).

[getData\(\)](#) - Method in class java.awt.image.[BufferedImage](#)

Returns the image as one large tile.

[getData\(\)](#) - Method in class java.awt.image.[DataByteBuffer](#)

Returns the default (first) byte data array.

[getData\(\)](#) - Method in class java.awt.image.[DataBufferInt](#)

Returns the default (first) int data array in DataBuffer.

[getData\(\)](#) - Method in class java.awt.image.[DataBufferShort](#)

Returns the default (first) byte data array.

[getData\(\)](#) - Method in class java.net.[DatagramPacket](#)

Returns the data received or the data to be sent.

[getData\(\)](#) - Method in class java.rmi.activation.[ActivationGroupDesc](#)

Returns the group's initialization data.

[getData\(\)](#) - Method in class java.rmi.activation.[ActivationDesc](#)

Returns a "marshalled object" containing initialization/activation data for the object specified by this descriptor.

[getData\(\)](#) - Method in class javax.sound.midi.[SysexMessage](#)

Obtains a copy of the data for the system exclusive message.

[getData\(\)](#) - Method in class javax.sound.midi.[MetaMessage](#)

Obtains a copy of the data for the meta message.

[getData\(\)](#) - Method in class javax.sound.midi.[SoundbankResource](#)

Obtains the sampled audio that is stored in this SoundbankResource.

[getData\(\)](#) - Method in class javax.swing.text.html.parser.[Entity](#)

Return the data.

[getData\(int\)](#) - Method in class java.awt.color.[ICC_Profile](#)

Returns a particular tagged data element from the profile as a byte array.

[getData\(int\)](#) - Method in class java.awt.image.[DataBufferUShort](#)

Returns the data array for the specified bank.

[getData\(int\)](#) - Method in class java.awt.image.[DataByteBuffer](#)

Returns the data array for the specified bank.

[getData\(int\)](#) - Method in class java.awt.image.[DataBufferInt](#)

Returns the data array for the specified bank.

[getData\(int\)](#) - Method in class java.awt.image.[DataBufferShort](#)

Returns the data array for the specified bank.

[getData\(Rectangle\)](#) - Method in interface java.awt.image.[RenderedImage](#)

Computes and returns an arbitrary region of the RenderedImage.

[getData\(Rectangle\)](#) - Method in class java.awt.image.[BufferedImage](#)

Computes and returns an arbitrary region of the BufferedImage.

[getData1\(\)](#) - Method in class javax.sound.midi.[ShortMessage](#)

Obtains the first data byte in the message.

getData2() - Method in class javax.sound.midi.ShortMessage

Obtains the second data byte in the message.

getDatabaseProductName() - Method in interface java.sql.DatabaseMetaData

What's the name of this database product?

getDatabaseProductVersion() - Method in interface java.sql.DatabaseMetaData

What's the version of this database product?

getDataBitOffset() - Method in class java.awt.image.MultiPixelPackedSampleModel

Returns the data bit offset in bits.

getDataBuffer() - Method in class java.awt.image.Raster

Returns the DataBuffer associated with this Raster.

getDataClass() - Method in class javax.sound.midi.SoundbankResource

Obtains the class used by this sample to represent its data.

getDataElement(int[], int) - Method in class java.awt.image.ColorModel

Returns a pixel value represented as an int in this ColorModel, given an array of unnormalized color/alpha components.

getDataElement(int[], int) - Method in class java.awt.image.ComponentColorModel

Returns a pixel value represented as an int in this ColorModel, given an array of unnormalized color/alpha components.

getDataElement(int[], int) - Method in class java.awt.image.DirectColorModel

Returns a pixel value represented as an int in this ColorModel, given an array of unnormalized color/alpha components.

getDataElement(int[], int) - Method in class java.awt.image.IndexColorModel

Returns a pixel value represented as an int in this ColorModel given an array of unnormalized color/alpha components.

getDataElements(int[], int, Object) - Method in class java.awt.image.ColorModel

Returns a data element array representation of a pixel in this ColorModel, given an array of unnormalized color/alpha components.

getDataElements(int[], int, Object) - Method in class java.awt.image.ComponentColorModel

Returns a data element array representation of a pixel in this ColorModel, given an array of unnormalized color/alpha components.

getDataElements(int[], int, Object) - Method in class java.awt.image.DirectColorModel

Returns a data element array representation of a pixel in this ColorModel, given an array of unnormalized color/alpha components.

getDataElements(int[], int, Object) - Method in class java.awt.image.IndexColorModel

Returns a data element array representation of a pixel in this ColorModel given an array of unnormalized color/alpha components.

getDataElements(int, int, int, int, Object) - Method in class java.awt.image.Raster

Returns the pixel data for the specified rectangle of pixels in a primitive array of type TransferType.

getDataElements(int, int, int, int, Object, DataBuffer) - Method in class java.awt.image.SampleModel

Returns the pixel data for the specified rectangle of pixels in a primitive array of type TransferType.

getDataElements(int, int, Object) - Method in class java.awt.image.Raster

Returns data for a single pixel in a primitive array of type TransferType.

getDataElements(int, int, Object, DataBuffer) - Method in class java.awt.image.SampleModel

Returns data for a single pixel in a primitive array of type TransferType.

getDataElements(int, int, Object, DataBuffer) - Method in class java.awt.image.ComponentSampleModel

Returns data for a single pixel in a primitive array of type TransferType.

getDataElements(int, int, Object, DataBuffer) - Method in class java.awt.image.BandedSampleModel

Returns data for a single pixel in a primitive array of type `TransferType`.
`getDataElements(int, int, Object, DataBuffer)` - Method in class `java.awt.image.MultiPixelPackedSampleModel`

Returns data for a single pixel in a primitive array of type `TransferType`.
`getDataElements(int, int, Object, DataBuffer)` - Method in class `java.awt.image.SinglePixelPackedSampleModel`

Returns data for a single pixel in a primitive array of type `TransferType`.
`getDataElements(int, Object)` - Method in class `java.awt.image.ColorModel`

Returns a data element array representation of a pixel in this `ColorModel`, given an integer pixel representation in the default RGB color model.
`getDataElements(int, Object)` - Method in class `java.awt.image.ComponentColorModel`

Returns a data element array representation of a pixel in this `ColorModel`, given an integer pixel representation in the default RGB color model.
`getDataElements(int, Object)` - Method in class `java.awt.image.DirectColorModel`

Returns a data element array representation of a pixel in this `ColorModel`, given an integer pixel representation in the default RGB color model.
`getDataElements(int, Object)` - Method in class `java.awt.image.IndexColorModel`

Returns a data element array representation of a pixel in this `ColorModel`, given an integer pixel representation in the default RGB color model.
`getDataLength(int)` - Method in class `javax.sound.midi.ShortMessage`

Retrieves the number of data bytes associated with a particular status byte value.
`getDataSize()` - Method in class `java.sql.DataTruncation`

Gets the number of bytes of data that should have been transferred.
`getDataType()` - Method in class `java.awt.image.SampleModel`

Returns the data type of the `DataBuffer` storing the pixel data.
`getDataType()` - Method in class `java.awt.image.DataBuffer`

Returns the data type of this `DataBuffer`.
`getDataTypeSize(int)` - Static method in class `java.awt.image.DataBuffer`

Returns the size (in bits) of the data type, given a datatype tag.
`getDataVector()` - Method in class `javax.swing.table.DefaultTableModel`

Returns the `Vector` of `Vectors` that contains the table's data values.
`getDate()` - Method in class `java.net.URLConnection`

Returns the value of the date header field.
`getDate()` - Method in class `java.sql.Time`

Deprecated.

`getDate()` - Method in class `java.util.Date`

Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.DAY_OF_MONTH)`.*

`getDate(int)` - Method in interface `java.sql.CallableStatement`

Gets the value of a JDBC DATE parameter as a `java.sql.Date` object.
`getDate(int)` - Method in interface `java.sql.ResultSet`

Gets the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Date` object in the Java programming language.
`getDate(int, Calendar)` - Method in interface `java.sql.CallableStatement`

Gets the value of a JDBC DATE parameter as a `java.sql.Date` object, using the given `Calendar` object to construct the date.
`getDate(int, Calendar)` - Method in interface `java.sql.ResultSet`

Returns the value of the designated column in the current row of this `ResultSet` object as a

`java.sql.Date` object in the Java programming language.

`getDate(String)` - Method in interface `java.sql.ResultSet`

Gets the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Date` object in the Java programming language.

`getDate(String, Calendar)` - Method in interface `java.sql.ResultSet`

Returns the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Date` object in the Java programming language.

`getDateFormatSymbols()` - Method in class `java.text.SimpleDateFormat`

Gets the date/time formatting data.

`getDateInstance()` - Static method in class `java.text.DateFormat`

Gets the date formatter with the default formatting style for the default locale.

`getDateInstance(int)` - Static method in class `java.text.DateFormat`

Gets the date formatter with the given formatting style for the default locale.

`getDateInstance(int, Locale)` - Static method in class `java.text.DateFormat`

Gets the date formatter with the given formatting style for the given locale.

`getTimeInstance()` - Static method in class `java.text.DateFormat`

Gets the date/time formatter with the default formatting style for the default locale.

`getTimeInstance(int, int)` - Static method in class `java.text.DateFormat`

Gets the date/time formatter with the given date and time formatting styles for the default locale.

`getTimeInstance(int, int, Locale)` - Static method in class `java.text.DateFormat`

Gets the date/time formatter with the given formatting styles for the given locale.

`getDay()` - Method in class `java.sql.Time`

Deprecated.

`getDay()` - Method in class `java.util.Date`

Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.DAY_OF_WEEK)`.*

`getDebugGraphicsOptions()` - Method in class `javax.swing.JComponent`

Returns the state of graphics debugging.

`getDebugOptions()` - Method in class `javax.swing.DebugGraphics`

Returns the current debugging options for this `DebugGraphics`.

`getDecayTime()` - Method in class `javax.sound.sampled.ReverbType`

Obtains the decay time, which is the amount of time over which the late reflections attenuate to effective zero.

`getDecimalFormatSymbols()` - Method in class `java.text.DecimalFormat`

Returns the decimal format symbols, which is generally not changed by the programmer or user.

`getDecimalSeparator()` - Method in class `java.text.DecimalFormatSymbols`

Gets the character used for decimal sign.

`getDeclaration(String)` - Method in class `javax.swing.text.html.StyleSheet`

Translates a CSS declaration to an `AttributeSet` that represents the CSS declaration.

`getDeclaredClasses()` - Method in class `java.lang.Class`

Returns an array of `Class` objects reflecting all the classes and interfaces declared as members of the class represented by this `Class` object.

`getDeclaredConstructor(Class[])` - Method in class `java.lang.Class`

Returns a `Constructor` object that reflects the specified constructor of the class or interface represented by this `Class` object.

`getDeclaredConstructors()` - Method in class `java.lang.Class`

Returns an array of `Constructor` objects reflecting all the constructors declared by the class represented by this `Class` object.

getDeclaredField(String) - Method in class java.lang.Class

Returns a Field object that reflects the specified declared field of the class or interface represented by this Class object.

getDeclaredFields() - Method in class java.lang.Class

Returns an array of Field objects reflecting all the fields declared by the class or interface represented by this Class object.

getDeclaredMethod(String, Class[]) - Method in class java.lang.Class

Returns a Method object that reflects the specified declared method of the class or interface represented by this Class object.

getDeclaredMethods() - Method in class java.lang.Class

Returns an array of Method objects reflecting all the methods declared by the class or interface represented by this Class object.

getDeclaringClass() - Method in class java.lang.Class

If the class or interface represented by this Class object is a member of another class, returns the Class object representing the class in which it was declared.

getDeclaringClass() - Method in interface java.lang.reflect.Member

Returns the Class object representing the class or interface that declares the member or constructor represented by this Member.

getDeclaringClass() - Method in class java.lang.reflect.Method

Returns the Class object representing the class or interface that declares the method represented by this Method object.

getDeclaringClass() - Method in class java.lang.reflect.Field

Returns the Class object representing the class or interface that declares the field represented by this Field object.

getDeclaringClass() - Method in class java.lang.reflect.Constructor

Returns the Class object representing the class that declares the constructor represented by this Constructor object.

getDecomposition() - Method in class java.text.Collator

Get the decomposition mode of this Collator.

getDeepestComponentAt(Component, int, int) - Static method in class javax.swing.SwingUtilities

Returns the deepest visible descendent Component of parent that contains the location x, y.

getDefault() - Static method in class java.util.TimeZone

Gets the default TimeZone for this host.

getDefault() - Static method in class java.util.Locale

Gets the current value of the default locale for this instance of the Java Virtual Machine.

getDefaultAction() - Method in interface javax.swing.text.Keymap

Fetches the default action to fire if a key is typed (i.e.

getDefaultActions() - Method in class java.awt.dnd.DropTarget

This method returns an int representing the current action(s) supported by this DropTarget.

getDefaultAllowUserInteraction() - Static method in class java.net.URLConnection

Returns the default value of the allowUserInteraction field.

getDefaultButton() - Method in class javax.swing.JRootPane

Returns the current default button for this JRootPane.

getDefaultChooserPanels() - Static method in class javax.swing.colorchooser.ColorChooserComponentFactory

getDefaultClosedIcon() - Method in class javax.swing.tree.DefaultTreeCellRenderer

Returns the default icon, for the current laf, that is used to represent non-leaf nodes that are not

expanded.

[getDefaultCloseOperation\(\)](#) - Method in class javax.swing.[JInternalFrame](#)

Returns the default operation which occurs when the user initiates a "close" on this window.

[getDefaultCloseOperation\(\)](#) - Method in class javax.swing.[JFrame](#)

Returns the operation that occurs when the user initiates a "close" on this frame.

[getDefaultCloseOperation\(\)](#) - Method in class javax.swing.[JDialog](#)

Returns the operation which occurs when the user initiates a "close" on this dialog.

[getDefaultConfiguration\(\)](#) - Method in class java.awt.[GraphicsDevice](#)

Returns the default GraphicsConfiguration associated with this GraphicsDevice.

[getDefaultCursor\(\)](#) - Static method in class java.awt.[Cursor](#)

Return the system default cursor.

[getDefaultCursor\(\)](#) - Method in class javax.swing.text.html.[HTMLEditorKit](#)

Returns the default cursor.

[getDefaultDragSource\(\)](#) - Static method in class java.awt.dnd.[DragSource](#)

This method returns the DragSource object associated with the underlying platform.

[getDefaultEditor\(Class\)](#) - Method in class javax.swing.[JTable](#)

Returns the editor to be used when no editor has been set in a TableColumn.

[getDefaultEventIndex\(\)](#) - Method in interface java.beans.[BeanInfo](#)

A bean may have a "default" event that is the event that will mostly commonly be used by humans when using the bean.

[getDefaultEventIndex\(\)](#) - Method in class java.beans.[SimpleBeanInfo](#)

Deny knowledge of a default event.

[getDefaultFlavorMap\(\)](#) - Static method in class java.awt.datatransfer.[SystemFlavorMap](#)

get the default system implementation

[getDefaultIcon\(\)](#) - Method in class javax.swing.plaf.basic.[BasicRadioButtonUI](#)

[getDefaultInitCtx\(\)](#) - Method in class javax.naming.[InitialContext](#)

Retrieves the initial context by calling NamingManager.getInitialContext() and cache it in defaultInitCtx.

[getDefaultLeafIcon\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellRenderer](#)

Returns the default icon, for the current laf, that is used to represent leaf nodes.

[getDefaultLightWeightPopupEnabled\(\)](#) - Static method in class javax.swing.[JPopupMenu](#)

Returns true if this is a light weight popup component, false otherwise.

[getDefaultOpenIcon\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellRenderer](#)

Returns the default icon, for the current laf, that is used to represent non-leaf nodes that are expanded.

[getDefaultPort\(\)](#) - Method in class java.net.[URLStreamHandler](#)

Returns the default port for a URL parsed by this handler.

[getDefaultPropertyIndex\(\)](#) - Method in interface java.beans.[BeanInfo](#)

A bean may have a "default" property that is the property that will mostly commonly be initially chosen for update by human's who are customizing the bean.

[getDefaultPropertyIndex\(\)](#) - Method in class java.beans.[SimpleBeanInfo](#)

Deny knowledge of a default property.

[getDefaultQueue\(\)](#) - Static method in class javax.swing.text.[LayoutQueue](#)

Fetch the default layout queue.

[getDefaultRenderer\(\)](#) - Method in class javax.swing.table.[JTableHeader](#)

Returns the default renderer used when no headerRenderer is defined by a TableColumn.

[getDefaultRenderer\(Class\)](#) - Method in class javax.swing.[JTable](#)

Returns the cell renderer to be used when no renderer has been set in a `TableColumn`.
`getDefaultRepresentationClass()` - Method in class `java.awt.datatransfer.DataFlavor`

`getDefaultRepresentationClassAsString()` - Method in class `java.awt.datatransfer.DataFlavor`

`getDefaultRequestProperty(String)` - Static method in class `java.net.URLConnection`

Deprecated. *The instance specific `getRequestProperty` method should be used after an appropriate instance of `URLConnection` is obtained.*

`getDefaultRootElement()` - Method in interface `javax.swing.text.Document`

Returns the root element that views should be based upon, unless some other mechanism for assigning views to element structures is provided.

`getDefaultRootElement()` - Method in class `javax.swing.text.AbstractDocument`

Returns the root element that views should be based upon unless some other mechanism for assigning views to element structures is provided.

`getDefaultRootElement()` - Method in class `javax.swing.text.PlainDocument`

Gets the default root element for the document model.

`getDefaultRootElement()` - Method in class `javax.swing.text.DefaultStyledDocument`

Gets the default root element.

`getDefaults()` - Method in class `javax.swing.LookAndFeel`

This method is called once by `UIManager.setLookAndFeel` to create the look and feel specific defaults table.

`getDefaults()` - Static method in class `javax.swing.UIManager`

Returns the default values for this look and feel.

`getDefaults()` - Method in class `javax.swing.plaf.basic.BasicLookAndFeel`

`getDefaults()` - Method in class `javax.swing.plaf.metal.MetalLookAndFeel`

`getDefaults()` - Method in class `javax.swing.plaf.multi.MultiLookAndFeel`

`getDefaultScreenDevice()` - Method in class `java.awt.GraphicsEnvironment`

Returns the default screen `GraphicsDevice`.

`getDefaultSelection()` - Method in class `java.awt.JobAttributes`

Specifies whether, for jobs using these attributes, the application should print all pages, the range specified by the return value of `getPageRanges`, or the current selection.

`getDefaultSize()` - Method in class `javax.swing.plaf.basic.BasicComboBoxUI`

Return the default size of an empty combo box.

`getDefaultSocketFactory()` - Static method in class `java.rmi.server.RMISocketFactory`

Returns a reference to the default socket factory used by this RMI implementation.

`getDefaultSoundbank()` - Method in interface `javax.sound.midi.Synthesizer`

Obtains the default soundbank for the synthesizer, if one exists.

`getDefaultStream()` - Static method in class `java.rmi.server.LogStream`

Deprecated. *no replacement*

`getDefaultStyleContext()` - Static method in class `javax.swing.text.StyleContext`

Returns default `AttributeContext` shared by all documents that don't bother to define/supply their own context.

`getDefaultTextIconGap(AbstractButton)` - Method in class `javax.swing.plaf.basic.BasicButtonUI`

getDefaultToolkit() - Static method in class java.awt.Toolkit

Gets the default toolkit.

getDefaultTransactionIsolation() - Method in interface java.sql.DatabaseMetaData

What's the database's default transaction isolation level? The values are defined in java.sql.Connection.

getDefaultTransform() - Method in class java.awt.GraphicsConfiguration

Returns the default AffineTransform for this GraphicsConfiguration.

getDefaultTreeModel() - Static method in class javax.swing.JTree

Creates and returns a sample TreeModel.

getDefaultType() - Static method in class java.security.KeyStore

Returns the default keystore type as specified in the Java security properties file, or the string "jks" (acronym for "Java keystore") if no such property exists.

getDefaultUseCaches() - Method in class java.net.URLConnection

Returns the default value of a URLConnection's useCaches flag.

getDefaultValue() - Method in class javax.swing.text.html.CSS.Attribute

Fetch the default value for the attribute.

getDelay() - Method in class javax.swing.JMenu

Returns the suggested delay, in milliseconds, before submenus are popped up or down.

getDelay() - Method in class javax.swing.Timer

Returns the Timer's delay.

getDepth() - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns the depth of the tree rooted at this node -- the longest distance from this node to a leaf.

getDerefLinkFlag() - Method in class javax.naming.directory.SearchControls

Determines whether links will be dereferenced during the search.

getDescendantToggledPaths(TreePath) - Method in class javax.swing.JTree

Returns an Enumeration of TreePaths that have been expanded that are descendants of parent.

getDescent() - Method in class java.awt.FontMetrics

Determines the *font descent* of the Font described by this FontMetrics object.

getDescent() - Method in class java.awt.font.TextLayout

Returns the descent of this TextLayout.

getDescent() - Method in class java.awt.font.GraphicAttribute

Returns the descent of this GraphicAttribute.

getDescent() - Method in class java.awt.font.ImageGraphicAttribute

Returns the descent of this ImageGraphicAttribute
getDescent() - Method in class java.awt.font.LineMetrics
Returns the descent of the text.

getDescent() - Method in class java.awt.font.ShapeGraphicAttribute

Returns the descent of this ShapeGraphicAttribute.

getDescent(GlyphView) - Method in class javax.swing.text.GlyphView.GlyphPainter

getDescription() - Method in class javax.sound.sampled.Mixer.Info

Obtains the description of the mixer.

getDescription() - Method in interface javax.sound.midi.Soundbank

Obtains a textual description of the sound bank, suitable for display.

getDescription() - Method in class javax.sound.midi.MidiDevice.Info

Obtains the description of the device.

getDescription() - Method in class javax.swing.LookAndFeel

Return a one line description of this look and feel implementation, e.g.

getDescription() - Method in class javax.swing.ImageIcon

Gets the description of the image.

getDescription() - Method in class javax.swing.filechooser.FileFilter
The description of this filter.

getDescription() - Method in class javax.swing.event.HyperlinkEvent
Get the description of the link as a string.

getDescription() - Method in class javax.swing.plaf.basic.BasicFileChooserUI.AcceptAllFileFilter

getDescription() - Method in class javax.swing.plaf.metal.MetalLookAndFeel

getDescription() - Method in class javax.swing.plaf.multi.MultiLookAndFeel

getDescription(File) - Method in class javax.swing.JFileChooser
Returns the file description.

getDescription(File) - Method in class javax.swing.filechooser.FileView
A human readable description of the file.

getDescription(File) - Method in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

getDesignAxisDefaults() - Method in interface java.awt.font.MultipleMaster
Returns an array of default design values for each axis.

getDesignAxisNames() - Method in interface java.awt.font.MultipleMaster
Returns the name for each design axis.

getDesignAxisRanges() - Method in interface java.awt.font.MultipleMaster
Returns an array of design limits interleaved in the form [from->to] for each axis.

getDesktopColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getDesktopColor() - Method in class javax.swing.plaf.metal.MetalTheme

getDesktopIcon() - Method in class javax.swing.JInternalFrame
Returns the JDesktopIcon used when this JInternalFrame is iconified.

getDesktopIconBorder() - Static method in class javax.swing.plaf.metal.MetalBorders
Returns a border instance for a Desktop Icon

getDesktopManager() - Method in class javax.swing.JDesktopPane
Returns the DesktopManger that handles desktop-specific UI actions.

getDesktopManager() - Method in class javax.swing.plaf.basic.BasicInternalFrameUI
Returns the proper DesktopManager.

getDesktopPane() - Method in class javax.swing.JInternalFrame
Convenience method that searches the ancestor heirarchy for a JDesktop instance.

getDesktopPane() - Method in class javax.swing.JInternalFrame.JDesktopIcon
Convience method to ask the icon for the Desktop object it belongs to.

getDesktopPaneForComponent(Component) - Static method in class javax.swing.JOptionPane
Returns the specified component's desktop pane.

getDesktopProperty(String) - Method in class java.awt.Toolkit
obtain a value for the specified desktop property.

getDestination() - Method in class java.awt.JobAttributes
Specifies whether output will be to a printer or a file for jobs using these attributes.

getDeterminant() - Method in class java.awt.geom.AffineTransform
Returns the determinant of the matrix representation of the transform.

getDevice() - Method in class java.awt.GraphicsConfiguration
Returns the GraphicsDevice associated with this GraphicsConfiguration.

getDevice(MidiDevice.Info) - Method in class javax.sound.midi.spi.MidiDeviceProvider
Obtains an instance of the device represented by the info object.

getDeviceConfiguration() - Method in class java.awt.Graphics2D
Returns the device configuration associated with this Graphics2D.

getDeviceInfo() - Method in interface javax.sound.midi.MidiDevice
Obtains information about the device, including its Java class and Strings containing its name, vendor, and description.

getDeviceInfo() - Method in class javax.sound.midi.spi.MidiDeviceProvider
Obtains the set of info objects representing the device or devices provided by this

MidiDeviceProvider.

getDialog() - Method in class java.awt.JobAttributes

Returns whether, for jobs using these attributes, the user should see a print dialog in which to modify the print settings, and which type of print dialog should be displayed.

getDialogTitle() - Method in class javax.swing.JFileChooser

Gets the string that goes in the JFileChooser's titlebar.

getDialogTitle(JFileChooser) - Method in class javax.swing.plaf.FileChooserUI

getDialogTitle(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

Returns the title of this dialog

getDialogTitle(JFileChooser) - Method in class javax.swing.plaf.multi.MultiFileChooserUI

Call getDialogTitle on each UI handled by this MultiUI.

getDialogType() - Method in class javax.swing.JFileChooser

Returns the type of this dialog.

getDigestLength() - Method in class java.security.MessageDigest

Returns the length of the digest in bytes, or 0 if this operation is not supported by the provider and the implementation is not cloneable.

getDigit() - Method in class java.text.DecimalFormatSymbols

Gets the character used for a digit in a pattern.

getDimension(Object) - Method in class javax.swing.UIDefaults

If the value of key is a Dimension return it, otherwise return null.

getDimension(Object) - Static method in class javax.swing.UIManager

Returns a dimension from the defaults table.

getDirection() - Method in class javax.swing.text.DefaultStyledDocument.ElementSpec

Gets the direction.

getDirection() - Method in class javax.swing.plaf.basic.BasicArrowButton

getDirectories() - Method in class javax.swing.plaf.basic.BasicDirectoryModel

getDirectory() - Method in class java.awt.FileDialog

Gets the directory of this file dialog.

getDirectoryName() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getDirectoryName() - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getDirtyRegion(JComponent) - Method in class javax.swing.RepaintManager

Return the current dirty region for a component.

getDisabledIcon() - Method in class javax.swing.AbstractButton

Returns the icon used by the button when it's disabled.

getDisabledIcon() - Method in class javax.swing.JLabel

Returns the value of the disabledIcon property if it's been set, If it hasn't been set and the value of the icon property is an ImageIcon, we compute a "grayed out" version of the icon and update the disabledIcon property with that.

getDisabledIconAt(int) - Method in class javax.swing.JTabbedPane

Returns the tab disabled icon at index.

getDisabledSelectedIcon() - Method in class javax.swing.AbstractButton

Returns the icon used by the button when it's disabled and selected.

getDisabledTextColor() - Method in class javax.swing.text.JTextComponent

Fetches the current color used to render the selected text.

getDisabledTextColor() - Method in class javax.swing.plaf.metal.MetalToggleButtonUI

getDisabledTextColor() - Method in class javax.swing.plaf.metal.MetalRadioButtonUI

getDisabledTextColor() - Method in class javax.swing.plaf.metal.MetalButtonUI

getDismissDelay() - Method in class javax.swing.ToolTipManager

Returns the dismissal delay value.

[getDisplayCountry\(\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's country that is appropriate for display to the user.

[getDisplayCountry\(Locale\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's country that is appropriate for display to the user.

[getDisplayedMnemonic\(\)](#) - Method in class javax.swing.[JLabel](#)
Return the keycode that indicates a mnemonic key.

[getDisplayLanguage\(\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's language that is appropriate for display to the user.

[getDisplayLanguage\(Locale\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's language that is appropriate for display to the user.

[getDisplayName\(\)](#) - Method in class java.beans.[FeatureDescriptor](#)
Gets the localized display name of this feature.

[getDisplayName\(\)](#) - Method in class java.util.[TimeZone](#)
Returns a name of this time zone suitable for presentation to the user in the default locale.

[getDisplayName\(Locale\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale that is appropriate for display to the user.

[getDisplayName\(\)](#) - Method in class javax.swing.colorchooser.[AbstractColorChooserPanel](#)
Returns a string containing the display name of the panel.

[getDisplayName\(boolean, int\)](#) - Method in class java.util.[TimeZone](#)
Returns a name of this time zone suitable for presentation to the user in the default locale.

[getDisplayName\(boolean, int, Locale\)](#) - Method in class java.util.[TimeZone](#)
Returns a name of this time zone suitable for presentation to the user in the specified locale.

[getDisplayName\(Locale\)](#) - Method in class java.util.[TimeZone](#)
Returns a name of this time zone suitable for presentation to the user in the specified locale.

[getDisplayName\(Locale\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale that is appropriate for display to the user.

[getDisplaySize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxUI](#)

[getDisplayVariant\(\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's variant code that is appropriate for display to the user.

[getDisplayVariant\(Locale\)](#) - Method in class java.util.[Locale](#)
Returns a name for the locale's variant code that is appropriate for display to the user.

[getDivider\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)
Returns the divider between the top Components.

[getDividerBorderSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)
Deprecated. *As of Java 2 platform v1.3, instead set the border on the divider.*

[getDividerLocation\(\)](#) - Method in class javax.swing.[JSplitPane](#)
Returns the last value passed to setDividerLocation.

[getDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.[SplitPaneUI](#)
Returns the location of the divider.

[getDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)
Returns the location of the divider, which may differ from what the splitpane thinks the location of the divider is.

[getDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.multi.[MultiSplitPaneUI](#)
Call getDividerLocation on each UI handled by this MultiUI.

[getDividerSize\(\)](#) - Method in class javax.swing.[JSplitPane](#)
Returns the size of the divider.

[getDividerSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneDivider](#)
Returns the size of the divider, that is the width if the splitpane is HORIZONTAL_SPLIT, or the height of VERTICAL_SPLIT.

[getDivisionType\(\)](#) - Method in class javax.sound.midi.[Sequence](#)
Obtains the timing division type for this sequence.

[getDivisionType\(\)](#) - Method in class javax.sound.midi.[MidiFileFormat](#)
Obtains the timing division type for the MIDI file.

[getDockingColor\(\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

Gets the color displayed when over a docking area

[getDocument\(\)](#) - Method in interface [javax.swing.event.DocumentEvent](#)
Gets the document that sourced the change event.

[getDocument\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)
Fetches the model associated with the editor.

[getDocument\(\)](#) - Method in class [javax.swing.text.View](#)
Fetches the model associated with the view.

[getDocument\(\)](#) - Method in interface [javax.swing.text.Element](#)
Fetches the document associated with this element.

[getDocument\(\)](#) - Method in class [javax.swing.text.AbstractWriter](#)
Fetches the document.

[getDocument\(\)](#) - Method in class [javax.swing.text.AbstractDocument](#).[AbstractElement](#)
Retrieves the underlying model.

[getDocument\(\)](#) - Method in class [javax.swing.text.AbstractDocument](#).[DefaultDocumentEvent](#)
Gets the document that sourced the change event.

[getDocumentBase\(\)](#) - Method in class [java.applet.Applet](#)
Returns an absolute URL naming the directory of the document in which the applet is embedded.

[getDocumentBase\(\)](#) - Method in interface [java.applet.AppletStub](#)
Returns an absolute URL naming the directory of the document in which the applet is embedded.

[getDocumentProperties\(\)](#) - Method in class [javax.swing.text.AbstractDocument](#)
Support for managing a set of properties.

[getDoInput\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of this URLConnection's doInput flag.

[getDomainCombiner\(\)](#) - Method in class [java.security.AccessControlContext](#)
Get the DomainCombiner associated with this AccessControlContext.

[getDoOutput\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of this URLConnection's doOutput flag.

[getDot\(\)](#) - Method in class [javax.swing.event.CaretEvent](#)
Fetches the location of the caret.

[getDot\(\)](#) - Method in class [javax.swing.text.DefaultCaret](#)
Fetches the current position of the caret.

[getDot\(\)](#) - Method in interface [javax.swing.text.Caret](#)
Fetches the current position of the caret.

[getDouble\(int\)](#) - Method in interface [java.sql.CallableStatement](#)
Gets the value of a JDBC DOUBLE parameter as a double in the Java programming language.

[getDouble\(int\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a double in the Java programming language.

[getDouble\(Object\)](#) - Method in class [java.lang.reflect.Field](#)
Gets the value of a field as a double on the specified object.

[getDouble\(Object, int\)](#) - Static method in class [java.lang.reflect.Array](#)
Returns the value of the indexed component in the specified array object, as a double.

[getDouble\(String\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a double in the Java programming language.

[getDoubleBufferMaximumSize\(\)](#) - Method in class [javax.swing.RepaintManager](#)
Returns the maximum double buffer size.

[getDoubleParameter\(int\)](#) - Method in class [java.awt.image.renderable.ParameterBlock](#)
A convenience method to return a parameter as a double.

[getDragAction\(\)](#) - Method in class [java.awt.dnd.DragGestureEvent](#)
This method returns an int representing the action selected by the user.

[getDraggedColumn\(\)](#) - Method in class [javax.swing.table.JTableHeader](#)
Returns the dragged column, if and only if, a drag is in process, otherwise returns null.

[getDraggedDistance\(\)](#) - Method in class [javax.swing.table.JTableHeader](#)
Returns the column's horizontal distance from its original position, if and only if, a drag is in process.

[getDragMode\(\)](#) - Method in class [javax.swing.JDesktopPane](#)

Get the current "dragging style" used by the desktop pane.

[getDragOrigin\(\)](#) - Method in class java.awt.dnd.[DragGestureEvent](#)
This method returns a Point in the coordinates of the Component over which the drag originated.

[getDragSource\(\)](#) - Method in class java.awt.dnd.[DragGestureRecognizer](#)
This method returns the DragSource this DragGestureRecognizer will use in order to process the Drag and Drop operation.

[getDragSourceContext\(\)](#) - Method in class java.awt.dnd.[DragSourceContext](#)
This method returns the DragSource that instantiated this DragSourceContext.

[getDragSourceContext\(\)](#) - Method in class java.awt.dnd.[DragGestureEvent](#)
This method returns the DragSource.

[getDragSourceContext\(\)](#) - Method in class java.awt.dnd.[DragSourceEvent](#)
This method returns the DragSourceContext that originated the event.

[getDrawsLayeredHighlights\(\)](#) - Method in class javax.swing.text.[DefaultHighlighter](#)

[getDriver\(String\)](#) - Static method in class java.sql.[DriverManager](#)
Attempts to locate a driver that understands the given URL.

[getDriverMajorVersion\(\)](#) - Method in interface java.sql.[DatabaseMetaData](#)
What's this JDBC driver's major version number?

[getDriverMinorVersion\(\)](#) - Method in interface java.sql.[DatabaseMetaData](#)
What's this JDBC driver's minor version number?

[getDriverName\(\)](#) - Method in interface java.sql.[DatabaseMetaData](#)
What's the name of this JDBC driver?

[getDrivers\(\)](#) - Static method in class java.sql.[DriverManager](#)
Retrieves an Enumeration with all of the currently loaded JDBC drivers to which the current caller has access.

[getDriverVersion\(\)](#) - Method in interface java.sql.[DatabaseMetaData](#)
What's the version of this JDBC driver?

[getDropAction\(\)](#) - Method in class java.awt.dnd.[DropTargetDropEvent](#)
This method returns an int representing the action(s) supported by the source at the time of the drop.

[getDropAction\(\)](#) - Method in class java.awt.dnd.[DragSourceDragEvent](#)
This method returns an int representing the effective drop action which is the intersection of the user's selected action, and the source and target actions.

[getDropAction\(\)](#) - Method in class java.awt.dnd.[DragSourceDropEvent](#)
This method returns an int representing the action performed by the target on the subject of the drop.

[getDropAction\(\)](#) - Method in class java.awt.dnd.[DropTargetDragEvent](#)
This method returns an int representing the currently selected drop action.

[getDropSuccess\(\)](#) - Method in class java.awt.dnd.[DragSourceDropEvent](#)
This method returns a boolean indicating if the drop was a success.

[getDropTarget\(\)](#) - Method in class java.awt.[Component](#)
Get the DropTarget associated with this Component

[getDropTarget\(\)](#) - Method in class java.awt.dnd.[DropTargetContext](#)
This method returns the DropTarget associated with this DropTargetContext.

[getDropTargetContext\(\)](#) - Method in class java.awt.dnd.[DropTargetEvent](#)
This method returns the DropTargetContext associated with this DropTargetEvent.

[getDropTargetContext\(\)](#) - Method in class java.awt.dnd.[DropTarget](#)
This method returns the DropTargetContext associated with this DropTarget.

[getDSTSavings\(\)](#) - Method in class java.util.[SimpleTimeZone](#)
Returns the amount of time in ms that the clock is advanced during DST.

[getDTD\(String\)](#) - Static method in class javax.swing.text.html.parser.[DTD](#)
Get a DTD.

[getEarlyReflectionDelay\(\)](#) - Method in class javax.sound.sampled.[ReverbType](#)
Returns the early reflection delay time in microseconds.

[getEarlyReflectionIntensity\(\)](#) - Method in class javax.sound.sampled.[ReverbType](#)
Returns the early reflection intensity in microseconds.

[getEastPane\(\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

[getEchoChar\(\)](#) - Method in class java.awt.[TextField](#)
Gets the character that is to be used for echoing.

[getEchoChar\(\)](#) - Method in class javax.swing.[JPasswordField](#)
Returns the character to be used for echoing.

[getEdgeCondition\(\)](#) - Method in class java.awt.image.[ConvolveOp](#)
Returns the edge condition.

[getEdit\(\)](#) - Method in class javax.swing.event.[UndoableEditEvent](#)
Returns the edit value.

[getEditingColumn\(\)](#) - Method in class javax.swing.[JTable](#)
Returns the index of the column that contains the cell currently being edited.

[getEditingPath\(\)](#) - Method in class javax.swing.[JTree](#)
Returns the path to the element that is currently being edited.

[getEditingPath\(JTree\)](#) - Method in class javax.swing.plaf.[TreeUI](#)
Returns the path to the element that is being edited.

[getEditingPath\(JTree\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)
Returns the path to the element that is being edited.

[getEditingPath\(JTree\)](#) - Method in class javax.swing.plaf.multi.[MultiTreeUI](#)
Call [getEditingPath](#) on each UI handled by this MultiUI.

[getEditingRow\(\)](#) - Method in class javax.swing.[JTable](#)
Returns the index of the row that contains the cell currently being edited.

[getEditor\(\)](#) - Method in class javax.swing.[JComboBox](#)
Returns the editor used to paint and edit the selected item in the JComboBox field.

[getEditor\(ActionEvent\)](#) - Method in class javax.swing.text.[StyledEditorKit](#).[StyledTextAction](#)
Gets the target editor for an action.

[getEditorComponent\(\)](#) - Method in interface javax.swing.[ComboBoxEditor](#)
Return the component that should be added to the tree hierarchy for this editor

[getEditorComponent\(\)](#) - Method in class javax.swing.[JTable](#)
Returns the component that is handling the editing session.

[getEditorComponent\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxEditor](#)

[getEditorKit\(\)](#) - Method in class javax.swing.[JEditorPane](#)
Fetches the currently installed kit for handling content.

[getEditorKit\(JTextComponent\)](#) - Method in class javax.swing.plaf.[TextUI](#)
Fetches the binding of services that set a policy for the type of document being edited.

[getEditorKit\(JTextComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTextUI](#)
Fetches the EditorKit for the UI.

[getEditorKit\(JTextComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicEditorPaneUI](#)
Fetches the EditorKit for the UI.

[getEditorKit\(JTextComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTextPaneUI](#)
Fetches the EditorKit for the UI.

[getEditorKit\(JTextComponent\)](#) - Method in class javax.swing.plaf.multi.[MultiTextUI](#)
Call [getEditorKit](#) on each UI handled by this MultiUI.

[getEditorKitClassNameForContentType\(String\)](#) - Static method in class javax.swing.[JEditorPane](#)
Returns the currently registered EditorKit class name for the type type.

[getEditorKitForContentType\(String\)](#) - Method in class javax.swing.[JEditorPane](#)
Fetches the editor kit to use for the given type of content.

[getEditorSearchPath\(\)](#) - Static method in class java.beans.[PropertyEditorManager](#)
Gets the package names that will be searched for property editors.

[getElem\(int\)](#) - Method in class java.awt.image.[DataBuffer](#)
Returns the requested data array element from the first (default) bank as an integer.

[getElem\(int\)](#) - Method in class java.awt.image.[DataBufferUShort](#)
Returns the requested data array element from the first (default) bank.

[getElem\(int\)](#) - Method in class java.awt.image.[DataBufferByte](#)
Returns the requested data array element from the first (default) bank.

[getElem\(int\)](#) - Method in class java.awt.image.[DataBufferInt](#)

Returns the requested data array element from the first (default) bank.

getElem(int) - Method in class java.awt.image.DataBufferShort

Returns the requested data array element from the first (default) bank.

getElem(int, int) - Method in class java.awt.image.DataBuffer

Returns the requested data array element from the specified bank as an integer.

getElem(int, int) - Method in class java.awt.image.DataBufferUShort

Returns the requested data array element from the specified bank

getElem(int, int) - Method in class java.awt.image.DataBufferByte

Returns the requested data array element from the specified bank

getElem(int, int) - Method in class java.awt.image.DataBufferInt

Returns the requested data array element from the specified bank

getElem(int, int) - Method in class java.awt.image.DataBufferShort

Returns the requested data array element from the specified bank

getElemDouble(int) - Method in class java.awt.image.DataBuffer

Returns the requested data array element from the first (default) bank as a double.

getElemDouble(int, int) - Method in class java.awt.image.DataBuffer

Returns the requested data array element from the specified bank as a double.

getElement() - Method in interface javax.swing.event.DocumentEvent.ElementChange

Returns the element represented.

getElement() - Method in class javax.swing.text.View

Fetches the structural portion of the subject that this view is mapped to.

getElement() - Method in class javax.swing.text.AbstractDocument.ElementEdit

Returns the underlying element.

getElement() - Method in class javax.swing.text.html.parser.TagElement

getElement(Element, Object, Object) - Method in class javax.swing.text.html.HTMLDocument

Returns the child element of e that contains the attribute, attribute with value value, or null if one isn't found.

getElement(int) - Method in interface javax.swing.text.Element

Fetches the child element at the given index.

getElement(int) - Method in class javax.swing.text.AbstractDocument.AbstractElement

Gets a child element.

getElement(int) - Method in class javax.swing.text.AbstractDocument.BranchElement

Gets a child element.

getElement(int) - Method in class javax.swing.text.AbstractDocument.LeafElement

Gets a child element.

getElement(int) - Method in class javax.swing.text.html.parser.DTD

Get an element by index.

getElement(String) - Method in class javax.swing.text.html.HTMLDocument

Fetches the element that has the given id attribute.

getElement(String) - Method in class javax.swing.text.html.parser.DTD

Get an element by name.

getElementAt(int) - Method in interface javax.swing.ListModel

Returns the value at the specified index.

getElementAt(int) - Method in class javax.swing.DefaultComboBoxModel

getElementAt(int) - Method in class javax.swing.DefaultListModel

Returns the component at the specified index.

getElementAt(int) - Method in class javax.swing.plaf.basic.BasicDirectoryModel

getElementAt(int) - Method in class javax.swing.plaf.metal.MetalFileChooserUI.DirectoryComboBoxModel

getElementAt(int) - Method in class javax.swing.plaf.metal.MetalFileChooserUI.FilterComboBoxModel

getElementCount() - Method in interface javax.swing.text.Element

Gets the number of child elements contained by this element.

getElementCount() - Method in class javax.swing.text.AbstractDocument.AbstractElement

Gets the number of children for the element.

[getElementCount\(\)](#) - Method in class javax.swing.text.[AbstractDocument.BranchElement](#)
Gets the number of children for the element.

[getElementCount\(\)](#) - Method in class javax.swing.text.[AbstractDocument.LeafElement](#)
Returns the number of child elements.

[getElementIndex\(int\)](#) - Method in interface javax.swing.text.[Element](#)
Gets the child element index closest to the given offset.

[getElementIndex\(int\)](#) - Method in class javax.swing.text.[AbstractDocument.AbstractElement](#)
Gets the child element index closest to the given model offset.

[getElementIndex\(int\)](#) - Method in class javax.swing.text.[AbstractDocument.BranchElement](#)
Gets the child element index closest to the given model offset.

[getElementIndex\(int\)](#) - Method in class javax.swing.text.[AbstractDocument.LeafElement](#)
Gets the child element index closest to the given model offset.

[getElementIterator\(\)](#) - Method in class javax.swing.text.[AbstractWriter](#)
Fetches the ElementIterator.

[getElements\(\)](#) - Method in class javax.swing.[ButtonGroup](#)
Return all the buttons that are participating in this group.

[getElements\(Vector\)](#) - Method in class javax.swing.text.html.parser.[ContentModel](#)
Update elemVec with the list of elements that are part of the this contentModel.

[getElementsAt\(HTMLDocument, int\)](#) - Method in class javax.swing.text.html.[HTMLEditorKit.HTMLTextAction](#)
Returns an array of the Elements that contain offset.

[getElemFloat\(int\)](#) - Method in class java.awt.image.[DataBuffer](#)
Returns the requested data array element from the first (default) bank as a float.

[getElemFloat\(int, int\)](#) - Method in class java.awt.image.[DataBuffer](#)
Returns the requested data array element from the specified bank as a float.

[getEmptySet\(\)](#) - Method in class javax.swing.text.[StyleContext](#)
Fetches an empty AttributeSet.

[getEmptySet\(\)](#) - Method in interface javax.swing.text.[AbstractDocument.AttributeContext](#)
Fetches an empty AttributeSet.

[getEncoded\(\)](#) - Method in interface java.security.[Key](#)
Returns the key in its primary encoding format, or null if this key does not support encoding.

[getEncoded\(\)](#) - Method in class java.security.[AlgorithmParameters](#)
Returns the parameters in their primary encoding format.

[getEncoded\(\)](#) - Method in class java.security.cert.[Certificate](#)
Returns the encoded form of this certificate.

[getEncoded\(\)](#) - Method in class java.security.cert.[X509CRLEntry](#)
Returns the ASN.1 DER-encoded form of this CRL Entry, that is the inner SEQUENCE.

[getEncoded\(\)](#) - Method in class java.security.cert.[X509CRL](#)
Returns the ASN.1 DER-encoded form of this CRL.

[getEncoded\(\)](#) - Method in class java.security.spec.[EncodedKeySpec](#)
Returns the encoded key.

[getEncoded\(\)](#) - Method in class java.security.spec.[PKCS8EncodedKeySpec](#)
Returns the key bytes, encoded according to the PKCS #8 standard.

[getEncoded\(\)](#) - Method in class java.security.spec.[X509EncodedKeySpec](#)
Returns the key bytes, encoded according to the X.509 standard.

[getEncoded\(String\)](#) - Method in class java.security.[AlgorithmParameters](#)
Returns the parameters encoded in the specified scheme.

[getEncodedValue\(\)](#) - Method in interface javax.naming.ldap.[Control](#)
Retrieves the ASN.1 BER encoded value of the LDAP control.

[getEncodedValue\(\)](#) - Method in interface javax.naming.ldap.[ExtendedRequest](#)
Retrieves the ASN.1 BER encoded value of the LDAP extended operation request.

[getEncodedValue\(\)](#) - Method in interface javax.naming.ldap.[ExtendedResponse](#)
Retrieves the ASN.1 BER encoded value of the LDAP extended operation response.

[getEncoding\(\)](#) - Method in class java.io.[InputStreamReader](#)
Returns the canonical name of the character encoding being used by this stream.

[getEncoding\(\)](#) - Method in class java.io.[OutputStreamWriter](#)

Returns the canonical name of the character encoding being used by this stream.

[getEncoding\(\)](#) - Method in class `javax.sound.sampled.AudioFormat`
Obtains the type of encoding for sounds in this format.

[getEndCap\(\)](#) - Method in class `java.awt.BasicStroke`
Returns the end cap style.

[getEndIndex\(\)](#) - Method in interface `java.text.CharacterIterator`
Returns the end index of the text.

[getEndIndex\(\)](#) - Method in class `java.text.StringCharacterIterator`
Implements `CharacterIterator.getEndIndex()` for `String`.

[getEndIndex\(\)](#) - Method in class `java.text.FieldPosition`
Retrieves the index of the character following the last character in the requested field.

[getEndIndex\(\)](#) - Method in class `javax.accessibility.AccessibleHyperlink`
Gets the index with the hypertext document at which this link ends

[getEndIndex\(\)](#) - Method in class `javax.swing.JEditorPane.AccessibleHypertextSupport.HTMLLink`
Get the index with the hypertext document at which this link ends

[getEndIndex\(\)](#) - Method in class `javax.swing.text.Segment`
Returns the end index of the text.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.View`
Fetches the portion of the model that this view is responsible for.

[getEndOffset\(\)](#) - Method in interface `javax.swing.text.Element`
Fetches the offset from the beginning of the document that this element ends at.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.GlyphView`
Fetches the portion of the model that this view is responsible for.

[getEndOffset\(\)](#) - Method in interface `javax.swing.text.Highlighter.Highlight`
Gets the ending model offset for the highlight.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.AbstractWriter`
Returns the last offset to be output.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.AbstractDocument.AbstractElement`
Gets the ending offset in the model for the element.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.AbstractDocument.BranchElement`
Gets the ending offset in the model for the element.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.AbstractDocument.LeafElement`
Gets the ending offset in the model for the element.

[getEndOffset\(\)](#) - Method in class `javax.swing.text.html.HTMLDocument.Iterator`
End of the range for which the current occurrence of the tag is defined and has the same attributes.

[getEndPoint\(\)](#) - Method in class `java.awt.geom.Arc2D`
Returns the ending point of the arc.

[getEndPosition\(\)](#) - Method in interface `javax.swing.text.Document`
Returns a position that represents the end of the document.

[getEndPosition\(\)](#) - Method in class `javax.swing.text.AbstractDocument`
Returns a position that represents the end of the document.

[getEntity\(int\)](#) - Method in class `javax.swing.text.html.parser.DTD`
Get a character entity.

[getEntity\(String\)](#) - Method in class `javax.swing.text.html.parser.DTD`
Get an entity by name.

[getEntries\(\)](#) - Method in class `java.util.jar.Manifest`
Returns a Map of the entries contained in this Manifest.

[getEntry\(String\)](#) - Method in class `java.util.jar.JarFile`
Returns the ZipEntry for the given entry name or null if not found.

[getEntry\(String\)](#) - Method in class `java.util.zip.ZipFile`
Returns the zip file entry for the specified name, or null if not found.

[getEntryName\(\)](#) - Method in class `java.net.JarURLConnection`
Return the entry name for this connection.

[getenv\(String\)](#) - Static method in class `java.lang.System`
Deprecated. *The preferred way to extract system-dependent information is the system properties*

of the `java.lang.System.getProperty` methods and the corresponding `getTypeName` methods of the `Boolean`, `Integer`, and `Long` primitive types. For example:

```
String classPath = System.getProperty("java.class.path", ".");
```

```
if (Boolean.getBoolean("myapp.exper.mode"))
    enableExpertCommands();
```

`getEnvironment()` - Method in class `javax.naming.InitialContext`

`getEnvironment()` - Method in class `javax.naming.CannotProceedException`

Retrieves the environment that was in effect when this exception was created.

`getEnvironment()` - Method in interface `javax.naming.Context`

Retrieves the environment in effect for this context.

`getEras()` - Method in class `java.text.DateFormatSymbols`

Gets era strings.

`getErrorCode()` - Method in class `java.sql.SQLException`

Retrieves the vendor-specific exception code for this `SQLException` object.

`getErrorIndex()` - Method in class `java.text.ParsePosition`

Retrieve the index at which an error occurred, or -1 if the error index has not been set.

`getErrorOffset()` - Method in class `java.text.ParseException`

Returns the position where the error was found.

`getErrorsAny()` - Method in class `java.awt.MediaTracker`

Returns a list of all media that have encountered an error.

`getErrorsID(int)` - Method in class `java.awt.MediaTracker`

Returns a list of media with the specified ID that have encountered an error.

`getErrorStream()` - Method in class `java.lang.Process`

Gets the error stream of the subprocess.

`getErrorStream()` - Method in class `java.net.HttpURLConnection`

Returns the error stream if the connection failed but the server sent useful data nonetheless.

`getEtchedBorderUIResource()` - Static method in class `javax.swing.plaf.BorderUIResource`

`getEtchedInsets()` - Static method in class `javax.swing.plaf.basic.BasicGraphicsUtils`

Returns the amount of space taken up by a border drawn by `drawEtchedRect()`

`getEtchType()` - Method in class `javax.swing.border.EtchedBorder`

Returns which etch-type is set on the etched border.

`getEventContext()` - Method in class `javax.naming.event.NamingEvent`

Retrieves the event source that fired this event.

`getEventContext()` - Method in class `javax.naming.event.NamingExceptionEvent`

Retrieves the `EventContext` that fired this event.

`getEventSetDescriptors()` - Method in interface `java.beans.BeanInfo`

Gets the beans `EventSetDescriptors`.

`getEventSetDescriptors()` - Method in class `java.beans.SimpleBeanInfo`

Deny knowledge of event sets.

`getEventType()` - Method in class `javax.swing.event.HyperlinkEvent`

Gets the type of event.

`getException()` - Method in class `java.awt.event.InvocationEvent`

Returns any `Exception` caught while executing the `Runnable`'s `run()` method.

`getException()` - Method in class `java.lang.ExceptionInInitializerError`

Returns the exception that occurred during a static initialization that caused this `Error` to be created.

`getException()` - Method in class `java.lang.ClassNotFoundException`

Returns the exception that was raised if an error occurred while attempting to load the class.

`getException()` - Method in class `java.security.PrivilegedActionException`

Returns the exception thrown by the privileged computation that resulted in this `PrivilegedActionException`.

`getException()` - Method in class `javax.naming.event.NamingExceptionEvent`
Retrieves the exception that was thrown.

`getException()` - Method in interface `javax.naming ldap.UnsolicitedNotification`
Retrieves the exception as constructed using information sent by the server.

`getExceptionTypes()` - Method in class `java.lang.reflect.Method`
Returns an array of `Class` objects that represent the types of the exceptions declared to be thrown by the underlying method represented by this `Method` object.

`getExceptionTypes()` - Method in class `java.lang.reflect.Constructor`
Returns an array of `Class` objects that represent the types of of exceptions declared to be thrown by the underlying constructor represented by this `Constructor` object.

`getExpandedDescendants(TreePath)` - Method in class `javax.swing.JTree`
Returns an `Enumeration` of the descendants of the path parent that are currently expanded.

`getExpandedIcon()` - Method in class `javax.swing.plaf.basic.BasicTreeUI`

`getExpandedState(TreePath)` - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns true if the path is expanded, and visible.

`getExpandedState(TreePath)` - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns true if the path is expanded, and visible.

`getExpandedState(TreePath)` - Method in class `javax.swing.tree.FixedHeightLayoutCache`
Returns true if the path is expanded, and visible.

`getExpandsSelectedPaths()` - Method in class `javax.swing.JTree`
Returns the `expandsSelectedPaths` property.

`getExpiration()` - Method in class `java.net.URLConnection`
Returns the value of the `expires` header field.

`getExplanation()` - Method in class `javax.naming.NamingException`
Retrieves the explanation associated with this exception.

`getExportedKeys(String, String, String)` - Method in interface `java.sql.DatabaseMetaData`
Gets a description of the foreign key columns that reference a table's primary key columns (the foreign keys exported by a table).

`getExtension()` - Method in class `javax.sound.sampled.AudioFileFormat.Type`
Obtains the common file name extension for this file type.

`getExtensionValue(String)` - Method in interface `java.security.cert.X509Extension`
Gets the DER-encoded OCTET string for the extension value (*extnValue*) identified by the passed-in oid `String`.

`getExtent()` - Method in class `javax.swing.DefaultBoundedRangeModel`
Return the model's extent.

`getExtent()` - Method in interface `javax.swing.BoundedRangeModel`
Returns the model's extent, the length of the inner range that begins at the model's value.

`getExtent()` - Method in class `javax.swing.JSlider`
Returns the "extent" -- the range of values "covered" by the knob.

`getExtentSize()` - Method in class `javax.swing.JViewport`
Returns the size of the visible part of the view in view coordinates.

`getExtra()` - Method in class `java.util.zip.ZipEntry`
Returns the extra field data for the entry, or null if none.

`getExtraNameCharacters()` - Method in interface `java.sql.DatabaseMetaData`
Gets all the "extra" characters that can be used in unquoted identifier names (those beyond a-z, A-Z, 0-9 and `_`).

`getFactoryClassLocation()` - Method in class `javax.naming.Reference`
Retrieves the location of the factory of the object to which this reference refers.

`getFactoryClassName()` - Method in class `javax.naming.Reference`
Retrieves the class name of the factory of the object to which this reference refers.

`getFailureHandler()` - Static method in class `java.rmi.server.RMISocketFactory`
Returns the handler for socket creation failure set by the `setFailureHandler` method.

`getFamily()` - Method in class `java.awt.Font`
Returns the family name of this `Font`.

getFamily(Locale) - Method in class java.awt.Font
Returns the family name of this Font, localized for the specified locale.

getFD() - Method in class java.io.FileOutputStream
Returns the file descriptor associated with this stream.

getFD() - Method in class java.io.RandomAccessFile
Returns the opaque file descriptor object associated with this stream.

getFD() - Method in class java.io.FileInputStream
Returns the FileDescriptor object that represents the connection to the actual file in the file system being used by this FileInputStream.

getFetchDirection() - Method in interface java.sql.Statement
Retrieves the direction for fetching rows from database tables that is the default for result sets generated from this Statement object.

getFetchDirection() - Method in interface java.sql.ResultSet
Returns the fetch direction for this ResultSet object.

getFetchSize() - Method in interface java.sql.Statement
Retrieves the number of result set rows that is the default fetch size for result sets generated from this Statement object.

getFetchSize() - Method in interface java.sql.ResultSet
Returns the fetch size for this ResultSet object.

getField() - Method in class java.text.FieldPosition
Retrieves the field identifier.

getField(String) - Method in class java.io.ObjectStreamClass
Get the field of this class by name.

getField(String) - Method in class java.lang.Class
Returns a Field object that reflects the specified public member field of the class or interface represented by this Class object.

getFields() - Method in class java.io.ObjectStreamClass
Return an array of the fields of this serializable class.

getFields() - Method in class java.lang.Class
Returns an array containing Field objects reflecting all the accessible public fields of the class or interface represented by this Class object.

getFile() - Method in class java.awt.FileDialog
Gets the selected file of this file dialog.

getFile() - Method in class java.net.URL
Returns the file name of this URL.

getFileChooser() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getFileChooserDetailViewIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getFileChooserHomeFolderIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getFileChooserListViewIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getFileChooserNewFolderIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getFileChooserUpFolderIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getFileDescriptor() - Method in class java.net.SocketImpl
Returns the value of this socket's fd field.

getFileDescriptor() - Method in class java.net.DatagramSocketImpl
Gets the datagram socket file descriptor.

getFileFilter() - Method in class javax.swing.JFileChooser
Returns the currently selected file filter.

getFileName() - Method in class java.awt.JobAttributes
Specifies the file name for the output file for jobs using these attributes.

getFileName() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getFileName() - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getFilenameFilter() - Method in class java.awt.FileDialog
Determines this file dialog's filename filter.

getFileNameMap() - Static method in class java.net.URLConnection
Loads filename map (a mimetable) from a data file.

getFilePointer() - Method in class java.io.RandomAccessFile
Returns the current offset in this file.

getFiles() - Method in class javax.swing.plaf.basic.BasicDirectoryModel

getFiles(File, boolean) - Method in class javax.swing.filechooser.FileSystemView
gets the list of shown (i.e.

getFileSelectionMode() - Method in class javax.swing.JFileChooser
Returns the current file-selection mode.

getFileSystemView() - Method in class javax.swing.JFileChooser
Returns the file system view.

getFileSystemView() - Static method in class javax.swing.filechooser.FileSystemView

getFileView() - Method in class javax.swing.JFileChooser
Returns the current file view.

getFileView(JFileChooser) - Method in class javax.swing.plaf.FileChooserUI

getFileView(JFileChooser) - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getFileView(JFileChooser) - Method in class javax.swing.plaf.multi.MultiFileChooserUI
Call getFileView on each UI handled by this MultiUI.

getFilterInstance(ImageConsumer) - Method in class java.awt.image.ImageFilter
Returns a unique instance of an ImageFilter object which will actually perform the filtering for the specified ImageConsumer.

getFirst() - Method in class java.util.LinkedList
Returns the first element in this list.

getFirstChild() - Method in class javax.swing.tree.DefaultMutableTreeNode
Returns this node's first child.

getFirstColumn() - Method in interface javax.accessibility.AccessibleTableModelChange
Returns the first column that changed.

getFirstColumn() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableModelChange

getFirstComponent(Container) - Method in class javax.swing.DefaultFocusManager
Return the first component that should receive the focus

getFirstDayOfWeek() - Method in class java.util.Calendar
Gets what the first day of the week is; e.g., Sunday in US, Monday in France.

getFirstIndex() - Method in class javax.swing.event.ListSelectionEvent
Returns the index of the first row whose selection may have changed.

getFirstLeaf() - Method in class javax.swing.tree.DefaultMutableTreeNode
Finds and returns the first leaf that is a descendant of this node -- either this node or its first child's first leaf.

getFirstLineIndent(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Gets the first line indent setting.

getFirstRow() - Method in interface javax.accessibility.AccessibleTableModelChange
Returns the first row that changed.

getFirstRow() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableModelChange

getFirstRow() - Method in class javax.swing.event.TableModelEvent
Returns the first row that changed.

getFirstVisibleIndex() - Method in class javax.swing.JList
Returns the index of the cell in the upper left corner of the JList or -1 if nothing is visible or the list is empty.

[getFixedCellHeight\(\)](#) - Method in class `javax.swing.JList`
Returns the fixed cell height value -- the value specified by setting the `fixedCellHeight` property, rather than that calculated from the list elements.

[getFixedCellWidth\(\)](#) - Method in class `javax.swing.JList`
Returns the fixed cell width value -- the value specified by setting the `fixedCellWidth` property, rather than that calculated from the list elements.

[getFlatness\(\)](#) - Method in class `java.awt.geom.QuadCurve2D`
Returns the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of this `QuadCurve2D`.

[getFlatness\(\)](#) - Method in class `java.awt.geom.CubicCurve2D`
Returns the flatness of this curve.

[getFlatness\(\)](#) - Method in class `java.awt.geom.FlatteningPathIterator`
Returns the flatness of this iterator.

[getFlatness\(double\[\], int\)](#) - Static method in class `java.awt.geom.QuadCurve2D`
Returns the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of the quadratic curve specified by the controlpoints stored in the indicated array at the indicated index.

[getFlatness\(double\[\], int\)](#) - Static method in class `java.awt.geom.CubicCurve2D`
Returns the flatness of the cubic curve specified by the controlpoints stored in the indicated array at the indicated index.

[getFlatness\(double, double, double, double, double, double\)](#) - Static method in class `java.awt.geom.QuadCurve2D`
Returns the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of the quadratic curve specified by the indicated controlpoints.

[getFlatness\(double, double, double, double, double, double, double, double\)](#) - Static method in class `java.awt.geom.CubicCurve2D`
Returns the flatness of the cubic curve specified by the indicated controlpoints.

[getFlatnessSq\(\)](#) - Method in class `java.awt.geom.QuadCurve2D`
Returns the square of the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of this `QuadCurve2D`.

[getFlatnessSq\(\)](#) - Method in class `java.awt.geom.CubicCurve2D`
Returns the square of the flatness of this curve.

[getFlatnessSq\(double\[\], int\)](#) - Static method in class `java.awt.geom.QuadCurve2D`
Returns the square of the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of the quadratic curve specified by the controlpoints stored in the indicated array at the indicated index.

[getFlatnessSq\(double\[\], int\)](#) - Static method in class `java.awt.geom.CubicCurve2D`
Returns the square of the flatness of the cubic curve specified by the controlpoints stored in the indicated array at the indicated index.

[getFlatnessSq\(double, double, double, double, double, double\)](#) - Static method in class `java.awt.geom.QuadCurve2D`
Returns the square of the flatness, or maximum distance of a controlpoint from the line connecting the endpoints, of the quadratic curve specified by the indicated controlpoints.

[getFlatnessSq\(double, double, double, double, double, double, double, double\)](#) - Static method in class `java.awt.geom.CubicCurve2D`
Returns the square of the flatness of the cubic curve specified by the indicated controlpoints.

[getFlavorMap\(\)](#) - Method in class `java.awt.dnd.DragSource`
This method returns the `FlavorMap` for this `DragSource`.

[getFlavorMap\(\)](#) - Method in class `java.awt.dnd.DropTarget`
This method returns the `FlavorMap` associated with this `DropTarget`.

[getFlavorsForNatives\(String\[\]\)](#) - Method in class `java.awt.datatransfer.SystemFlavorMap`
map natives to corresponding flavors

[getFlavorsForNatives\(String\[\]\)](#) - Method in interface `java.awt.datatransfer.FlavorMap`
map natives to corresponding flavors

[getFloat\(int\)](#) - Method in interface `java.sql.CallableStatement`
Gets the value of a JDBC FLOAT parameter as a float in the Java programming language.

[getFloat\(int\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this [ResultSet](#) object as a float in the Java programming language.

[getFloat\(Object\)](#) - Method in class [java.lang.reflect.Field](#)
Gets the value of a field as a float on the specified object.

[getFloat\(Object, int\)](#) - Static method in class [java.lang.reflect.Array](#)
Returns the value of the indexed component in the specified array object, as a float.

[getFloat\(String\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this [ResultSet](#) object as a float in the Java programming language.

[getFloatingColor\(\)](#) - Method in class [javax.swing.plaf.basic.BasicToolBarUI](#)
Gets the color displayed when over a floating area

[getFloatParameter\(int\)](#) - Method in class [java.awt.image.renderable.ParameterBlock](#)
A convenience method to return a parameter as a float.

[getFlowAxis\(\)](#) - Method in class [javax.swing.text.FlowView](#)
Fetch the axis along which views should be flowed.

[getFlowSpan\(int\)](#) - Method in class [javax.swing.text.FlowView](#)
Fetch the constraining span to flow against for the given child index.

[getFlowSpan\(int\)](#) - Method in class [javax.swing.text.ParagraphView](#)
Fetch the constraining span to flow against for the given child index.

[getFlowStart\(int\)](#) - Method in class [javax.swing.text.FlowView](#)
Fetch the location along the flow axis that the flow span will start at.

[getFlowStart\(int\)](#) - Method in class [javax.swing.text.ParagraphView](#)
Fetch the location along the flow axis that the flow span will start at.

[getFocusAccelerator\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)
Returns the key accelerator that will cause the receiving text component to get the focus.

[getFocusColor\(\)](#) - Method in class [javax.swing.plaf.basic.BasicSliderUI](#)

[getFocusColor\(\)](#) - Method in class [javax.swing.plaf.metal.MetalToggleButtonUI](#)

[getFocusColor\(\)](#) - Method in class [javax.swing.plaf.metal.MetalRadioButtonUI](#)

[getFocusColor\(\)](#) - Static method in class [javax.swing.plaf.metal.MetalLookAndFeel](#)

[getFocusColor\(\)](#) - Method in class [javax.swing.plaf.metal.MetalButtonUI](#)

[getFocusColor\(\)](#) - Method in class [javax.swing.plaf.metal.MetalTheme](#)

[getFocusedComponent\(\)](#) - Method in class [javax.swing.text.TextAction](#)
Fetches the text component that currently has focus.

[getFocusOwner\(\)](#) - Method in class [java.awt.Window](#)
Returns the child component of this [Window](#) which has focus if and only if this [Window](#) is active.

[getFocusOwner\(\)](#) - Method in class [javax.swing.JInternalFrame](#)
If this [JInternalFrame](#) is active, return the child which has focus.

[getFollowRedirects\(\)](#) - Static method in class [java.net.HttpURLConnection](#)
Returns a boolean indicating whether or not HTTP redirects (3xx) should be automatically followed.

[getFont\(\)](#) - Method in class [java.awt.Component](#)
Gets the font of this component.

[getFont\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)
Get the Font of this object.

[getFont\(\)](#) - Method in class [java.awt.MenuComponent](#)
Gets the font used for this menu component.

[getFont\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)
Get the Font of this object.

[getFont\(\)](#) - Method in interface [java.awt.MenuContainer](#)

getFont() - Method in class [java.awt.FontMetrics](#)
Gets the Font described by this FontMetrics object.

getFont() - Method in class [java.awt.Graphics](#)
Gets the current font.

getFont() - Method in class [java.awt.List.AccessibleAWTList.AccessibleAWTListChild](#)
Get the Font of this object.

getFont() - Method in class [java.awt.font.GlyphVector](#)
Returns the Font associated with this GlyphVector.

getFont() - Method in interface [javax.accessibility.AccessibleComponent](#)
Gets the Font of this object.

getFont() - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

getFont() - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

getFont() - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)
Gets the Font of this object.

getFont() - Method in class [javax.swing.DebugGraphics](#)
Returns the Font used for text drawing operations.

getFont() - Method in class
[javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

getFont() - Method in class [javax.swing.text.GlyphView](#)
Fetch the font that the glyphs should be based upon.

getFont() - Method in class [javax.swing.text.LabelView](#)
Fetch the font that the glyphs should be based upon.

getFont() - Method in class [javax.swing.tree.DefaultTreeCellEditor](#)
Gets the font used for editing.

getFont() - Method in class [javax.swing.tree.DefaultTreeCellEditor.DefaultTextField](#)

getFont(AttributeSet) - Method in class [javax.swing.text.StyleContext](#)
Gets the font from an attribute set.

getFont(AttributeSet) - Method in interface [javax.swing.text.StyledDocument](#)
Takes a set of attributes and turn it into a font specification.

getFont(AttributeSet) - Method in class [javax.swing.text.DefaultStyledDocument](#)
Gets the font from an attribute set.

getFont(AttributeSet) - Method in class [javax.swing.text.html.StyleSheet](#)
Fetches the font to use for the given set of attributes.

getFont(Component) - Method in class [javax.swing.border.TitledBorder](#)

getFont(Map) - Static method in class [java.awt.Font](#)
Returns a Font appropriate to this attribute set.

getFont(Object) - Method in class [javax.swing.UIManager](#)
If the value of key is a Font return it, otherwise return null.

getFont(Object) - Static method in class [javax.swing.UIManager](#)
Returns a drawing font from the defaults table.

getFont(String) - Static method in class [java.awt.Font](#)
Returns a Font object from the system properties list.

getFont(String, Font) - Static method in class [java.awt.Font](#)
Gets the specified Font from the system properties list.

getFont(String, int, int) - Method in class [javax.swing.text.StyleContext](#)
Gets a new font.

getFontFamily(AttributeSet) - Static method in class [javax.swing.text.StyleConstants](#)
Gets the font family setting from the attribute list.

getFontList() - Method in class [java.awt.Toolkit](#)
Deprecated. *see* [GraphicsEnvironment.getAvailableFontFamilyNames\(\)](#)

getFontMetrics() - Method in class [java.awt.Graphics](#)

Gets the font metrics of the current font.

getFontMetrics() - Method in class javax.swing.DebugGraphics
Overrides Graphics.getFontMetrics.

getFontMetrics() - Method in class javax.swing.text.LabelView
Deprecated. *FontMetrics are not used for glyph rendering when running in the Java2 SDK.*

getFontMetrics() - Method in class javax.swing.text.FieldView
Fetches the font metrics associated with the component hosting this view.

getFontMetrics() - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getFontMetrics(Font) - Method in class java.awt.Component
Gets the font metrics for the specified font.

getFontMetrics(Font) - Method in class java.awt.Component.AccessibleAWTComponent
Get the FontMetrics of this object.

getFontMetrics(Font) - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
Get the FontMetrics of this object.

getFontMetrics(Font) - Method in class java.awt.Graphics
Gets the font metrics for the specified font.

getFontMetrics(Font) - Method in class java.awt.Toolkit
Deprecated. *This returns integer metrics for the default screen.*

getFontMetrics(Font) - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild
Get the FontMetrics of this object.

getFontMetrics(Font) - Method in interface javax.accessibility.AccessibleComponent
Gets the FontMetrics of this object.

getFontMetrics(Font) - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getFontMetrics(Font) - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

getFontMetrics(Font) - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell
Gets the FontMetrics of this object.

getFontMetrics(Font) - Method in class javax.swing.DebugGraphics
Overrides Graphics.getFontMetrics.

getFontMetrics(Font) - Method in class javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getFontMetrics(Font) - Method in class javax.swing.text.StyleContext
Returns font metrics for a font.

getFontName() - Method in class java.awt.Font
Returns the font face name of this Font.

getFontName(Locale) - Method in class java.awt.Font
Returns the font face name of the Font, localized for the specified locale.

getFontPeer(String, int) - Method in class java.awt.Toolkit
Deprecated. *see java.awt.GraphicsEnvironment#getAllFonts*

getFontRenderContext() - Method in class java.awt.Graphics2D
Get the rendering context of the Font within this Graphics2D context.

getFontRenderContext() - Method in class java.awt.font.GlyphVector
Returns the FontRenderContext associated with this GlyphVector.

getFontSize(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Gets the font size setting from the attribute list.

getFontTable(int) - Method in interface java.awt.font.OpenType
Returns the table as an array of bytes for a specified tag.

getFontTable(int, int, int) - Method in interface java.awt.font.OpenType
Returns a subset of the table as an array of bytes for a specified tag.

getFontTable(String) - Method in interface java.awt.font.OpenType
Returns the table as an array of bytes for a specified tag.

getFontTable(String, int, int) - Method in interface java.awt.font.OpenType
Returns a subset of the table as an array of bytes for a specified tag.

getFontTableSize(int) - Method in interface java.awt.font.OpenType

Returns the size of the table for a specified tag.

[getFontTableSize\(String\)](#) - Method in interface [java.awt.font.OpenType](#)
Returns the size of the table for a specified tag.

[getForeground\(\)](#) - Method in class [java.awt.Component](#)
Gets the foreground color of this component.

[getForeground\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)
Get the foreground color of this object.

[getForeground\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)
Get the foreground color of this object.

[getForeground\(\)](#) - Method in class [java.awt.List.AccessibleAWTList.AccessibleAWTListChild](#)
Get the foreground color of this object.

[getForeground\(\)](#) - Method in interface [javax.accessibility.AccessibleComponent](#)
Gets the foreground color of this object.

[getForeground\(\)](#) - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

[getForeground\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)
Get the foreground color of this object.

[getForeground\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)
Gets the foreground color of this object.

[getForeground\(\)](#) - Method in class [javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getForeground\(\)](#) - Method in class [javax.swing.text.GlyphView](#)
Fetch the foreground color to use to render the glyphs.

[getForeground\(\)](#) - Method in class [javax.swing.text.LabelView](#)
Fetch the foreground color to use to render the glyphs.

[getForeground\(AttributeSet\)](#) - Method in class [javax.swing.text.StyleContext](#)
Takes a set of attributes and turn it into a foreground color specification.

[getForeground\(AttributeSet\)](#) - Static method in class [javax.swing.text.StyleConstants](#)
Gets the foreground color setting from the attribute list.

[getForeground\(AttributeSet\)](#) - Method in interface [javax.swing.text.StyledDocument](#)
Takes a set of attributes and turn it into a foreground color specification.

[getForeground\(AttributeSet\)](#) - Method in class [javax.swing.text.DefaultStyledDocument](#)
Gets the foreground color from an attribute set.

[getForeground\(AttributeSet\)](#) - Method in class [javax.swing.text.html.StyleSheet](#)
Takes a set of attributes and turn it into a foreground color specification.

[getForegroundAt\(int\)](#) - Method in class [javax.swing.JTabbedPane](#)
Returns the tab foreground color at index.

[getFormat\(\)](#) - Method in interface [java.security.Key](#)
Returns the name of the primary encoding format of this key, or null if this key does not support encoding.

[getFormat\(\)](#) - Method in interface [java.security.Certificate](#)
Deprecated. Returns the name of the coding format.

[getFormat\(\)](#) - Method in class [java.security.spec.EncodedKeySpec](#)
Returns the name of the encoding format associated with this key specification.

[getFormat\(\)](#) - Method in class [java.security.spec.PKCS8EncodedKeySpec](#)
Returns the name of the encoding format associated with this key specification.

[getFormat\(\)](#) - Method in class [java.security.spec.X509EncodedKeySpec](#)
Returns the name of the encoding format associated with this key specification.

[getFormat\(\)](#) - Method in class [javax.sound.sampled.AudioInputStream](#)
Obtains the audio format of the sound data in this audio input stream.

[getFormat\(\)](#) - Method in interface [javax.sound.sampled.DataLine](#)
Obtains the current format (encoding, sample rate, number of channels, etc.) of the data line's audio data.

[getFormat\(\)](#) - Method in class [javax.sound.sampled.AudioFileFormat](#)
Obtains the format of the audio data contained in the audio file.

[getFormats\(\)](#) - Method in class [java.text.ChoiceFormat](#)

Get the formats passed in the constructor.

getFormats() - Method in class java.text.MessageFormat
Gets formats that were set with setFormats.

getFormats() - Method in class javax.sound.sampled.DataLine.Info
Obtains a set of audio formats supported by the data line.

getFrame() - Method in class java.awt.geom.RectangularShape
Returns the framing Rectangle2D that defines the overall shape of this object.

getFrameForComponent(Component) - Static method in class javax.swing.JOptionPane
Returns the specified component's Frame.

getFrameIcon() - Method in class javax.swing.JInternalFrame
Returns the image displayed in the title bar of the frame (usually in the top-left corner).

getFrameLength() - Method in class javax.sound.sampled.AudioInputStream
Obtains the length of the stream, expressed in sample frames rather than bytes.

getFrameLength() - Method in class javax.sound.sampled.AudioFileFormat
Obtains the length of the audio data contained in the file, expressed in sample frames.

getFrameLength() - Method in interface javax.sound.sampled.Clip
Obtains the media length in sample frames.

getFramePosition() - Method in interface javax.sound.sampled.DataLine
Obtains the current position in the audio data, in sample frames.

getFramePosition() - Method in class javax.sound.sampled.LineEvent
Obtains the position in the line's audio data when the event occurred, expressed in sample frames.

getFrameRate() - Method in class javax.sound.sampled.AudioFormat
Obtains the frame rate in frames per second.

getFrames() - Static method in class java.awt.Frame
Returns an array containing all Frames created by the application.

getFrameSize() - Method in class javax.sound.sampled.AudioFormat
Obtains the frame size in bytes.

getFromIndex() - Method in class javax.swing.event.TableColumnModelEvent
Returns the fromIndex.

getFromPage() - Method in class java.awt.JobAttributes
Returns, for jobs using these attributes, the first page to be printed, if a range of pages is to be printed.

getG() - Method in interface java.security.interfaces.DSAParams
Returns the base, g.

getG() - Method in class java.security.spec.DSAPrivateKeySpec
Returns the base g.

getG() - Method in class java.security.spec.DSAPublicKeySpec
Returns the base g.

getG() - Method in class java.security.spec.DSAPrimitiveSpec
Returns the base g.

getGamma() - Method in class java.awt.color.ICC_ProfileGray
Returns a gamma value representing the tone reproduction curve (TRC).

getGamma(int) - Method in class java.awt.color.ICC_ProfileRGB
Returns a gamma value representing the tone reproduction curve (TRC) for a particular component.

getGestureModifiers() - Method in class java.awt.dnd.DragSourceDragEvent
This method returns an int representing the current state of the input device modifiers associated with the user's gesture.

getGlassPane() - Method in class javax.swing.JWindow
Returns the glassPane Component for this window.

getGlassPane() - Method in class javax.swing.JApplet
Returns the glassPane object for this applet.

getGlassPane() - Method in class javax.swing.JInternalFrame
Returns the glassPane object for this frame.

getGlassPane() - Method in class javax.swing.JFrame
Returns the glassPane object for this frame.

getGlassPane() - Method in interface [javax.swing.RootPaneContainer](#)
Returns the glassPane.

getGlassPane() - Method in class [javax.swing.JRootPane](#)
Returns the current glass pane for this JRootPane.

getGlassPane() - Method in class [javax.swing.JDialog](#)
Returns the glassPane object for this dialog.

getGlyphCode(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the glyphcode of the specified glyph.

getGlyphCodes(int, int, int[]) - Method in class [java.awt.font.GlyphVector](#)
Returns an array of glyphcodes for the specified glyphs.

getGlyphJustificationInfo(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the justification information for the glyph at the specified index into this GlyphVector.

getGlyphLogicalBounds(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the logical bounds of the specified glyph within this GlyphVector.

getGlyphMetrics(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the metrics of the glyph at the specified index into this GlyphVector.

getGlyphOutline(int) - Method in class [java.awt.font.GlyphVector](#)
Returns a Shape whose interior corresponds to the visual representation of the specified glyph within this GlyphVector.

getGlyphPainter() - Method in class [javax.swing.text.GlyphView](#)
Fetch the currently installed glyph painter.

getGlyphPosition(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the position of the specified glyph within this GlyphVector.

getGlyphPositions(int, int, float[]) - Method in class [java.awt.font.GlyphVector](#)
Returns an array of glyph positions for the specified glyphs.

getGlyphTransform(int) - Method in class [java.awt.font.GlyphVector](#)
Gets the transform of the specified glyph within this GlyphVector.

getGlyphVisualBounds(int) - Method in class [java.awt.font.GlyphVector](#)
Returns the visual bounds of the specified glyph within the GlyphVector.

getGoHomeAction() - Method in class [javax.swing.plaf.basic.BasicFileChooserUI](#)

getGraphics() - Method in class [java.awt.Component](#)
Creates a graphics context for this component.

getGraphics() - Method in class [java.awt.PrintJob](#)
Gets a Graphics object that will draw to the next page.

getGraphics() - Method in class [java.awt.Image](#)
Creates a graphics context for drawing to an off-screen image.

getGraphics() - Method in class [java.awt.image.BufferedImage](#)
This method returns a Graphics2D, but is here for backwards compatibility.

getGraphics() - Method in class [javax.swing.JComponent](#)
Returns this component's graphics context, which lets you draw on a component.

getGraphics() - Method in class [javax.swing.text.View](#)
Fetch a Graphics for rendering.

getGraphicsConfiguration() - Method in class [java.awt.Component](#)
Get the GraphicsConfiguration associated with this Component.

getGraphicsConfiguration() - Method in class [java.awt.Window](#)
This method returns the GraphicsConfiguration used by this Window.

getGreatestMinimum(int) - Method in class [java.util.Calendar](#)
Gets the highest minimum value for the given field if varies.

getGreatestMinimum(int) - Method in class [java.util.GregorianCalendar](#)
Returns highest minimum value for the given field if varies.

getGreen() - Method in class [java.awt.Color](#)
Returns the green component in the range 0-255 in the default sRGB space.

getGreen(int) - Method in class [java.awt.image.ColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(int\)](#) - Method in class java.awt.image.[ComponentColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(int\)](#) - Method in class java.awt.image.[DirectColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(int\)](#) - Method in class java.awt.image.[IndexColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(Object\)](#) - Method in class java.awt.image.[ColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(Object\)](#) - Method in class java.awt.image.[ComponentColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreen\(Object\)](#) - Method in class java.awt.image.[DirectColorModel](#)
Returns the green color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

[getGreenMask\(\)](#) - Method in class java.awt.image.[DirectColorModel](#)
Returns the mask indicating which bits in an int pixel representation contain the green color component.

[getGreens\(byte\[\]\)](#) - Method in class java.awt.image.[IndexColorModel](#)
Copies the array of green color components into the specified array.

[getGregorianChange\(\)](#) - Method in class java.util.[GregorianCalendar](#)
Gets the Gregorian Calendar change date.

[getGridColor\(\)](#) - Method in class javax.swing.[JTable](#)
Returns the color used to draw grid lines.

[getGridColumn\(\)](#) - Method in class javax.swing.text.[TableView.TableCell](#)
Deprecated. Gets the column of the grid location

[getGridRow\(\)](#) - Method in class javax.swing.text.[TableView.TableCell](#)
Deprecated. Gets the row of the grid location

[getGrooveInsets\(\)](#) - Static method in class javax.swing.plaf.basic.[BasicGraphicsUtils](#)
Returns the amount of space taken up by a border drawn by drawGroove()

[getGroup\(\)](#) - Method in class javax.swing.[DefaultButtonModel](#)
Returns the group that this button belongs to.

[getGroupID\(\)](#) - Method in class java.rmi.activation.[ActivationDesc](#)
Returns the group identifier for the object specified by this descriptor.

[getGroupingSeparator\(\)](#) - Method in class java.text.[DecimalFormatSymbols](#)
Gets the character used for thousands separator.

[getGroupingSize\(\)](#) - Method in class java.text.[DecimalFormat](#)
Return the grouping size.

[getGuarantor\(\)](#) - Method in interface java.security.[Certificate](#)
Deprecated. Returns the guarantor of the certificate, that is, the principal guaranteeing that the public key associated with this certificate is that of the principal associated with this certificate.

[getHAdjustable\(\)](#) - Method in class java.awt.[ScrollPane](#)
Returns the Adjustable object which represents the state of the horizontal scrollbar.

[getHashColor\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[getHeaderField\(int\)](#) - Method in class java.net.[URLConnection](#)
Returns the value for the nth header field.

[getHeaderField\(String\)](#) - Method in class java.net.[URLConnection](#)
Returns the name of the specified header field.

[getHeaderFieldDate\(String, long\)](#) - Method in class java.net.[URLConnection](#)
Returns the value of the named field parsed as date.

[getHeaderFieldDate\(String, long\)](#) - Method in class java.net.[HttpURLConnection](#)

[getHeaderFieldInt\(String, int\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of the named field parsed as a number.

[getHeaderFieldKey\(int\)](#) - Method in class [java.net.URLConnection](#)
Returns the key for the n^{th} header field.

[getHeaderRect\(int\)](#) - Method in class [javax.swing.table.JTableHeader](#)
Returns the rectangle containing the header tile at column.

[getHeaderRenderer\(\)](#) - Method in class [javax.swing.table.TableColumn](#)
Returns the TableCellRenderer used to draw the header of the TableColumn.

[getHeaderValue\(\)](#) - Method in class [javax.swing.table.TableColumn](#)
Returns the Object used as the value for the header renderer.

[getHeight\(\)](#) - Method in class [java.awt.Component](#)
Return the current height of this component.

[getHeight\(\)](#) - Method in class [java.awt.FontMetrics](#)
Gets the standard height of a line of text in this font.

[getHeight\(\)](#) - Method in class [java.awt.Dimension](#)
Returns the height of this dimension in double precision.

[getHeight\(\)](#) - Method in class [java.awt.Rectangle](#)
Returns the height of the bounding Rectangle in double precision.

[getHeight\(\)](#) - Method in class [java.awt.font.LineMetrics](#)
Returns the height of the text.

[getHeight\(\)](#) - Method in class [java.awt.geom.Dimension2D](#)
Returns the height of this Dimension in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.RectangularShape](#)
Returns the height of the framing rectangle in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.RoundRectangle2D.Float](#)
Returns the height of this RoundRectangle2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.RoundRectangle2D.Double](#)
Returns the height of this RoundRectangle2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.Rectangle2D.Float](#)
Returns the height of this Rectangle2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.Rectangle2D.Double](#)
Returns the height of this Rectangle2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.Arc2D.Float](#)
Returns the height of the ellipse of which this arc is a partial section

[getHeight\(\)](#) - Method in class [java.awt.geom.Arc2D.Double](#)
Returns the height of the ellipse of which this arc is a partial section

[getHeight\(\)](#) - Method in class [java.awt.geom.Ellipse2D.Float](#)
Returns the overall height of this Ellipse2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.geom.Ellipse2D.Double](#)
Returns the overall height of this Ellipse2D in double precision.

[getHeight\(\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the height in pixels.

[getHeight\(\)](#) - Method in class [java.awt.image.Kernel](#)
Returns the height of this Kernel.

[getHeight\(\)](#) - Method in class [java.awt.image.PixelGrabber](#)
Get the height of the pixel buffer (after adjusting for image height).

[getHeight\(\)](#) - Method in interface [java.awt.image.RenderedImage](#)
Returns the height of the RenderedImage.

[getHeight\(\)](#) - Method in class [java.awt.image.BufferedImage](#)
Returns the height of the BufferedImage.

[getHeight\(\)](#) - Method in class [java.awt.image.Raster](#)
Returns the height in pixels of the Raster.

[getHeight\(\)](#) - Method in class [java.awt.image.renderable.RenderableImageOp](#)
Gets the height in user coordinate space.

[getHeight\(\)](#) - Method in interface [java.awt.image.renderable.RenderableImage](#)

Gets the height in user coordinate space.

getHeight() - Method in class java.awt.print.Paper
Returns the height of the page in 1/72nds of an inch.

getHeight() - Method in class java.awt.print.PageFormat
Returns the height, in 1/72nds of an inch, of the page.

getHeight() - Method in class javax.swing.JComponent
Returns the current height of this component.

getHeight() - Method in class javax.swing.text.BoxView
The current height of the box.

getHeight(GlyphView) - Method in class javax.swing.text.GlyphView.GlyphPainter

getHeight(ImageObserver) - Method in class java.awt.Image
Determines the height of the image.

getHeight(ImageObserver) - Method in class java.awt.image.BufferedImage
Returns the actual height of the image.

getHeightOfHighValueLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getHeightOfLowValueLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getHeightOfTallestLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getHelpMenu() - Method in class java.awt.MenuBar
Gets the help menu on the menu bar.

getHelpMenu() - Method in class javax.swing.JMenuBar
Gets the help menu for the menu bar.

getHgap() - Method in class java.awt.CardLayout
Gets the horizontal gap between components.

getHgap() - Method in class java.awt.GridLayout
Gets the horizontal gap between components.

getHgap() - Method in class java.awt.BorderLayout
Returns the horizontal gap between components.

getHgap() - Method in class java.awt.FlowLayout
Gets the horizontal gap between components.

getHighestValueLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI
Returns the label that corresponds to the lowest slider value in the label table.

getHighlightColor() - Method in class javax.swing.border.EtchedBorder
Returns the highlight color of the etched border.

getHighlightColor() - Method in class javax.swing.plaf.basic.BasicSliderUI

getHighlightColor(Component) - Method in class javax.swing.border.EtchedBorder
Returns the highlight color of the etched border when rendered on the specified component.

getHighlightedTextColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getHighlightedTextColor() - Method in class javax.swing.plaf.metal.MetalTheme

getHighlighter() - Method in class javax.swing.text.JTextComponent
Fetches the object responsible for making highlights.

getHighlightInnerColor() - Method in class javax.swing.border.BevelBorder
Returns the inner highlight color of the bevel border.

getHighlightInnerColor(Component) - Method in class javax.swing.border.BevelBorder
Returns the inner highlight color of the bevel border when rendered on the specified component.

getHighlightOuterColor() - Method in class javax.swing.border.BevelBorder
Returns the outer highlight color of the bevel border.

getHighlightOuterColor(Component) - Method in class javax.swing.border.BevelBorder
Returns the outer highlight color of the bevel border when rendered on the specified component.

[getHighlights\(\)](#) - Method in interface [javax.swing.text.Highlighter](#)
Fetches the current list of highlights.

[getHighlights\(\)](#) - Method in class [javax.swing.text.DefaultHighlighter](#)
Makes a copy of the highlights.

[getHomeDirectory\(\)](#) - Method in class [javax.swing.filechooser.FileSystemView](#)

[getHorizontalAlignment\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the horizontal alignment of the icon and text.

[getHorizontalAlignment\(\)](#) - Method in class [javax.swing.JTextField](#)
Returns the horizontal alignment of the text.

[getHorizontalAlignment\(\)](#) - Method in class [javax.swing.JLabel](#)
Returns the alignment of the label's contents along the X axis.

[getHorizontalLegBuffer\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)
The horizontal element of legs between nodes starts at the right of the left-hand side of the child node by default.

[getHorizontalLegBuffer\(\)](#) - Method in class [javax.swing.plaf.metal.MetalTreeUI](#)

[getHorizontalScrollBar\(\)](#) - Method in class [javax.swing.ScrollPaneLayout](#)
Returns the JScrollBar object that handles horizontal scrolling.

[getHorizontalScrollBar\(\)](#) - Method in class [javax.swing.JScrollPane](#)
Returns the horizontal scroll bar that controls the viewport's horizontal view position.

[getHorizontalScrollBarPolicy\(\)](#) - Method in class [javax.swing.ScrollPaneLayout](#)
Returns the horizontal scrollbar-display policy.

[getHorizontalScrollBarPolicy\(\)](#) - Method in class [javax.swing.JScrollPane](#)
Returns the horizontal scroll bar policy value.

[getHorizontalSliderThumbIcon\(\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getHorizontalTextPosition\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the horizontal position of the text relative to the icon.

[getHorizontalTextPosition\(\)](#) - Method in class [javax.swing.JLabel](#)
Returns the horizontal position of the label's text, relative to its image.

[getHorizontalVisibility\(\)](#) - Method in class [javax.swing.JTextField](#)
Gets the visibility of the text field.

[getHost\(\)](#) - Method in class [java.net.URL](#)
Returns the host name of this URL, if applicable.

[getHostAddress\(\)](#) - Method in class [java.net.InetAddress](#)
Returns the IP address string "%d.%d.%d.%d".

[getHostAddress\(URL\)](#) - Method in class [java.net.URLStreamHandler](#)
Get the IP address of our host.

[getHostName\(\)](#) - Method in class [java.net.InetAddress](#)
Gets the host name for this IP address.

[getHours\(\)](#) - Method in class [java.sql.Date](#)
Deprecated.

[getHours\(\)](#) - Method in class [java.util.Date](#)
Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.HOUR_OF_DAY)`.*

[getHSBColor\(float, float, float\)](#) - Static method in class [java.awt.Color](#)
Creates a Color object based on the specified values for the HSB color model.

[getHScrollbarHeight\(\)](#) - Method in class [java.awt.ScrollPane](#)
Returns the height that would be occupied by a horizontal scrollbar, which is independent of whether it is currently displayed by the scroll pane or not.

[getHTMLDocument\(JEditorPane\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit.HTMLTextAction](#)

[getHTMLEditorKit\(JEditorPane\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit.HTMLTextAction](#)

[getHTMLTag\(\)](#) - Method in class [javax.swing.text.html.parser.TagElement](#)

[getHumanPresentableName\(\)](#) - Method in class [java.awt.datatransfer.DataFlavor](#)

Returns the human presentable name for the data format that this DataFlavor represents.

[getICCProfiles\(\)](#) - Method in class java.awt.image.ColorConvertOp
Returns the array of ICC_Profiles used to construct this ColorConvertOp.

[getIcon\(\)](#) - Method in class javax.swing.AbstractButton
Returns the default icon.

[getIcon\(\)](#) - Method in class javax.swing.JOptionPane
Returns the icon this pane displays.

[getIcon\(\)](#) - Method in class javax.swing.JLabel
Returns the graphic image (glyph, icon) that the label displays.

[getIcon\(\)](#) - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Returns the icon from the JOptionPane the receiver is providing the look and feel for, or the default icon as returned from getDefaultIcon.

[getIcon\(AttributeSet\)](#) - Static method in class javax.swing.text.StyleConstants
Gets the icon setting from the attribute list.

[getIcon\(File\)](#) - Method in class javax.swing.JFileChooser
Returns the icon for this file or type of file, depending on the system.

[getIcon\(File\)](#) - Method in class javax.swing.filechooser.FileView
The icon that represents this file in the JFileChooser.

[getIcon\(File\)](#) - Method in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

[getIcon\(int\)](#) - Method in interface java.beans.BeanInfo
This method returns an image object that can be used to represent the bean in toolboxes, toolbars, etc.

[getIcon\(int\)](#) - Method in class java.beans.SimpleBeanInfo
Claim there are no icons available.

[getIcon\(Object\)](#) - Method in class javax.swing.UIDefaults
If the value of key is an Icon return it, otherwise return null.

[getIcon\(Object\)](#) - Static method in class javax.swing.UIManager
Returns an Icon from the defaults table.

[getIconAt\(int\)](#) - Method in class javax.swing.JTabbedPane
Returns the tab icon at index.

[getIconForTab\(int\)](#) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

[getIconForType\(int\)](#) - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Returns the icon to use for the passed in type.

[getIconHeight\(\)](#) - Method in interface javax.swing.Icon
Returns the icon's height.

[getIconHeight\(\)](#) - Method in class javax.swing.ImageIcon
Gets the height of the icon.

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.IconUIResource

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalCheckBoxIcon

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalIconFactory.PaletteCloseIcon

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalIconFactory.FolderIcon16

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalIconFactory.FileIcon16

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeControlIcon

[getIconHeight\(\)](#) - Method in class javax.swing.plaf.metal.MetalComboBoxIcon
stubbed to satisfy the interface.

[getIconImage\(\)](#) - Method in class java.awt.Frame
Gets the image to be displayed in the minimized icon for this frame.

[getIconTextGap\(\)](#) - Method in class javax.swing.JLabel
Returns the amount of space between the text and the icon displayed in this label.

getIconWidth() - Method in interface javax.swing.Icon
Returns the icon's width.

getIconWidth() - Method in class javax.swing.ImageIcon
Gets the width of the icon.

getIconWidth() - Method in class javax.swing.plaf.IconUIResource

getIconWidth() - Method in class javax.swing.plaf.metal.MetalCheckBoxIcon

getIconWidth() - Method in class javax.swing.plaf.metal.MetalIconFactory.PaletteCloseIcon

getIconWidth() - Method in class javax.swing.plaf.metal.MetalIconFactory.FolderIcon16

getIconWidth() - Method in class javax.swing.plaf.metal.MetalIconFactory.FileIcon16

getIconWidth() - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeControlIcon

getIconWidth() - Method in class javax.swing.plaf.metal.MetalComboBoxIcon
stubbed to statify the interface.

getId() - Method in class org.omg.CORBA.portable.ApplicationException
Returns the CORBA repository ID of the exception without removing it from the exceptions input stream.

getID() - Method in class java.awt.AWTEvent
Returns the event type.

getID() - Method in class java.rmi.activation.Activatable
Returns the object's activation identifier.

getID() - Method in class java.util.TimeZone
Gets the ID of this time zone.

getID() - Method in class javax.naming.directory.BasicAttribute

getID() - Method in interface javax.naming.directory.Attribute
Retrieves the id of this attribute.

getID() - Method in interface javax.naming.ldap.Control
Retrieves the object identifier assigned for the LDAP control.

getID() - Method in interface javax.naming.ldap.ExtendedRequest
Retrieves the object identifier of the request.

getID() - Method in interface javax.naming.ldap.ExtendedResponse
Retrieves the object identifier of the response.

getID() - Method in class javax.swing.LookAndFeel
Return a string that identifies this look and feel.

getID() - Method in class javax.swing.plaf.metal.MetalLookAndFeel

getID() - Method in class javax.swing.plaf.multi.MultiLookAndFeel

getIdentifier() - Method in class javax.swing.table.TableColumn
Returns the identifier object for this column.

getIdentifierQuoteString() - Method in interface java.sql.DatabaseMetaData
What's the string used to quote SQL identifiers? This returns a space " " if identifier quoting isn't supported.

getIdentity(Principal) - Method in class java.security.IdentityScope
Deprecated. Retrieves the identity whose name is the same as that of the specified principal.

getIdentity(PublicKey) - Method in class java.security.IdentityScope
Deprecated. Retrieves the identity with the specified public key.

getIdentity(String) - Method in class java.security.IdentityScope
Deprecated. Returns the identity in this scope with the specified name (if any).

getIDs() - Method in interface javax.naming.directory.Attributes
Retrieves an enumeration of the ids of the attributes in the attribute set.

getIDs() - Method in class javax.naming.directory.BasicAttributes

getIDstring() - Method in class java.awt.GraphicsDevice
Returns the identification string associated with this GraphicsDevice.

getIfModifiedSince() - Method in class java.net.URLConnection
Returns the value of this object's ifModifiedSince field.

getImage() - Method in class java.awt.TexturePaint
Returns the BufferedImage texture used to fill the shapes.

getImage() - Method in class javax.swing.ImageIcon
Returns this icon's Image.

getImage(String) - Method in class java.awt.Toolkit
Returns an image which gets pixel data from the specified file, whose format can be either GIF, JPEG or PNG.

getImage(URL) - Method in interface java.applet.AppletContext
Returns an Image object that can then be painted on the screen.

getImage(URL) - Method in class java.applet.Applet
Returns an Image object that can then be painted on the screen.

getImage(URL) - Method in class java.awt.Toolkit
Returns an image which gets pixel data from the specified URL.

getImage(URL, String) - Method in class java.applet.Applet
Returns an Image object that can then be painted on the screen.

getImageableHeight() - Method in class java.awt.print.Paper
Returns the height of this Paper object's imageable area.

getImageableHeight() - Method in class java.awt.print.PageFormat
Return the height, in 1/72nds of an inch, of the imageable area of the page.

getImageableWidth() - Method in class java.awt.print.Paper
Returns the width of this Paper object's imageable area.

getImageableWidth() - Method in class java.awt.print.PageFormat
Returns the width, in 1/72nds of an inch, of the imageable area of the page.

getImageableX() - Method in class java.awt.print.Paper
Returns the x coordinate of the upper-left corner of this Paper object's imageable area.

getImageableX() - Method in class java.awt.print.PageFormat
Returns the x coordinate of the upper left point of the imageable area of the Paper object associated with this PageFormat.

getImageableY() - Method in class java.awt.print.Paper
Returns the y coordinate of the upper-left corner of this Paper object's imageable area.

getImageableY() - Method in class java.awt.print.PageFormat
Returns the y coordinate of the upper left point of the imageable area of the Paper object associated with this PageFormat.

getImageLoadStatus() - Method in class javax.swing.ImageIcon
Returns the status of the image loading operation.

getImageObserver() - Method in class javax.swing.ImageIcon
Returns the image observer for the image.

getImplementationTitle() - Method in class java.lang.Package
Return the title of this package.

getImplementationVendor() - Method in class java.lang.Package
Returns the name of the organization, vendor or company that provided this implementation.

getImplementationVersion() - Method in class java.lang.Package
Return the version of this implementation.

getImportedKeys(String, String, String) - Method in interface java.sql.DatabaseMetaData
Gets a description of the primary key columns that are referenced by a table's foreign key columns (the primary keys imported by a table).

getInactiveControlTextColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getInactiveControlTextColor() - Method in class javax.swing.plaf.metal.MetalTheme

getInactiveSystemTextColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getInactiveSystemTextColor() - Method in class javax.swing.plaf.metal.MetalTheme

getInCheck() - Method in class java.lang.SecurityManager

Deprecated. *This type of security checking is not recommended. It is recommended that the `checkPermission` call be used instead.*

getIndentLevel() - Method in class javax.swing.text.AbstractWriter

Returns the current indentation level.

getIndentSpace() - Method in class javax.swing.text.AbstractWriter

Returns the amount of space to indent.

getIndex() - Method in class java.sql.DataTruncation

Retrieves the index of the column or parameter that was truncated.

getIndex() - Method in class java.text.ParsePosition

Retrieve the current parse position.

getIndex() - Method in interface java.text.CharacterIterator

Returns the current index.

getIndex() - Method in class java.text.StringCharacterIterator

Implements `CharacterIterator.getIndex()` for `String`.

getIndex() - Method in interface javax.swing.event.DocumentEvent.ElementChange

Fetches the index within the element represented.

getIndex() - Method in class javax.swing.text.AbstractDocument.ElementEdit

Returns the index into the list of elements.

getIndex() - Method in class javax.swing.text.Segment

Returns the current index.

getIndex() - Method in class javax.swing.text.html.parser.Element

Get index.

getIndex(int) - Method in class javax.swing.SizeSequence

Returns the index of the entry that corresponds to the specified position.

getIndex(TreeNode) - Method in class javax.swing.text.AbstractDocument.AbstractElement

Returns the index of node in the receivers children.

getIndex(TreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns the index of the specified child in this node's child array.

getIndex(TreeNode) - Method in interface javax.swing.tree.TreeNode

Returns the index of node in the receivers children.

getIndex0() - Method in class javax.swing.event.ListDataEvent

Returns the lower index of the range.

getIndex1() - Method in class javax.swing.event.ListDataEvent

Returns the upper index of the range.

getIndexAtPoint(Point) - Method in class java.awt.TextComponent.AccessibleAWTTextComponent

Given a point in local coordinates, return the zero-based index of the character under that `Point`.

getIndexAtPoint(Point) - Method in interface javax.accessibility.AccessibleText

Given a point in local coordinates, return the zero-based index of the character under that `Point`.

getIndexAtPoint(Point) - Method in class javax.swing.AbstractButton.AccessibleAbstractButton

Given a point in local coordinates, return the zero-based index of the character under that `Point`.

getIndexAtPoint(Point) - Method in class javax.swing.JLabel.AccessibleJLabel

Given a point in local coordinates, return the zero-based index of the character under that `Point`.

getIndexAtPoint(Point) - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent

Given a point in local coordinates, return the zero-based index of the character under that `Point`.

getIndexedPropertyType() - Method in class java.beans.IndexedPropertyDescriptor

Gets the `Class` object of the indexed properties' type.

getIndexedReadMethod() - Method in class java.beans.IndexedPropertyDescriptor

Gets the method that should be used to read an indexed property value.

getIndexedWriteMethod() - Method in class java.beans.IndexedPropertyDescriptor

Gets the method that should be used to write an indexed property value.

[getIndexInfo\(String, String, String, boolean, boolean\)](#) - Method in interface [java.sql.DatabaseMetaData](#)

Gets a description of a table's indices and statistics.

[getIndexOf\(Component\)](#) - Method in class [javax.swing.JLayeredPane](#)

Returns the index of the specified Component.

[getIndexOf\(Object\)](#) - Method in class [javax.swing.DefaultComboBoxModel](#)

Returns the index-position of the specified object in the list.

[getIndexOfChild\(Object, Object\)](#) - Method in interface [javax.swing.tree.TreeModel](#)

Returns the index of child in parent.

[getIndexOfChild\(Object, Object\)](#) - Method in class [javax.swing.tree.DefaultTreeModel](#)

Returns the index of child in parent.

[getIndexOfSize\(float\)](#) - Static method in class [javax.swing.text.html.StyleSheet](#)

[getInetAddress\(\)](#) - Method in class [java.net.DatagramSocket](#)

Returns the address to which this socket is connected.

[getInetAddress\(\)](#) - Method in class [java.net.SocketImpl](#)

Returns the value of this socket's address field.

[getInetAddress\(\)](#) - Method in class [java.net.Socket](#)

Returns the address to which the socket is connected.

[getInetAddress\(\)](#) - Method in class [java.net.ServerSocket](#)

Returns the local address of this server socket.

[getInfinity\(\)](#) - Method in class [java.text.DecimalFormatSymbols](#)

Gets the character used to represent infinity.

[getInfo\(\)](#) - Method in class [java.security.Provider](#)

Returns a human-readable description of the provider and its services.

[getInfo\(\)](#) - Method in class [java.security.Identity](#)

Deprecated. Returns general information previously specified for this identity.

[getInitialContext\(Hashtable\)](#) - Static method in class [javax.naming.spi.NamingManager](#)

Creates an initial context using the specified environment properties.

[getInitialContext\(Hashtable\)](#) - Method in interface [javax.naming.spi.InitialContextFactory](#)

Creates an Initial Context for beginning name resolution.

[getInitialDelay\(\)](#) - Method in class [javax.swing.ToolTipManager](#)

Returns the initial delay value.

[getInitialDelay\(\)](#) - Method in class [javax.swing.Timer](#)

Returns the Timer's initial delay.

[getInitialLocation\(Insets\)](#) - Method in class [javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager](#)

Returns the left inset, unless the Insets are null in which case 0 is returned.

[getInitialSelectionValue\(\)](#) - Method in class [javax.swing.JOptionPane](#)

Returns the initial-selection value.

[getInitialValue\(\)](#) - Method in class [javax.swing.JOptionPane](#)

Returns the initial value.

[getInitialValueIndex\(\)](#) - Method in class [javax.swing.plaf.basic.BasicOptionPaneUI](#)

Returns the initial index into the buttons to select.

[getInputAttributes\(\)](#) - Method in class [javax.swing.JTextPane](#)

Gets the input attributes for the pane.

[getInputAttributes\(\)](#) - Method in class [javax.swing.text.StyledEditorKit](#)

Gets the input attributes for the pane.

[getInputAttributes\(\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit](#)

Gets the input attributes used for the styled editing actions.

[getInputContext\(\)](#) - Method in class [java.awt.Component](#)

Gets the input context used by this component for handling the communication with input methods when text is entered in this component.

[getInputContext\(\)](#) - Method in class [java.awt.Window](#)

Gets the input context for this window.

[getInputMap\(\)](#) - Method in class [javax.swing.JComponent](#)

Returns the InputMap that is used when the receiver has focus.

[getInputMap\(int\)](#) - Method in class `javax.swing.JComponent`
Returns the InputMap that is used during condition.

[getInputMethodControlObject\(\)](#) - Method in class `java.awt.im.InputContext`
Returns a control object from the current input method, or null.

[getInputMethodDisplayName\(Locale, Locale\)](#) - Method in interface `java.awt.im.spi.InputMethodDescriptor`
Returns the user-visible name of the corresponding input method for the given input locale in the language in which the name will be displayed.

[getInputMethodIcon\(Locale\)](#) - Method in interface `java.awt.im.spi.InputMethodDescriptor`
Returns an icon for the corresponding input method.

[getInputMethodRequests\(\)](#) - Method in class `java.awt.Component`
Gets the input method request handler which supports requests from input methods for this component.

[getInputMethodRequests\(\)](#) - Method in class `javax.swing.text.JTextComponent`

[getInputStream\(\)](#) - Method in class `java.lang.Process`
Gets the input stream of the subprocess.

[getInputStream\(\)](#) - Method in class `java.net.URLConnection`
Returns an input stream that reads from this open connection.

[getInputStream\(\)](#) - Method in class `java.net.SocketImpl`
Returns an input stream for this socket.

[getInputStream\(\)](#) - Method in class `java.net.Socket`
Returns an input stream for this socket.

[getInputStream\(\)](#) - Method in interface `java.rmi.server.RemoteCall`
Deprecated. no replacement

[getInputStream\(\)](#) - Method in class `org.omg.CORBA.portable.ApplicationException`
Returns the input stream from which the exception data can be read as its parameters.

[getInputStream\(ZipEntry\)](#) - Method in class `java.util.jar.JarFile`
Returns an input stream for reading the contents of the specified ZIP file entry.

[getInputStream\(ZipEntry\)](#) - Method in class `java.util.zip.ZipFile`
Returns an input stream for reading the contents of the specified zip file entry.

[getValue\(\)](#) - Method in class `javax.swing.JOptionPane`
Returns the value the user has input, if `wantsInput` is true.

[getVerifier\(\)](#) - Method in class `javax.swing.JComponent`
Returns the input verifier for this component.

[getInsertionIndex\(\)](#) - Method in class `java.awt.font.TextHitInfo`
Returns the insertion index.

[getInsertPositionOffset\(\)](#) - Method in interface `java.awt.im.InputMethodRequests`
Gets the offset of the insert position in the committed text contained in the text editing component.

[getInset\(int, View\)](#) - Method in class `javax.swing.text.html.StyleSheet.BoxPainter`
Fetches the inset needed on a given side to account for the margin, border, and padding.

[getInsets\(\)](#) - Method in class `java.awt.Container`
Determines the insets of this container, which indicate the size of the container's border.

[getInsets\(\)](#) - Method in class `javax.swing.JComponent`
If a border has been set on this component, returns the border's insets; otherwise calls `super.getInsets()`.

[getInsets\(\)](#) - Method in class `javax.swing.JViewport`
Returns the insets (border) dimensions as (0,0,0,0), since borders are not supported on a `JViewport`.

[getInsets\(\)](#) - Method in class `javax.swing.plaf.basic.BasicToolBarUI.DragWindow`

[getInsets\(\)](#) - Method in class `javax.swing.plaf.basic.BasicComboBoxUI`
Gets the insets from the `JComboBox`.

[getInsets\(\)](#) - Method in class `javax.swing.plaf.basic.BasicSplitPaneDivider`
If a border has been set on this component, returns the border's insets, else calls

`super.getInsets.`

`getInsets(Insets)` - Method in class `javax.swing.JComponent`
Returns an Insets object containing this component's inset values.

`getInsets(Insets)` - Method in class `javax.swing.JViewport`
Returns an Insets object containing this JViewports inset values.

`getInsets(JComponent)` - Method in class `javax.swing.plaf.basic.BasicSplitPaneUI`
Returns the insets.

`getInsets(JComponent)` - Method in class `javax.swing.plaf.basic.BasicDesktopIconUI`

`getInsets(Object)` - Method in class `javax.swing.UIManager`
If the value of key is an Insets return it, otherwise return null.

`getInsets(Object)` - Static method in class `javax.swing.UIManager`
Returns an Insets object from the defaults table.

`getInsideAllocation(Shape)` - Method in class `javax.swing.text.CompositeView`
Translates the immutable allocation given to the view to a mutable allocation that represents the interior allocation (i.e.

`getInsideBorder()` - Method in class `javax.swing.border.CompoundBorder`
Returns the inside border object.

`getInstalledLookAndFeels()` - Static method in class `javax.swing.UIManager`
Return an array of objects that provide some information about the LookAndFeel implementations that have been installed with this software development kit.

`getInstance()` - Static method in class `java.awt.im.InputContext`
Returns a new InputContext instance.

`getInstance()` - Static method in class `java.text.NumberFormat`
Returns the default number format for the current default locale.

`getInstance()` - Static method in class `java.text.Collator`
Gets the Collator for the current default locale.

`getInstance()` - Static method in class `java.text.DateFormat`
Get a default date/time formatter that uses the SHORT style for both the date and the time.

`getInstance()` - Static method in class `java.util.Calendar`
Gets a calendar using the default time zone and locale.

`getInstance(byte[])` - Static method in class `java.awt.color.ICC_Profile`
Constructs an ICC_Profile object corresponding to the data in a byte array.

`getInstance(InputStream)` - Static method in class `java.awt.color.ICC_Profile`
Constructs an ICC_Profile corresponding to the data in an InputStream.

`getInstance(int)` - Static method in class `java.awt.AlphaComposite`
Creates an AlphaComposite object with the specified rule.

`getInstance(int)` - Static method in class `java.awt.color.ICC_Profile`
Constructs an ICC_Profile corresponding to one of the specific color spaces defined by the ColorSpace class (for example CS_sRGB).

`getInstance(int)` - Static method in class `java.awt.color.ColorSpace`
Returns a ColorSpace representing one of the specific predefined color spaces.

`getInstance(int, float)` - Static method in class `java.awt.AlphaComposite`
Creates an AlphaComposite object with the specified rule and the constant alpha to multiply with the alpha of the source.

`getInstance(Locale)` - Static method in class `java.text.NumberFormat`
Returns the default number format for the specified locale.

`getInstance(Locale)` - Static method in class `java.text.Collator`
Gets the Collator for the desired locale.

`getInstance(Locale)` - Static method in class `java.util.Calendar`
Gets a calendar using the default time zone and specified locale.

`getInstance(String)` - Static method in class `java.awt.color.ICC_Profile`
Constructs an ICC_Profile corresponding to the data in a file.

`getInstance(String)` - Static method in class `java.security.KeyFactory`
Generates a KeyFactory object that implements the specified digest algorithm.

`getInstance(String)` - Static method in class `java.security.KeyPairGenerator`
Generates a KeyPairGenerator object that implements the specified digest algorithm.

getInstance(String) - Static method in class java.security.SecureRandom
Generates a SecureRandom object that implements the specified Pseudo Random Number Generator (PRNG) algorithm.

getInstance(String) - Static method in class java.security.AlgorithmParameters
Generates a parameter object for the specified algorithm.

getInstance(String) - Static method in class java.security.AlgorithmParameterGenerator
Generates an AlgorithmParameterGenerator object that implements the specified digest algorithm.

getInstance(String) - Static method in class java.security.KeyStore
Generates a keystore object of the given type.

getInstance(String) - Static method in class java.security.MessageDigest
Generates a MessageDigest object that implements the specified digest algorithm.

getInstance(String) - Static method in class java.security.Signature
Generates a Signature object that implements the specified digest algorithm.

getInstance(String) - Static method in class java.security.cert.CertificateFactory
Generates a certificate factory object that implements the specified certificate type.

getInstance(String, String) - Static method in class java.security.KeyFactory
Generates a KeyFactory object for the specified algorithm from the specified provider.

getInstance(String, String) - Static method in class java.security.KeyPairGenerator
Generates a KeyPairGenerator object implementing the specified algorithm, as supplied from the specified provider, if such an algorithm is available from the provider.

getInstance(String, String) - Static method in class java.security.SecureRandom
Generates a SecureRandom object for the specified PRNG algorithm, as supplied from the specified provider, if such a PRNG implementation is available from the provider.

getInstance(String, String) - Static method in class java.security.AlgorithmParameters
Generates a parameter object for the specified algorithm, as supplied by the specified provider, if such an algorithm is available from the provider.

getInstance(String, String) - Static method in class java.security.AlgorithmParameterGenerator
Generates an AlgorithmParameterGenerator object for the requested algorithm, as supplied from the specified provider, if such a parameter generator is available from the provider.

getInstance(String, String) - Static method in class java.security.KeyStore
Generates a keystore object for the specified keystore type from the specified provider.

getInstance(String, String) - Static method in class java.security.MessageDigest
Generates a MessageDigest object implementing the specified algorithm, as supplied from the specified provider, if such an algorithm is available from the provider.

getInstance(String, String) - Static method in class java.security.Signature
Generates a Signature object implementing the specified algorithm, as supplied from the specified provider, if such an algorithm is available from the provider.

getInstance(String, String) - Static method in class java.security.cert.CertificateFactory
Generates a certificate factory object for the specified certificate type from the specified provider.

getInstance(TimeZone) - Static method in class java.util.Calendar
Gets a calendar using the specified time zone and default locale.

getInstance(TimeZone, Locale) - Static method in class java.util.Calendar
Gets a calendar with the specified time zone and locale.

getInstanceFollowRedirects() - Method in class java.net.HttpURLConnection
Returns the value of this HttpURLConnection's instanceFollowRedirects field.

getInstanceOf(Object, Class) - Static method in class java.beans.Beans
From a given bean, obtain an object representing a specified type view of that source object.

getInstrument(Patch) - Method in interface javax.sound.midi.Soundbank
Obtains an Instrument from the given Patch.

getInstruments() - Method in interface javax.sound.midi.Soundbank
Obtains a list of instruments contained in this sound bank.

getInt(int) - Method in interface java.sql.CallableStatement
Gets the value of a JDBC INTEGER parameter as an int in the Java programming language.

getInt(int) - Method in interface java.sql.ResultSet
Gets the value of the designated column in the current row of this ResultSet object as an int

in the Java programming language.

[getInt\(Object\)](#) - Method in class [java.lang.reflect.Field](#)

Gets the value of a field as an int on the specified object.

[getInt\(Object\)](#) - Method in class [javax.swing.UIDefaults](#)

If the value of key is an Integer return its integer value, otherwise return 0.

[getInt\(Object\)](#) - Static method in class [javax.swing.UIManager](#)

Returns an int from the defaults table.

[getInt\(Object, int\)](#) - Static method in class [java.lang.reflect.Array](#)

Returns the value of the indexed component in the specified array object, as an int.

[getInt\(String\)](#) - Method in interface [java.sql.ResultSet](#)

Gets the value of the designated column in the current row of this ResultSet object as an int in the Java programming language.

[getInteger\(String\)](#) - Static method in class [java.lang.Integer](#)

Determines the integer value of the system property with the specified name.

[getInteger\(String, int\)](#) - Static method in class [java.lang.Integer](#)

Determines the integer value of the system property with the specified name.

[getInteger\(String, Integer\)](#) - Static method in class [java.lang.Integer](#)

Returns the integer value of the system property with the specified name.

[getIntegerAttributeValue\(AttributeSet, HTML.Attribute, int\)](#) - Static method in class [javax.swing.text.html.HTML](#)

Fetch an integer attribute value.

[getInterCellSpacing\(\)](#) - Method in class [javax.swing.JTable](#)

Returns the horizontal and vertical space between cells.

[getInterface\(\)](#) - Method in class [java.net.MulticastSocket](#)

Retrieve the address of the network interface used for multicast packets.

[getInterfaces\(\)](#) - Method in class [java.lang.Class](#)

Determines the interfaces implemented by the class or interface represented by this object.

[getInteriorRectangle\(Component, Border, int, int, int, int\)](#) - Static method in class [javax.swing.border.AbstractBorder](#)

Returns a rectangle using the arguments minus the insets of the border.

[getInteriorRectangle\(Component, int, int, int, int\)](#) - Method in class [javax.swing.border.AbstractBorder](#)

This convenience method calls the static method.

[getInternalFrame\(\)](#) - Method in class [javax.swing.JInternalFrame.JDesktopIcon](#)

Returns the JInternalFrame that this DesktopIcon is associated with.

[getInternalFrame\(\)](#) - Method in class [javax.swing.event.InternalFrameEvent](#)

Returns the originator of the event.

[getInternalFrameAltMaximizeIcon\(int\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getInternalFrameBorder\(\)](#) - Static method in class [javax.swing.plaf.basic.BasicBorders](#)

[getInternalFrameCloseIcon\(int\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getInternalFrameDefaultMenuIcon\(\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getInternalFrameMaximizeIcon\(int\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getInternalFrameMinimizeIcon\(int\)](#) - Static method in class [javax.swing.plaf.metal.MetalIconFactory](#)

[getInternationalCurrencySymbol\(\)](#) - Method in class [java.text.DecimalFormatSymbols](#)

Return the international string denoting the local currency.

[getInterpolationType\(\)](#) - Method in class [java.awt.image.AffineTransformOp](#)

Returns the interpolation type used by this op.

[getIntParameter\(int\)](#) - Method in class [java.awt.image.renderable.ParameterBlock](#)

A convenience method to return a parameter as an int.

[getInverted\(\)](#) - Method in class [javax.swing.JSlider](#)

Returns true if the value-range shown for the slider is reversed.

[getInvocationHandler\(Object\)](#) - Static method in class java.lang.reflect.[Proxy](#)
Returns the invocation handler for the specified proxy instance.

[getInvoker\(\)](#) - Method in class javax.swing.JPopupMenu
Returns the component which is the 'invoker' of this popup menu.

[getInvokesStopCellEditing\(\)](#) - Method in class javax.swing.JTree
Returns the indicator that tells what happens when editing is interrupted.

[getIOException\(\)](#) - Method in class java.awt.print.PrinterIOException
Returns the IOException that terminated the print job.

[getISO3Country\(\)](#) - Method in class java.util.Locale
Returns a three-letter abbreviation for this locale's country.

[getISO3Language\(\)](#) - Method in class java.util.Locale
Returns a three-letter abbreviation for this locale's language.

[getISOCountries\(\)](#) - Static method in class java.util.Locale
Returns a list of all 2-letter country codes defined in ISO 3166.

[getISOLanguages\(\)](#) - Static method in class java.util.Locale
Returns a list of all 2-letter language codes defined in ISO 639.

[getIssuerDN\(\)](#) - Method in class java.security.cert.X509Certificate
Gets the issuer (issuer distinguished name) value from the certificate.

[getIssuerDN\(\)](#) - Method in class java.security.cert.X509CRL
Gets the issuer (issuer distinguished name) value from the CRL.

[getIssuerUniqueID\(\)](#) - Method in class java.security.cert.X509Certificate
Gets the issuerUniqueID value from the certificate.

[getItalicAngle\(\)](#) - Method in class java.awt.Font
Returns the italic angle of this Font.

[getItem\(\)](#) - Method in class java.awt.event.ItemEvent
Returns the item affected by the event.

[getItem\(\)](#) - Method in interface javax.swing.ComboBoxEditor
Return the edited item

[getItem\(\)](#) - Method in class javax.swing.plaf.basic.BasicComboBoxEditor

[getItem\(int\)](#) - Method in class java.awt.Menu
Gets the item located at the specified index of this menu.

[getItem\(int\)](#) - Method in class java.awt.List
Gets the item associated with the specified index.

[getItem\(int\)](#) - Method in class java.awt.Choice
Gets the string at the specified index in this Choice menu.

[getItem\(int\)](#) - Method in class javax.swing.JMenu
Returns the JMenuItem at the specified position.

[getItemAt\(int\)](#) - Method in class javax.swing.JComboBox
Returns the list item at the specified index.

[getItemCount\(\)](#) - Method in class java.awt.Menu
Get the number of items in this menu.

[getItemCount\(\)](#) - Method in class java.awt.List
Gets the number of items in the list.

[getItemCount\(\)](#) - Method in class java.awt.Choice
Returns the number of items in this Choice menu.

[getItemCount\(\)](#) - Method in class javax.swing.JMenu
Returns the number of items on the menu, including separators.

[getItemCount\(\)](#) - Method in class javax.swing.JComboBox
Returns the number of items in the list.

[getItems\(\)](#) - Method in class java.awt.List
Gets the items in the list.

[getItemSelectable\(\)](#) - Method in class java.awt.event.ItemEvent
Returns the originator of the event.

[getIterator\(\)](#) - Method in class java.text.AttributedString
Creates an AttributedStringIterator instance that provides access to the entire contents of

this string.

[getIterator\(AttributedCharacterIterator.Attribute\[\]\)](#) - Method in class [java.text.AttributedString](#)
Creates an AttributedCharacterIterator instance that provides access to selected contents of this string.

[getIterator\(AttributedCharacterIterator.Attribute\[\], int, int\)](#) - Method in class [java.text.AttributedString](#)
Creates an AttributedCharacterIterator instance that provides access to selected contents of this string.

[getIterator\(HTML.Tag\)](#) - Method in class [javax.swing.text.html.HTMLDocument](#)
Fetches an iterator for the following kind of HTML tag.

[getJarEntry\(\)](#) - Method in class [java.net.JarURLConnection](#)
Return the JAR entry object for this connection, if any.

[getJarEntry\(String\)](#) - Method in class [java.util.jar.JarFile](#)
Returns the JarEntry for the given entry name or null if not found.

[getJarFile\(\)](#) - Method in class [java.net.JarURLConnection](#)
Return the JAR file for this connection.

[getJarFileURL\(\)](#) - Method in class [java.net.JarURLConnection](#)
Returns the URL for the Jar file for this connection.

[getJavaInitializationString\(\)](#) - Method in interface [java.beans.PropertyEditor](#)
This method is intended for use when generating Java code to set the value of the property.

[getJavaInitializationString\(\)](#) - Method in class [java.beans.PropertyEditorSupport](#)
This method is intended for use when generating Java code to set the value of the property.

[getJMenuBar\(\)](#) - Method in class [javax.swing.JApplet](#)
Returns the menubar set on this applet.

[getJMenuBar\(\)](#) - Method in class [javax.swing.JInternalFrame](#)
Returns the current JMenuBar for this JInternalFrame, or null if no menu bar has been set.

[getJMenuBar\(\)](#) - Method in class [javax.swing.JFrame](#)
Returns the menubar set on this frame.

[getJMenuBar\(\)](#) - Method in class [javax.swing.JRootPane](#)
Returns the menu bar from the layered pane.

[getJMenuBar\(\)](#) - Method in class [javax.swing.JDialog](#)
Returns the menubar set on this dialog.

[getJobName\(\)](#) - Method in class [java.awt.print.PrinterJob](#)
Gets the name of the document to be printed.

[getJustificationInfo\(\)](#) - Method in class [java.awt.font.GraphicAttribute](#)
Returns the justification information for this GraphicAttribute.

[getJustifiedLayout\(float\)](#) - Method in class [java.awt.font.TextLayout](#)
Creates a copy of this TextLayout justified to the specified width.

[getKeepAlive\(\)](#) - Method in class [java.net.Socket](#)
Tests if SO_KEEPALIVE is enabled.

[getKernel\(\)](#) - Method in class [java.awt.image.ConvolveOp](#)
Returns the Kernel.

[getKernelData\(float\[\]\)](#) - Method in class [java.awt.image.Kernel](#)
Returns the kernel data in row major order.

[getKey\(\)](#) - Method in class [java.awt.MenuShortcut](#)
Return the raw keycode of this MenuShortcut.

[getKey\(\)](#) - Method in class [java.util.MissingResourceException](#)
Gets parameter passed by constructor.

[getKey\(\)](#) - Method in interface [java.util.Map.Entry](#)
Returns the key corresponding to this entry.

[getKey\(\)](#) - Method in class [javax.accessibility.AccessibleRelation](#)
Returns the key for this relation

[getKey\(String, char\[\]\)](#) - Method in class [java.security.KeyStore](#)
Returns the key associated with the given alias, using the given password to recover it.

[getKeyChar\(\)](#) - Method in class [java.awt.event.KeyEvent](#)
Returns the character associated with the key in this event.

[getKeyChar\(\)](#) - Method in class [javax.swing.KeyStroke](#)

Returns the character defined by this `KeyStroke` object.

`getKeyCode()` - Method in class `java.awt.event.KeyEvent`
Returns the integer key-code associated with the key in this event.

`getKeyCode()` - Method in class `javax.swing.KeyStroke`
Returns the numeric keycode defined by this `KeyStroke` object.

`getKeyListener()` - Method in class `javax.swing.plaf.basic.BasicComboPopup`
Implementation of `ComboPopup.getKeyListener()`.

`getKeyListener()` - Method in interface `javax.swing.plaf.basic.ComboPopup`
Returns a key listener that shows and hides the popup.

`getKeymap()` - Method in class `javax.swing.text.JTextComponent`
Fetches the keymap currently active in this text component.

`getKeymap(String)` - Static method in class `javax.swing.text.JTextComponent`
Fetches a named keymap previously added to the document.

`getKeymapName()` - Method in class `javax.swing.plaf.basic.BasicTextUI`
Fetches the name of the keymap that will be installed/used by default for this UI.

`getKeyModifiersText(int)` - Static method in class `java.awt.event.KeyEvent`
Returns a String describing the modifier key(s), such as "Shift", or "Ctrl+Shift".

`getKeys()` - Method in class `java.util.ResourceBundle`
Return an enumeration of the keys.

`getKeys()` - Method in class `java.util.PropertyResourceBundle`
Implementation of `ResourceBundle.getKeys`.

`getKeys()` - Method in class `java.util.ListResourceBundle`
Implementation of `ResourceBundle.getKeys`.

`getKeys()` - Method in class `javax.swing.AbstractAction`
Returns an array of Objects which are keys for which values have been set for this `AbstractAction`, or null if no keys have values set.

`getKeySelectionManager()` - Method in class `javax.swing.JComboBox`
Returns the list's key-selection manager.

`getKeySize()` - Method in class `java.security.spec.RSAKeyGenParameterSpec`
Returns the keysize.

`getKeySpec(Key, Class)` - Method in class `java.security.KeyFactory`
Returns a specification (key material) of the given key object.

`getKeyStroke(char)` - Static method in class `javax.swing.KeyStroke`
Return a shared instance of a key stroke that is activated when the key is pressed (that is, a `KeyStroke` for the `KEY_TYPED` event).

`getKeyStroke(Character, int)` - Static method in class `javax.swing.KeyStroke`
Return a shared instance of a key stroke, given a character object and a set of modifiers.

`getKeyStroke(char, boolean)` - Static method in class `javax.swing.KeyStroke`
Deprecated. *use `getKeyStroke(char)`*

`getKeyStroke(int, int)` - Static method in class `javax.swing.KeyStroke`
Return a shared instance of a key stroke given a char code and a set of modifiers -- the key is activated when it is pressed.

`getKeyStroke(int, int, boolean)` - Static method in class `javax.swing.KeyStroke`
Return a shared instance of a key stroke given a numeric keycode and a set of modifiers, specifying whether the key is activated when it is pressed or released.

`getKeyStroke(String)` - Static method in class `javax.swing.KeyStroke`
Parse a string and return a `KeyStroke`.

`getKeyStrokeForEvent(KeyEvent)` - Static method in class `javax.swing.KeyStroke`
Return a keystroke from an event.

`getKeyStrokesForAction(Action)` - Method in interface `javax.swing.text.Keymap`
Fetches the keystrokes that will result in the given action.

`getKeyText(int)` - Static method in class `java.awt.event.KeyEvent`
Returns a String describing the `keyCode`, such as "HOME", "F1" or "A".

`getKeyUsage()` - Method in class `java.security.cert.X509Certificate`
Gets a boolean array representing bits of the `KeyUsage` extension, (OID = 2.5.29.15).

`getLabel()` - Method in class `java.awt.MenuItem`
Gets the label for this menu item.

getLabel() - Method in class java.awt.Checkbox
Gets the label of this check box.

getLabel() - Method in class java.awt.Button
Gets the label of this button.

getLabel() - Method in class javax.swing.AbstractButton
Deprecated. - *Replaced by getText*

getLabel() - Method in class javax.swing.JPopupMenu
Returns the popup menu's label

getLabel() - Method in class javax.swing.text.html.Option
Fetch the label associated with the option.

getLabelFor() - Method in class javax.swing.JLabel
Get the component this is labelling.

getLabelTable() - Method in class javax.swing.JSlider
Returns the dictionary of what labels to draw at which values.

getLanguage() - Method in class java.util.Locale
Returns the language code for this locale, which will either be the empty string or a lowercase ISO 639 code.

getLargeDisplayIcon() - Method in class javax.swing.colorchooser.AbstractColorChooserPanel
Returns the small display icon for the panel.

getLast() - Method in class java.util.LinkedList
Returns the last element in this list.

getLastChild() - Method in class javax.swing.tree.DefaultMutableTreeNode
Returns this node's last child.

getLastChildPath(TreePath) - Method in class javax.swing.plaf.basic.BasicTreeUI
Returns a path to the last child of parent.

getLastColumn() - Method in interface javax.accessibility.AccessibleTableModelChange
Returns the last column that changed.

getLastColumn() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableModelChange

getLastComponent(Container) - Method in class javax.swing.DefaultFocusManager
Return the last component that should receive the focus

getLastDividerLocation() - Method in class javax.swing.JSplitPane
Returns the last location the divider was at.

getLastDragLocation() - Method in class javax.swing.plaf.basic.BasicSplitPaneUI
Returns the last drag location of the JSplitPane.

getLastIndex() - Method in class javax.swing.event.ListSelectionEvent
Returns the index of the last row whose selection may have changed.

getLastLeaf() - Method in class javax.swing.tree.DefaultMutableTreeNode
Finds and returns the last leaf that is a descendant of this node -- either this node or its last child's last leaf.

getLastModified() - Method in class java.net.URLConnection
Returns the value of the last-modified header field.

getLastPathComponent() - Method in class javax.swing.tree.TreePath
Returns the last component of this path.

getLastRow() - Method in interface javax.accessibility.AccessibleTableModelChange
Returns the last row that changed.

getLastRow() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableModelChange

getLastRow() - Method in class javax.swing.event.TableModelEvent
Returns the last row that changed.

getLastSelectedPathComponent() - Method in class javax.swing.JTree
Returns the last path component in the first node of the current selection.

getLastVisibleIndex() - Method in class javax.swing.JList
Returns the index of the cell in the lower right corner of the JList or -1 if nothing is visible or the list is empty.

getLatency() - Method in interface javax.sound.midi.Synthesizer
Obtains the processing latency incurred by this synthesizer, expressed in microseconds.

[getLateReflectionDelay\(\)](#) - Method in class `javax.sound.sampled.ReverbType`
Returns the late reflection delay time in microseconds.

[getLateReflectionIntensity\(\)](#) - Method in class `javax.sound.sampled.ReverbType`
Returns the late reflection intensity in microseconds.

[getLayer\(\)](#) - Method in class `javax.swing.JInternalFrame`
Convenience method for getting the layer attribute of this component.

[getLayer\(Component\)](#) - Method in class `javax.swing.JLayeredPane`
Returns the layer attribute for the specified Component.

[getLayer\(JComponent\)](#) - Static method in class `javax.swing.JLayeredPane`
Gets the layer property for a JComponent, it does not cause any side effects like `setLayer()`.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JWindow`
Returns the layeredPane object for this window.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JApplet`
Returns the layeredPane object for this applet.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JInternalFrame`
Returns the layeredPane object for this frame.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JFrame`
Returns the layeredPane object for this frame.

[getLayeredPane\(\)](#) - Method in interface `javax.swing.RootPaneContainer`
Returns the layeredPane.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JRootPane`
Get the layered pane used by the root pane.

[getLayeredPane\(\)](#) - Method in class `javax.swing.JDialog`
Returns the layeredPane object for this dialog.

[getLayeredPaneAbove\(Component\)](#) - Static method in class `javax.swing.JLayeredPane`
Convenience method that returns the first JLayeredPane which contains the specified component.

[getLayout\(\)](#) - Method in class `java.awt.Container`
Gets the layout manager for this container.

[getLayout\(int, int\)](#) - Method in class `java.awt.font.TextMeasurer`
Returns a TextLayout on the given character range.

[getLayoutAlignmentX\(Container\)](#) - Method in interface `java.awt.LayoutManager2`
Returns the alignment along the x axis.

[getLayoutAlignmentX\(Container\)](#) - Method in class `java.awt.CardLayout`
Returns the alignment along the x axis.

[getLayoutAlignmentX\(Container\)](#) - Method in class `java.awt.BorderLayout`
Returns the alignment along the x axis.

[getLayoutAlignmentX\(Container\)](#) - Method in class `java.awt.GridBagLayout`
Returns the alignment along the x axis.

[getLayoutAlignmentX\(Container\)](#) - Method in class `javax.swing.BoxLayout`
Returns the alignment along the X axis for the container.

[getLayoutAlignmentX\(Container\)](#) - Method in class `javax.swing.OverlayLayout`
Returns the alignment along the x axis for the container.

[getLayoutAlignmentX\(Container\)](#) - Method in class `javax.swing.JRootPane.RootLayout`

[getLayoutAlignmentX\(Container\)](#) - Method in class
`javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager`
Returns the alignment along the x axis.

[getLayoutAlignmentY\(Container\)](#) - Method in interface `java.awt.LayoutManager2`
Returns the alignment along the y axis.

[getLayoutAlignmentY\(Container\)](#) - Method in class `java.awt.CardLayout`
Returns the alignment along the y axis.

[getLayoutAlignmentY\(Container\)](#) - Method in class `java.awt.BorderLayout`
Returns the alignment along the y axis.

[getLayoutAlignmentY\(Container\)](#) - Method in class `java.awt.GridBagLayout`
Returns the alignment along the y axis.

[getLayoutAlignmentY\(Container\)](#) - Method in class `javax.swing.BoxLayout`
Returns the alignment along the Y axis for the container.

getLayoutAlignmentY(Container) - Method in class javax.swing.OverlayLayout

Returns the alignment along the y axis for the container.

getLayoutAlignmentY(Container) - Method in class javax.swing.JRootPane.RootLayout

getLayoutAlignmentY(Container) - Method in class
javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager

Returns the alignment along the y axis.

getLayoutDimensions() - Method in class java.awt.GridBagLayout

Determines column widths and row heights for the layout grid.

GetLayoutInfo(Container, int) - Method in class java.awt.GridBagLayout

Print the layout constraints.

getLayoutOrigin() - Method in class java.awt.GridBagLayout

Determines the origin of the layout grid.

getLayoutQueue() - Method in class javax.swing.text.AsyncBoxView

Fetch the queue to use for layout.

getLayoutView(int) - Method in class javax.swing.text.ParagraphView

The child views of the paragraph are rows which have been used to arrange pieces of the Views that represent the child elements.

getLayoutViewCount() - Method in class javax.swing.text.ParagraphView

The child views of the paragraph are rows which have been used to arrange pieces of the Views that represent the child elements.

getLayoutWeights() - Method in class java.awt.GridBagLayout

Determines the weights of the layout grid's columns and rows.

getLeader() - Method in class javax.swing.text.TabStop

getLeading() - Method in class java.awt.FontMetrics

Determines the *standard leading* of the Font described by this FontMetrics object.

getLeading() - Method in class java.awt.font.TextLayout

Returns the leading of the TextLayout.

getLeading() - Method in class java.awt.font.LineMetrics

Returns the leading of the text.

getLeadSelectionIndex() - Method in class javax.swing.DefaultListSelectionModel

getLeadSelectionIndex() - Method in class javax.swing.JList

Returns the second index argument from the most recent addSelectionInterval or setSelectionInterval call.

getLeadSelectionIndex() - Method in interface javax.swing.ListSelectionModel

Return the second index argument from the most recent call to setSelectionInterval(), addSelectionInterval() or removeSelectionInterval().

getLeadSelectionPath() - Method in class javax.swing.JTree

Returns the path identified as the lead.

getLeadSelectionPath() - Method in class javax.swing.tree.DefaultTreeSelectionModel

Returns the last path that was added.

getLeadSelectionPath() - Method in interface javax.swing.tree.TreeSelectionModel

Returns the last path that was added.

getLeadSelectionRow() - Method in class javax.swing.JTree

Returns the row index corresponding to the lead path.

getLeadSelectionRow() - Method in class javax.swing.tree.DefaultTreeSelectionModel

Returns the lead selection index.

getLeadSelectionRow() - Method in interface javax.swing.tree.TreeSelectionModel

Returns the lead selection index.

getLeafCount() - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns the total number of leaves that are descendants of this node.

getLeafIcon() - Method in class javax.swing.tree.DefaultTreeCellRenderer

Returns the icon used to represent leaf nodes.

getLeastMaximum(int) - Method in class java.util.Calendar

Gets the lowest maximum value for the given field if varies.

getLeastMaximum(int) - Method in class java.util.GregorianCalendar
Returns lowest maximum value for the given field if varies.

getLeftChildIndent() - Method in class javax.swing.plaf.basic.BasicTreeUI

getLeftComponent() - Method in class javax.swing.JSplitPane
Returns the component to the left (or above) the divider.

getLeftIndent(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Gets the left indent setting.

getLeftInset() - Method in class javax.swing.text.CompositeView
Gets the left inset.

getLeftInset() - Method in class javax.swing.text.AsyncBoxView
Get the left part of the margin around the view.

getLength() - Method in class java.net.DatagramPacket
Returns the length of the data to be sent or the length of the data received.

getLength() - Method in class javax.sound.midi.MidiMessage
Obtains the total length of the MIDI message in bytes.

getLength() - Method in interface javax.swing.event.DocumentEvent
Returns the length of the change.

getLength() - Method in interface javax.swing.text.Document
Returns number of characters of content currently in the document.

getLength() - Method in class javax.swing.text.AbstractDocument
Returns the length of the data.

getLength() - Method in class javax.swing.text.AbstractDocument.DefaultDocumentEvent
Returns the length of the change.

getLength() - Method in class javax.swing.text.DefaultStyledDocument.ElementSpec
Gets the length.

getLength(Object) - Static method in class java.lang.reflect.Array
Returns the length of the specified array object, as an int.

getLevel() - Method in interface javax.sound.sampled.DataLine
Obtains the current volume level for the line.

getLevel() - Method in class javax.swing.tree.DefaultMutableTreeNode
Returns the number of levels above this node -- the distance from the root to this node.

getLimit() - Method in class javax.swing.undo.UndoManager
Returns the maximum number of edits this UndoManager will hold.

getLimits() - Method in class java.text.ChoiceFormat
Get the limits passed in the constructor.

getLine() - Method in class javax.sound.sampled.LineEvent
Obtains the audio line that is the source of this event.

getLine(Line.Info) - Method in interface javax.sound.sampled.Mixer
Obtains a line that is available for use and that matches the description in the specified Line.Info object.

getLine(Line.Info) - Static method in class javax.sound.sampled.AudioSystem
Obtains a line that matches the description in the specified Line.Info object.

getLineBreakIndex(int, float) - Method in class java.awt.font.TextMeasurer
Returns the index of the first character which will not fit on on a line which begins at start and may be up to maxAdvance in graphical width.

getLineBuffer() - Method in class javax.swing.text.PlainView
Gives access to a buffer that can be used to fetch text from the associated document.

getLineBuffer() - Method in class javax.swing.text.WrappedPlainView
Gives access to a buffer that can be used to fetch text from the associated document.

getLineClass() - Method in class javax.sound.sampled.Line.Info
Obtains the class of the line that this Line.Info object describes.

getLineColor() - Method in class javax.swing.border.LineBorder
Returns the color of the border.

getLineCount() - Method in class javax.swing.JTextArea
Determines the number of lines contained in the area.

getLineEndOffset(int) - Method in class javax.swing.JTextArea

Determines the offset of the end of the given line.

[getLineIncrement\(\)](#) - Method in class java.awt.[Scrollbar](#)
 Deprecated. As of JDK version 1.1, replaced by [getUnitIncrement\(\)](#).

[getLineInfo\(\)](#) - Method in interface javax.sound.sampled.[Line](#)
 Obtains the Line.Info object describing this line.

[getLineInstance\(\)](#) - Static method in class java.text.[BreakIterator](#)
 Create BreakIterator for line-breaks using default locale.

[getLineInstance\(Locale\)](#) - Static method in class java.text.[BreakIterator](#)
 Create BreakIterator for line-breaks using specified locale.

[getLineJoin\(\)](#) - Method in class java.awt.[BasicStroke](#)
 Returns the line join style.

[getLineLength\(\)](#) - Method in class javax.swing.text.[AbstractWriter](#)
 Returns the maximum line length.

[getLineMetrics\(char\[\], int, int, FontRenderContext\)](#) - Method in class java.awt.[Font](#)
 Returns a LineMetrics object created with the specified arguments.

[getLineMetrics\(char\[\], int, int, Graphics\)](#) - Method in class java.awt.[FontMetrics](#)
 Returns the [LineMetrics](#) object for the specified character array in the specified [Graphics](#) context.

[getLineMetrics\(CharacterIterator, int, int, FontRenderContext\)](#) - Method in class java.awt.[Font](#)
 Returns a LineMetrics object created with the specified arguments.

[getLineMetrics\(CharacterIterator, int, int, Graphics\)](#) - Method in class java.awt.[FontMetrics](#)
 Returns the [LineMetrics](#) object for the specified [CharacterIterator](#) in the specified [Graphics](#) context.

[getLineMetrics\(String, FontRenderContext\)](#) - Method in class java.awt.[Font](#)
 Returns a [LineMetrics](#) object created with the specified String and [FontRenderContext](#).

[getLineMetrics\(String, Graphics\)](#) - Method in class java.awt.[FontMetrics](#)
 Returns the [LineMetrics](#) object for the specified String in the specified [Graphics](#) context.

[getLineMetrics\(String, int, int, FontRenderContext\)](#) - Method in class java.awt.[Font](#)
 Returns a LineMetrics object created with the specified arguments.

[getLineMetrics\(String, int, int, Graphics\)](#) - Method in class java.awt.[FontMetrics](#)
 Returns the [LineMetrics](#) object for the specified String in the specified [Graphics](#) context.

[getLineNumber\(\)](#) - Method in class java.io.[LineNumberReader](#)
 Get the current line number.

[getLineNumber\(\)](#) - Method in class java.io.[LineNumberInputStream](#)
 Deprecated. Returns the current line number.

[getLineOfOffset\(int\)](#) - Method in class javax.swing.[JTextArea](#)
 Translates an offset into the components text to a line number.

[getLineSeparator\(\)](#) - Method in class javax.swing.text.[AbstractWriter](#)
 Returns the string used to represent newlines.

[getLineSpacing\(AttributeSet\)](#) - Static method in class javax.swing.text.[StyleConstants](#)
 Gets the line spacing setting.

[getLineStartOffset\(int\)](#) - Method in class javax.swing.[JTextArea](#)
 Determines the offset of the start of the given line.

[getLineWidth\(\)](#) - Method in class java.awt.[BasicStroke](#)
 Returns the line width.

[getLineWrap\(\)](#) - Method in class javax.swing.[JTextArea](#)
 Gets the line-wrapping policy of the text area.

[getLink\(int\)](#) - Method in interface javax.accessibility.[AccessibleHypertext](#)
 Returns the nth Link of this Hypertext document.

[getLink\(int\)](#) - Method in class javax.swing.JEditorPane.[JEditorPaneAccessibleHypertextSupport](#)
 Returns the index into an array of hyperlinks that index.

[getLinkCount\(\)](#) - Method in interface javax.accessibility.[AccessibleHypertext](#)
 Returns the number of links within this hypertext document.

[getLinkCount\(\)](#) - Method in class javax.swing.JEditorPane.[JEditorPaneAccessibleHypertextSupport](#)
 Returns the number of links within this hypertext doc.

[getLinkCursor\(\)](#) - Method in class javax.swing.text.html.[HTMLEditorKit](#)
 Returns the cursor to use over hyper links.

getLinkExplanation() - Method in class javax.naming.LinkException

Retrieves the explanation associated with the problem encounter when resolving a link.

getLinkIndex(int) - Method in interface javax.accessibility.AccessibleHypertext

Returns the index into an array of hyperlinks that is associated with this character index, or -1 if there is no hyperlink associated with this index.

getLinkIndex(int) - Method in class javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport

Returns the index into an array of hyperlinks that is associated with this character index, or -1 if there is no hyperlink associated with this index.

getLinkName() - Method in class javax.naming.LinkRef

Retrieves the name of this link.

getLinkRemainingName() - Method in class javax.naming.LinkException

Retrieves the remaining unresolved portion of the link name.

getLinkResolvedName() - Method in class javax.naming.LinkException

Retrieves the leading portion of the link name that was resolved successfully.

getLinkResolvedObj() - Method in class javax.naming.LinkException

Retrieves the object to which resolution was successful.

getLinkText(int) - Method in class javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport

Returns the contiguous text within the document that is associated with this hyperlink.

getList() - Method in class javax.swing.plaf.basic.BasicComboPopup

Implementation of ComboPopup.getList().

getList() - Method in interface javax.swing.plaf.basic.ComboPopup

Returns the list that is being used to draw the items in the JComboBox.

getListCellRendererComponent(JList, Object, int, boolean, boolean) - Method in class javax.swing.DefaultListCellRenderer

getListCellRendererComponent(JList, Object, int, boolean, boolean) - Method in interface javax.swing.ListCellRenderer

Return a component that has been configured to display the specified value.

getListCellRendererComponent(JList, Object, int, boolean, boolean) - Method in class javax.swing.plaf.basic.BasicComboBoxRenderer

getListCellRendererComponent(JList, Object, int, boolean, boolean) - Method in class javax.swing.plaf.metal.MetalFileChooserUI.FileRenderer

getListCellRendererComponent(JList, Object, int, boolean, boolean) - Method in class javax.swing.plaf.metal.MetalFileChooserUI.FilterComboBoxRenderer

getListenerCount() - Method in class javax.swing.event.EventListenerList

Returns the total number of listeners for this listener list.

getListenerCount(Class) - Method in class javax.swing.event.EventListenerList

Returns the total number of listeners of the supplied type for this listener list.

getListenerList() - Method in class javax.swing.event.EventListenerList

Passes back the event listener list as an array of ListenerType-listener pairs.

getListenerMethodDescriptors() - Method in class java.beans.EventSetDescriptor

Gets the MethodDescriptors of the target listener interface.

getListenerMethods() - Method in class java.beans.EventSetDescriptor

Gets the methods of the target listener interface.

getListeners(Class) - Method in class java.awt.Component

Return an array of all the listeners that were added to the Component with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Container

Return an array of all the listeners that were added to the Container with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Scrollbar

Return an array of all the listeners that were added to the Scrollbar with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.MenuItem

Return an array of all the listeners that were added to the MenuItem with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Checkbox
Return an array of all the listeners that were added to the Checkbox with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Window
Return an array of all the listeners that were added to the Window with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.List
Return an array of all the listeners that were added to the List with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.TextComponent
Return an array of all the listeners that were added to the TextComponent with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Choice
Return an array of all the listeners that were added to the Choice with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.TextField
Return an array of all the listeners that were added to the TextField with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.Button
Return an array of all the listeners that were added to the Button with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class java.awt.CheckboxMenuItem
Return an array of all the listeners that were added to the CheckboxMenuItem with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class javax.swing.DefaultSingleSelectionModel
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.JComponent
Return an array of all the listeners that were added to this JComponent with addXXXListener(), where XXX is the name of the listenerType argument.

getListeners(Class) - Method in class javax.swing.DefaultBoundedRangeModel
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.AbstractListModel
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.DefaultListSelectionModel
Returns an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.Timer
Return an array of all the listeners of the given type that were added to this timer.

getListeners(Class) - Method in class javax.swing.DefaultButtonModel
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.event.EventListenerList
Return an array of all the listeners of the given type.

getListeners(Class) - Method in class javax.swing.table.AbstractTableModel
Returns an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.table.DefaultTableColumnModel
Returns an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.text.StyleContext.NamedStyle
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.text.AbstractDocument
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.text.DefaultCaret
Return an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.tree.DefaultTreeSelectionModel
Returns an array of all the listeners of the given type that were added to this model.

getListeners(Class) - Method in class javax.swing.tree.DefaultTreeModel
Return an array of all the listeners of the given type that were added to this model.

[getListenerType\(\)](#) - Method in class java.beans.[EventSetDescriptor](#)
Gets the Class object for the target interface.

[getListPainter\(AttributeSet\)](#) - Method in class javax.swing.text.html.[StyleSheet](#)
Fetches the list formatter to use for the given set of CSS attributes.

[getLoadedInstruments\(\)](#) - Method in interface javax.sound.midi.[Synthesizer](#)
Obtains a list of the instruments that are currently loaded onto this Synthesizer.

[getLocalAddress\(\)](#) - Method in class java.net.[DatagramSocket](#)
Gets the local address to which the socket is bound.

[getLocalAddress\(\)](#) - Method in class java.net.[Socket](#)
Gets the local address to which the socket is bound.

[getLocalBounds\(Component\)](#) - Static method in class javax.swing.[SwingUtilities](#)
Return the rectangle (0,0,bounds.width,bounds.height) for the component aComponent

[getLocale\(\)](#) - Method in class java.applet.[Applet](#)
Gets the Locale for the applet, if it has been set.

[getLocale\(\)](#) - Method in class java.awt.[Component](#)
Gets the locale of this component.

[getLocale\(\)](#) - Method in class java.awt.[Component.AccessibleAWTComponent](#)
Return the locale of this object.

[getLocale\(\)](#) - Method in class java.awt.[MenuComponent.AccessibleAWTMenuComponent](#)
Return the locale of this object.

[getLocale\(\)](#) - Method in class java.awt.[Window](#)
Gets the Locale object that is associated with this window, if the locale has been set.

[getLocale\(\)](#) - Method in class java.awt.[List.AccessibleAWTList.AccessibleAWTListChild](#)
Gets the locale of the component.

[getLocale\(\)](#) - Method in class java.awt.im.[InputContext](#)
Returns the current locale of the current input method.

[getLocale\(\)](#) - Method in interface java.awt.im.spi.[InputMethod](#)
Returns the current input locale.

[getLocale\(\)](#) - Method in class java.beans.beancontext.[BeanContextSupport](#)
Gets the locale for this BeanContext.

[getLocale\(\)](#) - Method in class java.text.[MessageFormat](#)
Gets the locale.

[getLocale\(\)](#) - Method in class java.util.[ResourceBundle](#)
Return the Locale for this ResourceBundle.

[getLocale\(\)](#) - Method in class javax.accessibility.[AccessibleContext](#)
Gets the locale of the component.

[getLocale\(\)](#) - Method in class javax.swing.[JList.AccessibleJList.AccessibleJListChild](#)

[getLocale\(\)](#) - Method in class javax.swing.[JTree.AccessibleJTree.AccessibleJTreeNode](#)
Gets the locale of the component.

[getLocale\(\)](#) - Method in class javax.swing.[JTable.AccessibleJTable.AccessibleJTableCell](#)
Gets the locale of the component.

[getLocale\(\)](#) - Method in class javax.swing.[ImageIcon.AccessibleImageIcon](#)
Returns the locale of this object.

[getLocale\(\)](#) - Method in class
javax.swing.table.[JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getLocalGraphicsEnvironment\(\)](#) - Static method in class java.awt.[GraphicsEnvironment](#)
Returns the local GraphicsEnvironment.

[getLocalHost\(\)](#) - Static method in class java.net.[InetAddress](#)
Returns the local host.

[getLocalizedInputStream\(InputStream\)](#) - Method in class java.lang.[Runtime](#)
Deprecated. *As of JDK 1.1, the preferred way translate a byte stream in the local encoding into a character stream in Unicode is via the [InputStreamReader](#) and [BufferedReader](#) classes.*

[getLocalizedMessage\(\)](#) - Method in class java.lang.[Throwable](#)
Creates a localized description of this Throwable.

[getLocalizedOutputStream\(OutputStream\)](#) - Method in class java.lang.[Runtime](#)

Deprecated. As of JDK 1.1, the preferred way to translate a Unicode character stream into a byte stream in the local encoding is via the *OutputStreamWriter*, *BufferedWriter*, and *PrintWriter* classes.

getLocalPatternChars() - Method in class java.text.DateFormatSymbols

Gets localized date-time pattern characters.

getLocalPort() - Method in class java.net.DatagramSocket

Returns the port number on the local host to which this socket is bound.

getLocalPort() - Method in class java.net.SocketImpl

Returns the value of this socket's localport field.

getLocalPort() - Method in class java.net.Socket

Returns the local port to which this socket is bound.

getLocalPort() - Method in class java.net.ServerSocket

Returns the port on which this socket is listening.

getLocalPort() - Method in class java.net.DatagramSocketImpl

Gets the local port.

getLocation() - Method in class java.awt.Component

Gets the location of this component in the form of a point specifying the component's top-left corner.

getLocation() - Method in class java.awt.Component.AccessibleAWTComponent

Gets the location of the object relative to the parent in the form of a point specifying the object's top-left corner in the screen's coordinate space.

getLocation() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent

Gets the location of the object relative to the parent in the form of a point specifying the object's top-left corner in the screen's coordinate space.

getLocation() - Method in class java.awt.Point

Returns the location of this point.

getLocation() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild

Gets the location of the object relative to the parent in the form of a point specifying the object's top-left corner in the screen's coordinate space.

getLocation() - Method in class java.awt.Rectangle

Returns the location of this Rectangle.

getLocation() - Method in class java.awt.dnd.DropTargetDropEvent

This method returns a Point indicating the Cursor's current location in the Component's coordinates.

getLocation() - Method in class java.awt.dnd.DropTargetDragEvent

This method returns a Point indicating the Cursor's current location within the Component's coordinates.

getLocation() - Method in class java.rmi.activation.ActivationGroupDesc

Returns the group's code location.

getLocation() - Method in class java.rmi.activation.ActivationDesc

Returns the code location for the object specified by this descriptor.

getLocation() - Method in class java.security.CodeSource

Returns the location associated with this CodeSource.

getLocation() - Method in interface javax.accessibility.AccessibleComponent

Gets the location of the object relative to the parent in the form of a point specifying the object's top-left corner in the screen's coordinate space.

getLocation() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getLocation() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

getLocation() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

Gets the location of the object relative to the parent in the form of a point specifying the object's top-left corner in the screen's coordinate space.

getLocation() - Method in class

javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getLocation(Point) - Method in class java.awt.Component

Store the x,y origin of this component into "return value" rv and return rv.

[getLocation\(Point\)](#) - Method in class [javax.swing.JComponent](#)
Stores the x,y origin of this component into "return value" rv and returns rv.

[getLocationInJTree\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

[getLocationOffset\(int, int\)](#) - Method in interface [java.awt.im.InputMethodRequests](#)
Gets the offset within the composed text for the specified absolute x and y coordinates on the screen.

[getLocationOnScreen\(\)](#) - Method in class [java.awt.Component](#)
Gets the location of this component in the form of a point specifying the component's top-left corner in the screen's coordinate space.

[getLocationOnScreen\(\)](#) - Method in class [java.awt.Component.AccessibleAWTComponent](#)
Returns the location of the object on the screen.

[getLocationOnScreen\(\)](#) - Method in class [java.awt.MenuComponent.AccessibleAWTMenuComponent](#)
Returns the location of the object on the screen.

[getLocationOnScreen\(\)](#) - Method in class [java.awt.List.AccessibleAWTList.AccessibleAWTListChild](#)
Returns the location of the object on the screen.

[getLocationOnScreen\(\)](#) - Method in interface [javax.accessibility.AccessibleComponent](#)
Returns the location of the object on the screen.

[getLocationOnScreen\(\)](#) - Method in class [javax.swing.JList.AccessibleJList.AccessibleJListChild](#)

[getLocationOnScreen\(\)](#) - Method in class [javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode](#)

[getLocationOnScreen\(\)](#) - Method in class [javax.swing.JTable.AccessibleJTable.AccessibleJTableCell](#)
Returns the location of the object on the screen.

[getLocationOnScreen\(\)](#) - Method in class [javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry](#)

[getLockingKeyState\(int\)](#) - Method in class [java.awt.Toolkit](#)
Returns whether the given locking key on the keyboard is currently in its "on" state.

[getLog\(\)](#) - Static method in class [java.rmi.server.RemoteServer](#)
Returns stream for the RMI call log.

[getLogicalBounds\(\)](#) - Method in class [java.awt.font.GlyphVector](#)
Returns the logical bounds of this GlyphVector.

[getLogicalHighlightShape\(int, int\)](#) - Method in class [java.awt.font.TextLayout](#)
Returns a Shape enclosing the logical selection in the specified range, extended to the natural bounds of this TextLayout.

[getLogicalHighlightShape\(int, int, Rectangle2D\)](#) - Method in class [java.awt.font.TextLayout](#)
Returns a Shape enclosing the logical selection in the specified range, extended to the specified bounds.

[getLogicalRangesForVisualSelection\(TextHitInfo, TextHitInfo\)](#) - Method in class [java.awt.font.TextLayout](#)
Returns the logical ranges of text corresponding to a visual selection.

[getLogicalStyle\(\)](#) - Method in class [javax.swing.JTextPane](#)
Fetches the logical style assigned to the paragraph represented by the current position of the caret, or null.

[getLogicalStyle\(int\)](#) - Method in interface [javax.swing.text.StyledDocument](#)
Gets a logical style for a given position in a paragraph.

[getLogicalStyle\(int\)](#) - Method in class [javax.swing.text.DefaultStyledDocument](#)
Fetches the logical style assigned to the paragraph represented by the given position.

[getLogicalView\(FlowView\)](#) - Method in class [javax.swing.text.FlowView.FlowStrategy](#)
This method gives flow strategies access to the logical view of the FlowView.

[getLoginTimeout\(\)](#) - Static method in class [java.sql.DriverManager](#)
Gets the maximum time in seconds that a driver can wait when attempting to log in to a database.

[getLogStream\(\)](#) - Static method in class [java.sql.DriverManager](#)
Deprecated.

getLogTimers() - Static method in class [javax.swing.Timer](#)
Returns true if logging is enabled.

getLogWriter() - Static method in class [java.sql.DriverManager](#)
Gets the log writer.

getLong(int) - Method in interface [java.sql.CallableStatement](#)
Gets the value of a JDBC BIGINT parameter as a long in the Java programming language.

getLong(int) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a long in the Java programming language.

getLong(Object) - Method in class [java.lang.reflect.Field](#)
Gets the value of a field as a long on the specified object.

getLong(Object, int) - Static method in class [java.lang.reflect.Array](#)
Returns the value of the indexed component in the specified array object, as a long.

getLong(String) - Static method in class [java.lang.Long](#)
Determines the long value of the system property with the specified name.

getLong(String) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a long in the Java programming language.

getLong(String, long) - Static method in class [java.lang.Long](#)
Determines the long value of the system property with the specified name.

getLong(String, Long) - Static method in class [java.lang.Long](#)
Returns the long value of the system property with the specified name.

getLongParameter(int) - Method in class [java.awt.image.renderable.ParameterBlock](#)
A convenience method to return a parameter as a long.

getLookAndFeel() - Static method in class [javax.swing.UIManager](#)
Returns The current default look and feel, or null.

getLookAndFeelDefaults() - Static method in class [javax.swing.UIManager](#)
Returns the default values for this look and feel.

getLoweredBevelBorderUIResource() - Static method in class [javax.swing.plaf.BorderUIResource](#)

getLowestSetBit() - Method in class [java.math.BigInteger](#)
Returns the index of the rightmost (lowest-order) one bit in this BigInteger (the number of zero bits to the right of the rightmost one bit).

getLowestValueLabel() - Method in class [javax.swing.plaf.basic.BasicSliderUI](#)
Returns the label that corresponds to the highest slider value in the label table.

getLSB() - Method in class [java.awt.font.GlyphMetrics](#)
Returns the left (top) side bearing of the glyph.

getMagicCaretPosition() - Method in class [javax.swing.text.DefaultCaret](#)
Gets the saved caret position.

getMagicCaretPosition() - Method in interface [javax.swing.text.Caret](#)
Gets the current caret visual location.

getMainAttributes() - Method in class [java.net.JarURLConnection](#)
Returns the main Attributes for the JAR file for this connection.

getMainAttributes() - Method in class [java.util.jar.Manifest](#)
Returns the main Attributes for the Manifest.

getMajorAxis() - Method in class [javax.swing.text.AsyncBoxView](#)
Fetch the major axis (the axis the children are tiled along).

getMajorOffset() - Method in class [javax.swing.text.AsyncBoxView.ChildState](#)
Get the offset along the major axis

getMajorSpan() - Method in class [javax.swing.text.AsyncBoxView.ChildState](#)
What is the span along the major axis.

getMajorTickSpacing() - Method in class [javax.swing.JSlider](#)
This method returns the major tick spacing.

getMajorVersion() - Method in class [java.awt.color.ICC_Profile](#)
Returns profile major version.

getMajorVersion() - Method in interface [java.sql.Driver](#)
Gets the driver's major version number.

getManifest() - Method in class java.net.JarURLConnection
Returns the Manifest for this connection, or null if none.

getManifest() - Method in class java.util.jar.JarInputStream
Returns the Manifest for this JAR file, or null if none.

getManifest() - Method in class java.util.jar.JarFile
Returns the JAR file manifest, or null if none.

getMapSize() - Method in class java.awt.image.IndexColorModel
Returns the size of the color/alpha component arrays in this IndexColorModel.

getMargin() - Method in class javax.swing.AbstractButton
Returns the margin between the button's border and the label.

getMargin() - Method in class javax.swing.JPopupMenu
Returns the margin, in pixels, between the popup menu's border and its containees.

getMargin() - Method in class javax.swing.JToolBar
Returns the margin between the toolbar's border and its buttons.

getMargin() - Method in class javax.swing.JMenuBar
Returns the margin between the menubar's border and its menus.

getMargin() - Method in class javax.swing.text.JTextComponent
Returns the margin between the text component's border and its text.

getMark() - Method in class javax.swing.event.CaretEvent
Fetches the location of other end of a logical selection.

getMark() - Method in class javax.swing.text.DefaultCaret
Fetches the current position of the mark.

getMark() - Method in interface javax.swing.text.Caret
Fetches the current position of the mark.

getMask(int) - Method in class java.awt.image.PackedColorModel
Returns the mask indicating which bits in a pixel contain the specified color/alpha sample.

getMasks() - Method in class java.awt.image.PackedColorModel
Returns a mask array indicating which bits in a pixel contain the color and alpha samples.

getMasterSyncMode() - Method in interface javax.sound.midi.Sequencer
Obtains the current master synchronization mode for this sequencer.

getMasterSyncModes() - Method in interface javax.sound.midi.Sequencer
Obtains the set of master synchronization modes supported by this sequencer.

getMatrix() - Method in class java.awt.color.ICC_ProfileRGB
Returns a 3x3 float matrix constructed from the X, Y, and Z components of the redColorantTag, greenColorantTag, and blueColorantTag in the ICC profile, as described above.

getMatrix() - Method in class java.awt.image.BandCombineOp
Returns the matrix.

getMatrix() - Method in class java.awt.print.PageFormat
Returns a transformation matrix that translates user space rendering to the requested orientation of the page.

getMatrix(double[]) - Method in class java.awt.geom.AffineTransform
Retrieves the 6 specifiable values in the 3x3 affine transformation matrix and places them into an array of double precisions values.

getMatteColor() - Method in class javax.swing.border.MatteBorder
Returns the color used for tiling the border or null if a tile icon is being used.

getMaxAdvance() - Method in class java.awt.FontMetrics
Gets the maximum advance width of any character in this Font.

getMaxAscent() - Method in class java.awt.FontMetrics
Determines the maximum ascent of the Font described by this FontMetrics object.

getMaxBinaryLiteralLength() - Method in interface java.sql.DatabaseMetaData
How many hex characters can you have in an inline binary literal?

getMaxBufferSize() - Method in class javax.sound.sampled.DataLine.Info
Obtains the maximum buffer size supported by the data line.

getMaxCatalogNameLength() - Method in interface java.sql.DatabaseMetaData
What's the maximum length of a catalog name?

getMaxCharactersPerLineCount() - Method in class javax.swing.JOptionPane
Returns the maximum number of characters to place on a line in a message.

getMaxCharactersPerLineCount() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Returns the maximum number of characters to place on a line.

getMaxCharBounds(FontRenderContext) - Method in class java.awt.Font
Returns the bounds for the character with the maximum bounds as defined in the specified FontRenderContext.

getMaxCharBounds(Graphics) - Method in class java.awt.FontMetrics
Returns the bounds for the character with the maximum bounds in the specified Graphics context.

getMaxCharLiteralLength() - Method in interface java.sql.DatabaseMetaData
What's the max length for a character literal?

getMaxColumnNameLength() - Method in interface java.sql.DatabaseMetaData
What's the limit on column name length?

getMaxColumnsInGroupBy() - Method in interface java.sql.DatabaseMetaData
What's the maximum number of columns in a "GROUP BY" clause?

getMaxColumnsInIndex() - Method in interface java.sql.DatabaseMetaData
What's the maximum number of columns allowed in an index?

getMaxColumnsInOrderBy() - Method in interface java.sql.DatabaseMetaData
What's the maximum number of columns in an "ORDER BY" clause?

getMaxColumnsInSelect() - Method in interface java.sql.DatabaseMetaData
What's the maximum number of columns in a "SELECT" list?

getMaxColumnsInTable() - Method in interface java.sql.DatabaseMetaData
What's the maximum number of columns in a table?

getMaxConnections() - Method in interface java.sql.DatabaseMetaData
How many active connections can we have at a time to this database?

getMaxCursorNameLength() - Method in interface java.sql.DatabaseMetaData
What's the maximum cursor name length?

getMaxDecent() - Method in class java.awt.FontMetrics
Deprecated. *As of JDK version 1.1.1, replaced by getMaxDescent().*

getMaxDescent() - Method in class java.awt.FontMetrics
Determines the maximum descent of the Font described by this FontMetrics object.

getMaxExpansion(int) - Method in class java.text.CollationElementIterator
Return the maximum length of any expansion sequences that end with the specified comparison order.

getMaxFieldSize() - Method in interface java.sql.Statement
Returns the maximum number of bytes allowed for any column value.

getMaximum() - Method in class java.awt.Scrollbar
Gets the maximum value of this scroll bar.

getMaximum() - Method in interface java.awt.Adjustable
Gets the maximum value of the adjustable object.

getMaximum() - Method in class javax.sound.sampled.FloatControl
Obtains the maximum value permitted.

getMaximum() - Method in class javax.swing.DefaultBoundedRangeModel
Return the model's maximum.

getMaximum() - Method in class javax.swing.ProgressMonitor
Returns the maximum value -- the higher end of the progress value.

getMaximum() - Method in interface javax.swing.BoundedRangeModel
Returns the model's maximum.

getMaximum() - Method in class javax.swing.JScrollbar
The maximum value of the scrollbar is maximum - extent.

getMaximum() - Method in class javax.swing.JProgressBar
Returns the model's maximum value.

getMaximum() - Method in class javax.swing.JSlider
Returns the maximum value supported by the slider.

getMaximum(int) - Method in class java.util.Calendar
Gets the maximum value for the given time field.

getMaximum(int) - Method in class java.util.GregorianCalendar
Returns maximum value for the given field.

[getMaximumAccessibleValue\(\)](#) - Method in class java.awt.[Scrollbar.AccessibleAWTScrollbar](#)
Get the maximum accessible value of this object.

[getMaximumAccessibleValue\(\)](#) - Method in class java.awt.[MenuItem.AccessibleAWTMenuItem](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class java.awt.[Checkbox.AccessibleAWTCheckbox](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class java.awt.[Button.AccessibleAWTButton](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class
java.awt.[CheckboxMenuItem.AccessibleAWTCheckboxMenuItem](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in interface javax.accessibility.[AccessibleValue](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[AbstractButton.AccessibleAbstractButton](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[JInternalFrame.AccessibleJInternalFrame](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class
javax.swing.[JInternalFrame.JDesktopIcon.AccessibleJDesktopIcon](#)
Get the maximum value of this object as a Number.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[JSplitPane.AccessibleJSplitPane](#)
Gets the maximum accessible value of this object.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[JScrollbar.AccessibleJScrollbar](#)
Get the maximum accessible value of this object.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[JProgressBar.AccessibleJProgressBar](#)
Get the maximum accessible value of this object.

[getMaximumAccessibleValue\(\)](#) - Method in class javax.swing.[JSlider.AccessibleJSlider](#)
Get the maximum accessible value of this object.

[getMaximumCursorColors\(\)](#) - Method in class java.awt.[Toolkit](#)
Returns the maximum number of colors the Toolkit supports in a custom cursor palette.

[getMaximumDividerLocation\(\)](#) - Method in class javax.swing.[JSplitPane](#)
Returns the maximum location of the divider from the look and feel implementation.

[getMaximumDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.[SplitPaneUI](#)
Returns the maximum possible location of the divider.

[getMaximumDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneUI](#)
Gets the maximum location of the divider.

[getMaximumDividerLocation\(JSplitPane\)](#) - Method in class javax.swing.plaf.multi.[MultiSplitPaneUI](#)
Call [getMaximumDividerLocation](#) on each UI handled by this MultiUI.

[getMaximumFractionDigits\(\)](#) - Method in class java.text.[NumberFormat](#)
Returns the maximum number of digits allowed in the fraction portion of a number.

[getMaximumIntegerDigits\(\)](#) - Method in class java.text.[NumberFormat](#)
Returns the maximum number of digits allowed in the integer portion of a number.

[getMaximumRowCount\(\)](#) - Method in class javax.swing.[JComboBox](#)
Returns the maximum number of items the combo box can display without a scrollbar

[getMaximumSize\(\)](#) - Method in class java.awt.[Component](#)
Gets the maximum size of this component.

[getMaximumSize\(\)](#) - Method in class java.awt.[Container](#)
Returns the maximum size of this container.

[getMaximumSize\(\)](#) - Method in class javax.swing.[JComponent](#)
If the maximum size has been set to a non-null value just returns it.

[getMaximumSize\(\)](#) - Method in class javax.swing.[JToolBar.Separator](#)
Returns the maximum size for the separator.

[getMaximumSize\(\)](#) - Method in class javax.swing.[Box.Filler](#)
Returns the maximum size of the component.

[getMaximumSize\(\)](#) - Method in class javax.swing.[JScrollbar](#)
The scrollbar is flexible along it's scrolling axis and rigid along the other axis.

[getMaximumSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicArrowButton](#)

getMaximumSize() - Method in class javax.swing.plaf.metal.MetalScrollbarUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.ComponentUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTextUI
Gets the maximum size for the editor component.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSeparatorUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuItemUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicButtonUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolBarSeparatorUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicProgressBarUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Messages getPreferredSize.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicPopupMenuUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTableUI
Return the maximum size of the table.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolTipUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicScrollbarUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolBarUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicListUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicLabelUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTableHeaderUI
Return the maximum size of the header.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuBarUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTreeUI
Returns the maximum size for this component, which will be the preferred size if the instance is currently in a JTree, or 0, 0.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSplitPaneUI
Returns the maximum size for the passed in component, This is passed off to the current layoutmanager.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicScrollPaneUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopIconUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSliderUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiListUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSeparatorUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiLabelUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPopupMenuUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPanelUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollbarUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTextUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiComboBoxUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTableHeaderUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiFileChooserUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiColorChooserUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTreeUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiViewportUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTabbedPaneUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiProgressBarUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollPaneUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiOptionPaneUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSplitPaneUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiButtonUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiToolBarUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSliderUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiDesktopPaneUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTableUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiDesktopIconUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiMenuItemUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiInternalFrameUI
 Call getMaximumSize on each UI handled by this MultiUI.

getMaximumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiToolTipUI

Call `getMaximumSize` on each UI handled by this `MultiUI`.

`getMaximumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuBarUI`

Call `getMaximumSize` on each UI handled by this `MultiUI`.

`getMaximumSpan(int)` - Method in class `javax.swing.text.View`

Determines the maximum span for this view along an axis.

`getMaximumSpan(int)` - Method in class `javax.swing.text.BoxView`

Determines the maximum span for this view along an axis.

`getMaximumSpan(int)` - Method in class `javax.swing.text.AsyncBoxView`

Determines the maximum span for this view along an axis.

`getMaximumSpan(int)` - Method in class `javax.swing.text.ComponentView`

Determines the maximum span for this view along an axis.

`getMaximumSpan(int)` - Method in class `javax.swing.text.WrappedPlainView`

Determines the maximum span for this view along an axis.

`getMaximumSpan(int)` - Method in class `javax.swing.text.html.ParagraphView`

Determines the maximum span for this view along an axis.

`getMaximumThumbSize()` - Method in class `javax.swing.plaf.basic.BasicScrollBarUI`

Return the largest acceptable size for the thumb.

`getMaximumZoneSize()` - Method in class `javax.swing.text.ZoneView`

Get the current maximum zone size.

`getMaxIndexLength()` - Method in interface `java.sql.DatabaseMetaData`

Retrieves the maximum number of bytes for an index, including all of the parts of the index.

`getMaxLabel()` - Method in class `javax.sound.sampled.FloatControl`

Obtains the label for the maximum value, such as "Right" or "Full."

`getMaxLines(Line.Info)` - Method in interface `javax.sound.sampled.Mixer`

Obtains the maximum number of lines of the requested type that can be open simultaneously on the mixer.

`getMaxPage()` - Method in class `java.awt.JobAttributes`

Specifies the maximum value the user can specify as the last page to be printed for jobs using these attributes.

`getMaxPolyphony()` - Method in interface `javax.sound.midi.Synthesizer`

Obtains the maximum number of notes that this synthesizer can sound simultaneously.

`getMaxPriority()` - Method in class `java.lang.ThreadGroup`

Returns the maximum priority of this thread group.

`getMaxProcedureNameLength()` - Method in interface `java.sql.DatabaseMetaData`

What's the maximum length of a procedure name?

`getMaxReceivers()` - Method in interface `javax.sound.midi.MidiDevice`

Obtains the maximum number of MIDI IN connections available on this MIDI device for receiving MIDI data.

`getMaxRows()` - Method in interface `java.sql.Statement`

Retrieves the maximum number of rows that a `ResultSet` object can contain.

`getMaxRowSize()` - Method in interface `java.sql.DatabaseMetaData`

What's the maximum length of a single row?

`getMaxSchemaNameLength()` - Method in interface `java.sql.DatabaseMetaData`

What's the maximum length allowed for a schema name?

`getMaxSelectionIndex()` - Method in class `javax.swing.DefaultListSelectionModel`

`getMaxSelectionIndex()` - Method in class `javax.swing.JList`

Returns the largest selected cell index.

`getMaxSelectionIndex()` - Method in interface `javax.swing.ListSelectionModel`

Returns the last selected index or -1 if the selection is empty.

`getMaxSelectionRow()` - Method in class `javax.swing.JTree`

Returns the last selected row.

`getMaxSelectionRow()` - Method in class `javax.swing.tree.DefaultTreeSelectionModel`

Returns the largest value obtained from the `RowMapper` for the current set of selected `TreePaths`.

`getMaxSelectionRow()` - Method in interface `javax.swing.tree.TreeSelectionModel`

Returns the largest value obtained from the `RowMapper` for the current set of selected

TreePaths.

getMaxStatementLength() - Method in interface java.sql.DatabaseMetaData

What's the maximum length of an SQL statement?

getMaxStatements() - Method in interface java.sql.DatabaseMetaData

How many active statements can we have open at one time to this database?

getMaxTableNameLength() - Method in interface java.sql.DatabaseMetaData

What's the maximum length of a table name?

getMaxTablesInSelect() - Method in interface java.sql.DatabaseMetaData

What's the maximum number of tables in a SELECT statement?

getMaxTransmitters() - Method in interface javax.sound.midi.MidiDevice

Obtains the maximum number of MIDI OUT connections available on this MIDI device for transmitting MIDI data.

getMaxUserNameLength() - Method in interface java.sql.DatabaseMetaData

What's the maximum length of a user name?

getMaxWidth() - Method in class javax.swing.table.TableColumn

Returns the maximum width for the TableColumn.

getMaxX() - Method in class java.awt.geom.RectangularShape

Returns the largest X coordinate of the framing rectangle of the Shape in double precision.

getMaxY() - Method in class java.awt.geom.RectangularShape

Returns the largest Y coordinate of the framing rectangle of the Shape in double precision.

getMaxZonesLoaded() - Method in class javax.swing.text.ZoneView

Get the current setting of the number of zones allowed to be loaded at the same time.

getMedia() - Method in class java.awt.PageAttributes

Returns the paper size for pages using these attributes.

getMediaWhitePoint() - Method in class java.awt.color.ICC_ProfileGray

Returns a float array of length 3 containing the X, Y, and Z components of the mediaWhitePointTag in the ICC profile.

getMediaWhitePoint() - Method in class java.awt.color.ICC_ProfileRGB

Returns a float array of length 3 containing the X, Y, and Z components of the mediaWhitePointTag in the ICC profile.

getMemberControls() - Method in class javax.sound.sampled.CompoundControl

Returns the set of member controls that comprise the compound control.

getMenu(int) - Method in class java.awt.MenuBar

Gets the specified menu.

getMenu(int) - Method in class javax.swing.JMenuBar

Returns the menu at the specified position in the menu bar.

getMenuArrowIcon() - Static method in class javax.swing.plaf.basic.BasicIconFactory

getMenuArrowIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getMenuBackground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getMenuBackground() - Method in class javax.swing.plaf.metal.MetalTheme

getMenuBar() - Method in class java.awt.Frame

Gets the menu bar for this frame.

getMenuBar() - Method in class javax.swing.JInternalFrame

Deprecated. *As of Swing version 1.0.3, replaced by getJMenuBar().*

getMenuBar() - Method in class javax.swing.JRootPane

Deprecated. *As of Swing version 1.0.3 replaced by getJMenuBar().*

getMenuBarBorder() - Static method in class javax.swing.plaf.basic.BasicBorders

getMenuComponent(int) - Method in class javax.swing.JMenu

Returns the component at position n.

getMenuComponentCount() - Method in class javax.swing.JMenu

Returns the number of components on the menu.

getMenuComponents() - Method in class javax.swing.JMenu

Returns an array of Components of the menu's subcomponents.

[getMenuCount\(\)](#) - Method in class java.awt.[MenuBar](#)
 Gets the number of menus on the menu bar.

[getMenuCount\(\)](#) - Method in class javax.swing.[JMenuBar](#)
 Returns the number of items in the menu bar.

[getMenuDisabledForeground\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getMenuDisabledForeground\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getMenuForeground\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getMenuForeground\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getMenuItemArrowIcon\(\)](#) - Static method in class javax.swing.plaf.basic.[BasicIconFactory](#)

[getMenuItemArrowIcon\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalIconFactory](#)

[getMenuItemCheckIcon\(\)](#) - Static method in class javax.swing.plaf.basic.[BasicIconFactory](#)

[getMenuItemCheckIcon\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalIconFactory](#)

[getMenuSelectedBackground\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getMenuSelectedBackground\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getMenuSelectedForeground\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getMenuSelectedForeground\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getMenuSelectionManager\(\)](#) - Method in class javax.swing.event.[MenuKeyEvent](#)
 Returns the current menu selection manager.

[getMenuSelectionManager\(\)](#) - Method in class javax.swing.event.[MenuDragMouseEvent](#)
 Returns the current menu selection manager.

[getMenuShortcutKeyMask\(\)](#) - Method in class java.awt.[Toolkit](#)
 Determines which modifier key is the appropriate accelerator key for menu shortcuts.

[getMenuTextFont\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getMenuTextFont\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getMenuTextFont\(\)](#) - Method in class javax.swing.plaf.metal.[DefaultMetalTheme](#)

[getMessage\(\)](#) - Method in class java.io.[InvalidClassException](#)
 Produce the message and include the classname, if present.

[getMessage\(\)](#) - Method in class java.io.[WriteAbortedException](#)
 Produce the message and include the message from the nested exception, if there is one.

[getMessage\(\)](#) - Method in class java.lang.[Throwable](#)
 Returns the error message string of this throwable object.

[getMessage\(\)](#) - Method in class java.rmi.[RemoteException](#)
 Returns the detail message, including the message from the nested exception if there is one.

[getMessage\(\)](#) - Method in class java.rmi.activation.[ActivationException](#)
 Produces the message, include the message from the nested exception if there is one.

[getMessage\(\)](#) - Method in class java.rmi.server.[ServerCloneException](#)
 Obtains the message, include the message from the nested exception if there is one.

[getMessage\(\)](#) - Method in class javax.sound.midi.[MidiMessage](#)
 Obtains the MIDI message data.

[getMessage\(\)](#) - Method in class javax.sound.midi.[MidiEvent](#)
 Obtains the MIDI message contained in the event.

getMessage() - Method in class javax.swing.JOptionPane
Returns the message-object this pane displays.

getMessage() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Returns the message to display from the JOptionPane the receiver is providing the look and feel for.

getMessageDigest() - Method in class java.security.DigestOutputStream
Returns the message digest associated with this stream.

getMessageDigest() - Method in class java.security.DigestInputStream
Returns the message digest associated with this stream.

getMessageType() - Method in class javax.swing.JOptionPane
Returns the message type.

getMetaData() - Method in interface java.sql.PreparedStatement
Gets the number, types and properties of a ResultSet object's columns.

getMetaData() - Method in interface java.sql.Connection
Gets the metadata regarding this connection's database.

getMetaData() - Method in interface java.sql.ResultSet
Retrieves the number, types and properties of this ResultSet object's columns.

getMethod() - Method in class java.beans.MethodDescriptor
Gets the method that this MethodDescriptor encapsulates.

getMethod() - Method in class java.util.zip.ZipEntry
Returns the compression method of the entry, or -1 if not specified.

getMethod(String, Class[]) - Method in class java.lang.Class
Returns a Method object that reflects the specified public member method of the class or interface represented by this Class object.

getMethodDescriptors() - Method in interface java.beans.BeanInfo
Gets the beans MethodDescriptors.

getMethodDescriptors() - Method in class java.beans.SimpleBeanInfo
Deny knowledge of methods.

getMethods() - Method in class java.lang.Class
Returns an array containing Method objects reflecting all the public *member* methods of the class or interface represented by this Class object, including those declared by the class or interface and those inherited from superclasses and superinterfaces.

getMicrosecondLength() - Method in interface javax.sound.sampled.Clip
Obtains the media duration in microseconds

getMicrosecondLength() - Method in class javax.sound.midi.Sequence
Obtains the duration of this sequence, expressed in microseconds.

getMicrosecondLength() - Method in class javax.sound.midi.MidiFileFormat
Obtains the length of the MIDI file, expressed in microseconds.

getMicrosecondLength() - Method in interface javax.sound.midi.Sequencer
Obtains the length of the current sequence, expressed in microseconds.

getMicrosecondPosition() - Method in interface javax.sound.sampled.DataLine
Obtains the current position in the audio data, in microseconds.

getMicrosecondPosition() - Method in interface javax.sound.midi.MidiDevice
Obtains the current time-stamp of the device, in microseconds.

getMicrosecondPosition() - Method in interface javax.sound.midi.Sequencer
Obtains the current position in the sequence, expressed in microseconds.

getMidiDevice(MidiDevice.Info) - Static method in class javax.sound.midi.MidiSystem
Obtains the requested MIDI device.

getMidiDeviceInfo() - Static method in class javax.sound.midi.MidiSystem
Obtains an array of information objects representing the set of all MIDI devices available on the system.

getMidiFileFormat(File) - Static method in class javax.sound.midi.MidiSystem
Obtains the MIDI file format of the specified File.

getMidiFileFormat(File) - Method in class javax.sound.midi.spi.MidiFileReader
Obtains the MIDI file format of the File provided.

getMidiFileFormat(InputStream) - Static method in class javax.sound.midi.MidiSystem
Obtains the MIDI file format of the data in the specified input stream.

getMidiFileFormat(InputStream) - Method in class `javax.sound.midi.spi.MidiFileReader`
Obtains the MIDI file format of the input stream provided.

getMidiFileFormat(URL) - Static method in class `javax.sound.midi.MidiSystem`
Obtains the MIDI file format of the data in the specified URL.

getMidiFileFormat(URL) - Method in class `javax.sound.midi.spi.MidiFileReader`
Obtains the MIDI file format of the URL provided.

getMidiFileTypes() - Static method in class `javax.sound.midi.MidiSystem`
Obtains the set of MIDI file types for which file writing support is provided by the system.

getMidiFileTypes() - Method in class `javax.sound.midi.spi.MidiFileWriter`
Obtains the set of MIDI file types for which file writing support is provided by this file writer.

getMidiFileTypes(Sequence) - Static method in class `javax.sound.midi.MidiSystem`
Obtains the set of MIDI file types that the system can write from the sequence specified.

getMidiFileTypes(Sequence) - Method in class `javax.sound.midi.spi.MidiFileWriter`
Obtains the file types that this file writer can write from the sequence specified.

getMidLabel() - Method in class `javax.sound.sampled.FloatControl`
Obtains the label for the mid-point value, such as "Center" or "Default."

getMillisToDecideToPopup() - Method in class `javax.swing.ProgressMonitor`
Returns the amount of time this object waits before deciding whether or not to popup a progress monitor.

getMillisToPopup() - Method in class `javax.swing.ProgressMonitor`
Returns the amount of time it will take for the popup to appear.

getMimeType() - Method in class `java.awt.datatransfer.DataFlavor`
Returns the MIME type string for this DataFlavor

getMinBufferSize() - Method in class `javax.sound.sampled.DataLine.Info`
Obtains the minimum buffer size supported by the data line.

getMinimalDaysInFirstWeek() - Method in class `java.util.Calendar`
Gets what the minimal days required in the first week of the year are; e.g., if the first week is defined as one that contains the first day of the first month of a year, `getMinimalDaysInFirstWeek` returns 1.

getMinimum() - Method in class `java.awt.Scrollbar`
Gets the minimum value of this scrollbar.

getMinimum() - Method in interface `java.awt.Adjustable`
Gets the minimum value of the adjustable object.

getMinimum() - Method in class `javax.sound.sampled.FloatControl`
Obtains the minimum value permitted.

getMinimum() - Method in class `javax.swing.DefaultBoundedRangeModel`
Return the model's minimum.

getMinimum() - Method in class `javax.swing.ProgressMonitor`
Returns the minimum value -- the lower end of the progress value.

getMinimum() - Method in interface `javax.swing.BoundedRangeModel`
Returns the minimum acceptable value.

getMinimum() - Method in class `javax.swing.JScrollbar`
Returns the minimum value supported by the scrollbar (usually zero).

getMinimum() - Method in class `javax.swing.JProgressBar`
Returns the model's minimum value.

getMinimum() - Method in class `javax.swing.JSlider`
Returns the minimum value supported by the slider.

getMinimum(int) - Method in class `java.util.Calendar`
Gets the minimum value for the given time field.

getMinimum(int) - Method in class `java.util.GregorianCalendar`
Returns minimum value for the given field.

getMinimumAccessibleValue() - Method in class `java.awt.Scrollbar.AccessibleAWTScrollbar`
Get the minimum accessible value of this object.

getMinimumAccessibleValue() - Method in class `java.awt.MenuItem.AccessibleAWTMenuItem`
Get the minimum value of this object as a Number.

getMinimumAccessibleValue() - Method in class `java.awt.Checkbox.AccessibleAWTCheckbox`

Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class [java.awt.Button.AccessibleAWTButton](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class
[java.awt.CheckboxMenuItem.AccessibleAWTCheckboxMenuItem](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in interface [javax.accessibility.AccessibleValue](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.JInternalFrame.AccessibleJInternalFrame](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class
[javax.swing.JInternalFrame.JDesktopIcon.AccessibleJDesktopIcon](#)
 Get the minimum value of this object as a Number.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.JSplitPane.AccessibleJSplitPane](#)
 Gets the minimum accessible value of this object.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.JScrollBar.AccessibleJScrollBar](#)
 Get the minimum accessible value of this object.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.JProgressBar.AccessibleJProgressBar](#)
 Get the minimum accessible value of this object.
[getMinimumAccessibleValue\(\)](#) - Method in class [javax.swing.JSlider.AccessibleJSlider](#)
 Get the minimum accessible value of this object.
[getMinimumDividerLocation\(\)](#) - Method in class [javax.swing.JSplitPane](#)
 Returns the minimum location of the divider from the look and feel implementation.
[getMinimumDividerLocation\(JSplitPane\)](#) - Method in class [javax.swing.plaf.SplitPaneUI](#)
 Returns the minimum possible location of the divider.
[getMinimumDividerLocation\(JSplitPane\)](#) - Method in class [javax.swing.plaf.basic.BasicSplitPaneUI](#)
 Gets the minimum location of the divider.
[getMinimumDividerLocation\(JSplitPane\)](#) - Method in class [javax.swing.plaf.multi.MultiSplitPaneUI](#)
 Call [getMinimumDividerLocation](#) on each UI handled by this MultiUI.
[getMinimumFractionDigits\(\)](#) - Method in class [java.text.NumberFormat](#)
 Returns the minimum number of digits allowed in the fraction portion of a number.
[getMinimumHorizontalSize\(\)](#) - Method in class [javax.swing.plaf.basic.BasicSliderUI](#)

[getMinimumIntegerDigits\(\)](#) - Method in class [java.text.NumberFormat](#)
 Returns the minimum number of digits allowed in the integer portion of a number.
[getMinimumOptionPaneSize\(\)](#) - Method in class [javax.swing.plaf.basic.BasicOptionPaneUI](#)
 Returns the minimum size the option pane should be.
[getMinimumSize\(\)](#) - Method in class [java.awt.Component](#)
 Gets the minimum size of this component.
[getMinimumSize\(\)](#) - Method in class [java.awt.Container](#)
 Returns the minimum size of this container.
[getMinimumSize\(\)](#) - Method in class [java.awt.List](#)
 Determines the minimum size of this scrolling list.
[getMinimumSize\(\)](#) - Method in class [java.awt.TextField](#)
 Gets the minimum dimensions for this text field.
[getMinimumSize\(\)](#) - Method in class [java.awt.TextArea](#)
 Determines the minimum size of this text area.
[getMinimumSize\(\)](#) - Method in class [javax.swing.JComponent](#)
 If the minimum size has been set to a non-null value just returns it.
[getMinimumSize\(\)](#) - Method in class [javax.swing.JToolBar.Separator](#)
 Returns the minimum size for the separator.
[getMinimumSize\(\)](#) - Method in class [javax.swing.Box.Filler](#)
 Returns the minimum size of the component.
[getMinimumSize\(\)](#) - Method in class [javax.swing.JScrollBar](#)
 The scrollbar is flexible along it's scrolling axis and rigid along the other axis.

getMinimumSize() - Method in class javax.swing.plaf.basic.BasicSplitPaneDivider
Returns dividerSize x dividerSize

getMinimumSize() - Method in class javax.swing.plaf.basic.BasicArrowButton

getMinimumSize() - Method in class javax.swing.plaf.metal.MetalScrollbar

getMinimumSize(Component) - Method in class javax.swing.border.TitledBorder
Returns the minimum dimensions this border requires in order to fully display the border and title.

getMinimumSize(int) - Method in class java.awt.List
Gets the minimum dimensions for a list with the specified number of rows.

getMinimumSize(int) - Method in class java.awt.TextField
Gets the minimum dimensions for a text field with the specified number of columns.

getMinimumSize(int, int) - Method in class java.awt.TextArea
Determines the minimum size of a text area with the specified number of rows and columns.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.ComponentUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTextUI
Gets the minimum size for the editor component.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSeparatorUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuItemUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicButtonUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolBarSeparatorUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicProgressBarUI
The minimum size for this component is 10.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Messages getPreferredSize.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicPopupMenuUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTableUI
Return the minimum size of the table.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolTipUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicScrollbarUI
A vertical scrollbar's minimum width is the largest minimum width of the (non null) increment/decrement buttons, and the minimum width of the thumb.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicToolBarUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicListUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicLabelUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTableHeaderUI
Return the minimum size of the header.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuBarUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTreeUI
Returns the minimum size for this component.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSplitPaneUI
Returns the minimum size for the passed in component, This is passed off to the current layoutmanager.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicScrollPaneUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopIconUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSliderUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.metal.MetalComboBoxUI

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiListUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSeparatorUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiLabelUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPopupMenuUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPanelUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollbarUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTextUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiComboBoxUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTableHeaderUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiFileChooserUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiColorChooserUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTreeUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiViewportUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTabbedPaneUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiProgressBarUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollPaneUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiOptionPaneUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSplitPaneUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiButtonUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiToolBarUI
Call getMinimumSize on each UI handled by this MultiUI.

getMinimumSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSliderUI

Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiDesktopPaneUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiTableUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiDesktopIconUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuItemUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiInternalFrameUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiToolTipUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuBarUI`
 Call `getMinimumSize` on each UI handled by this `MultiUI`.

`getMinimumSpan(int)` - Method in class `javax.swing.text.View`
 Determines the minimum span for this view along an axis.

`getMinimumSpan(int)` - Method in class `javax.swing.text.BoxView`
 Determines the minimum span for this view along an axis.

`getMinimumSpan(int)` - Method in class `javax.swing.text.AsyncBoxView`
 Determines the minimum span for this view along an axis.

`getMinimumSpan(int)` - Method in class `javax.swing.text.ComponentView`
 Determines the minimum span for this view along an axis.

`getMinimumSpan(int)` - Method in class `javax.swing.text.WrappedPlainView`
 Determines the minimum span for this view along an axis.

`getMinimumSpan(int)` - Method in class `javax.swing.text.html.ParagraphView`
 Determines the minimum span for this view along an axis.

`getMinimumThumbSize()` - Method in class `javax.swing.plaf.basic.BasicScrollBarUI`
 Return the smallest acceptable size for the thumb.

`getMinimumThumbSize()` - Method in class `javax.swing.plaf.metal.MetalScrollBarUI`

`getMinimumVerticalSize()` - Method in class `javax.swing.plaf.basic.BasicSliderUI`

`getMinLabel()` - Method in class `javax.sound.sampled.FloatControl`
 Obtains the label for the minimum value, such as "Left" or "Off."

`getMinorAxis()` - Method in class `javax.swing.text.AsyncBoxView`
 Fetch the minor axis (the axis orthogonal to the tiled axis).

`getMinorOffset()` - Method in class `javax.swing.text.AsyncBoxView.ChildState`
 What is the offset along the minor axis

`getMinorSpan()` - Method in class `javax.swing.text.AsyncBoxView.ChildState`
 What is the span along the minor axis.

`getMinorTickSpacing()` - Method in class `javax.swing.JSlider`
 This method returns the minor tick spacing.

`getMinorVersion()` - Method in class `java.awt.color.ICC_Profile`
 Returns profile minor version.

`getMinorVersion()` - Method in interface `java.sql.Driver`
 Gets the driver's minor version number.

`getMinPage()` - Method in class `java.awt.JobAttributes`
 Specifies the minimum value the user can specify as the first page to be printed for jobs using these attributes.

`getMinSelectionIndex()` - Method in class `javax.swing.DefaultListSelectionModel`

`getMinSelectionIndex()` - Method in class `javax.swing.JList`
 Returns the smallest selected cell index.

`getMinSelectionIndex()` - Method in interface `javax.swing.ListSelectionModel`
 Returns the first selected index or -1 if the selection is empty.

`getMinSelectionRow()` - Method in class `javax.swing.JTree`

Gets the first selected row.

[getMinSelectionRow\(\)](#) - Method in class `javax.swing.tree.DefaultTreeSelectionModel`
Returns the smallest value obtained from the RowMapper for the current set of selected TreePaths.

[getMinSelectionRow\(\)](#) - Method in interface `javax.swing.tree.TreeSelectionModel`
Returns the smallest value obtained from the RowMapper for the current set of selected TreePaths.

[GetMinSize\(Container, GridBagLayoutInfo\)](#) - Method in class `java.awt.GridBagLayout`

[getMinTileX\(\)](#) - Method in interface `java.awt.image.RenderedImage`
Returns the minimum tile index in the X direction.

[getMinTileX\(\)](#) - Method in class `java.awt.image.BufferedImage`
Returns the minimum tile index in the x direction.

[getMinTileY\(\)](#) - Method in interface `java.awt.image.RenderedImage`
Returns the minimum tile index in the Y direction.

[getMinTileY\(\)](#) - Method in class `java.awt.image.BufferedImage`
Returns the minimum tile index in the y direction.

[getMinusSign\(\)](#) - Method in class `java.text.DecimalFormatSymbols`
Gets the character used to represent minus sign.

[getMinutes\(\)](#) - Method in class `java.sql.Date`
Deprecated.

[getMinutes\(\)](#) - Method in class `java.util.Date`
Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.MINUTE)`.*

[getMinWidth\(\)](#) - Method in class `javax.swing.table.TableColumn`
Returns the minimum width for the TableColumn.

[getMinX\(\)](#) - Method in class `java.awt.geom.RectangularShape`
Returns the smallest X coordinate of the framing rectangle of the Shape in double precision.

[getMinX\(\)](#) - Method in interface `java.awt.image.RenderedImage`
Returns the minimum X coordinate (inclusive) of the RenderedImage.

[getMinX\(\)](#) - Method in class `java.awt.image.BufferedImage`
Returns the minimum x coordinate of this BufferedImage.

[getMinX\(\)](#) - Method in class `java.awt.image.Raster`
Returns the minimum valid X coordinate of the Raster.

[getMinX\(\)](#) - Method in class `java.awt.image.renderable.RenderableImageOp`
Gets the minimum X coordinate of the rendering-independent image data.

[getMinX\(\)](#) - Method in interface `java.awt.image.renderable.RenderableImage`
Gets the minimum X coordinate of the rendering-independent image data.

[getMinY\(\)](#) - Method in class `java.awt.geom.RectangularShape`
Returns the smallest Y coordinate of the framing rectangle of the Shape in double precision.

[getMinY\(\)](#) - Method in interface `java.awt.image.RenderedImage`
Returns the minimum Y coordinate (inclusive) of the RenderedImage.

[getMinY\(\)](#) - Method in class `java.awt.image.BufferedImage`
Returns the minimum y coordinate of this BufferedImage.

[getMinY\(\)](#) - Method in class `java.awt.image.Raster`
Returns the minimum valid Y coordinate of the Raster.

[getMinY\(\)](#) - Method in class `java.awt.image.renderable.RenderableImageOp`
Gets the minimum Y coordinate of the rendering-independent image data.

[getMinY\(\)](#) - Method in interface `java.awt.image.renderable.RenderableImage`
Gets the minimum Y coordinate of the rendering-independent image data.

[getMissingGlyphCode\(\)](#) - Method in class `java.awt.Font`
Returns the glyphCode which is used when this Font does not have a glyph for a specified unicode.

[getMiterLimit\(\)](#) - Method in class `java.awt.BasicStroke`
Returns the limit of miter joins.

[getMixer\(Mixer.Info\)](#) - Static method in class `javax.sound.sampled.AudioSystem`
Obtains the requested audio mixer.

[getMixer\(Mixer.Info\)](#) - Method in class `javax.sound.sampled.spi.MixerProvider`

Obtains an instance of the mixer represented by the info object.

[getMixerInfo\(\)](#) - Method in interface [javax.sound.sampled.Mixer](#)
Obtains information about this mixer, including the product's name, version, vendor, etc.

[getMixerInfo\(\)](#) - Static method in class [javax.sound.sampled.AudioSystem](#)
Obtains an array of mixer info objects that represents the set of audio mixers that are currently installed on the system.

[getMixerInfo\(\)](#) - Method in class [javax.sound.sampled.spi.MixerProvider](#)
Obtains the set of info objects representing the mixer or mixers provided by this MixerProvider.

[getMnemonic\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the keyboard mnemonic from the the current model.

[getMnemonic\(\)](#) - Method in interface [javax.swing.ButtonModel](#)
Gets the keyboard mnemonic for this model

[getMnemonic\(\)](#) - Method in class [javax.swing.DefaultButtonModel](#)
Gets the keyboard mnemonic for this model

[getMode\(\)](#) - Method in class [java.awt.FileDialog](#)
Indicates whether this file dialog box is for loading from a file or for saving to a file.

[getModel\(\)](#) - Method in class [javax.swing.JTabbedPane](#)
Returns the model associated with this tabbedpane.

[getModel\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the model that this button represents.

[getModel\(\)](#) - Method in class [javax.swing.JComboBox](#)
Returns the data model currently used by the JComboBox.

[getModel\(\)](#) - Method in class [javax.swing.JList](#)
Returns the data model that holds the list of items displayed by the JList component.

[getModel\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the TreeModel that is providing the data.

[getModel\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the TableModel that provides the data displayed by this JTable.

[getModel\(\)](#) - Method in class [javax.swing.JScrollBar](#)
Returns data model that handles the scrollbar's four fundamental properties: minimum, maximum, value, extent.

[getModel\(\)](#) - Method in class [javax.swing.JProgressBar](#)
Returns the data model used by the JProgressBar.

[getModel\(\)](#) - Method in class [javax.swing.JSlider](#)
Returns data model that handles the sliders three fundamental properties: minimum, maximum, value.

[getModel\(\)](#) - Method in class [javax.swing.tree.AbstractLayoutCache](#)
Returns the TreeModel that is providing the data.

[getModel\(\)](#) - Method in class [javax.swing.plaf.basic.BasicFileChooserUI](#)

[getModel\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)

[getModelIndex\(\)](#) - Method in class [javax.swing.table.TableColumn](#)
Returns the model index for this column.

[getModificationOp\(\)](#) - Method in class [javax.naming.directory.ModificationItem](#)
Retrieves the modification code of this modification item.

[getModifier\(\)](#) - Method in class [javax.swing.text.html.parser.AttributeList](#)

[getModifiers\(\)](#) - Method in class [java.awt.event.ActionEvent](#)
Returns the modifier keys held down during this action event.

[getModifiers\(\)](#) - Method in class [java.awt.event.InputEvent](#)
Returns the modifiers flag for this event.

[getModifiers\(\)](#) - Method in class [java.lang.Class](#)
Returns the Java language modifiers for this class or interface, encoded in an integer.

[getModifiers\(\)](#) - Method in interface [java.lang.reflect.Member](#)
Returns the Java language modifiers for the member or constructor represented by this Member,

as an integer.

[getModifiers\(\)](#) - Method in class java.lang.reflect.[Method](#)
Returns the Java language modifiers for the method represented by this Method object, as an integer.

[getModifiers\(\)](#) - Method in class java.lang.reflect.[Field](#)
Returns the Java language modifiers for the field represented by this Field object, as an integer.

[getModifiers\(\)](#) - Method in class java.lang.reflect.[Constructor](#)
Returns the Java language modifiers for the constructor represented by this Constructor object, as an integer.

[getModifiers\(\)](#) - Method in class javax.swing.[KeyStroke](#)
Returns the modifier keys defined by this KeyStroke object.

[getModulus\(\)](#) - Method in interface java.security.interfaces.[RSAKey](#)
Returns the modulus.

[getModulus\(\)](#) - Method in class java.security.spec.[RSAPrivateKeySpec](#)
Returns the modulus.

[getModulus\(\)](#) - Method in class java.security.spec.[RSAPublicKeySpec](#)
Returns the modulus.

[getMonetaryDecimalSeparator\(\)](#) - Method in class java.text.[DecimalFormatSymbols](#)
Return the monetary decimal separator.

[getMono\(\)](#) - Method in interface javax.sound.midi.[MidiChannel](#)
Obtains the current mono/poly mode.

[getMonth\(\)](#) - Method in class java.sql.[Time](#)
Deprecated.

[getMonth\(\)](#) - Method in class java.util.[Date](#)
Deprecated. *As of JDK version 1.1, replaced by Calendar.get(Calendar.MONTH).*

[getMonths\(\)](#) - Method in class java.text.[DateFormatSymbols](#)
Gets month strings.

[getMoreResults\(\)](#) - Method in interface java.sql.[Statement](#)
Moves to a Statement object's next result.

[getMouseListener\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboPopup](#)
Implementation of ComboPopup.getMouseListener().

[getMouseListener\(\)](#) - Method in interface javax.swing.plaf.basic.[ComboPopup](#)
Returns a mouse listener that shows and hides the popup.

[getMouseMotionListener\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboPopup](#)
Implementation of ComboPopup.getMouseMotionListener().

[getMouseMotionListener\(\)](#) - Method in interface javax.swing.plaf.basic.[ComboPopup](#)
Returns a mouse motion listener that makes the popup act like a menu.

[getMultipleDocumentHandling\(\)](#) - Method in class java.awt.[JobAttributes](#)
Specifies the handling of multiple documents, including collation, for jobs using these attributes.

[getMultiplier\(\)](#) - Method in class java.text.[DecimalFormat](#)
Get the multiplier for use in percent, permill, etc.

[getMute\(\)](#) - Method in interface javax.sound.midi.[MidiChannel](#)
Obtains the current mute state for this channel.

[getName\(\)](#) - Method in class java.awt.[Component](#)
Gets the name of the component.

[getName\(\)](#) - Method in class java.awt.[MenuComponent](#)
Gets the name of the menu component.

[getName\(\)](#) - Method in class java.awt.[Font](#)
Returns the logical name of this Font.

[getName\(\)](#) - Method in class java.awt.[Cursor](#)
Returns the name of this cursor.

[getName\(\)](#) - Method in class java.awt.datatransfer.[Clipboard](#)
Returns the name of this clipboard object.

[getName\(\)](#) - Method in class java.beans.[FeatureDescriptor](#)
Gets the programmatic name of this feature.

Specifies the number of cells in a column for the component's display area.

GridLayout - class java.awt.GridLayout.
The GridLayout class is a layout manager that lays out a container's components in a rectangular grid.

GridLayout() - Constructor for class java.awt.GridLayout
Creates a grid layout with a default of one column per component, in a single row.

GridLayout(int, int) - Constructor for class java.awt.GridLayout
Creates a grid layout with the specified number of rows and columns.

GridLayout(int, int, int, int) - Constructor for class java.awt.GridLayout
Creates a grid layout with the specified number of rows and columns.

gridwidth - Variable in class java.awt.GridBagConstraints
Specifies the number of cells in a row for the component's display area.

gridx - Variable in class java.awt.GridBagConstraints
Specifies the cell at the left of the component's display area, where the leftmost cell has gridx=0.

gridy - Variable in class java.awt.GridBagConstraints
Specifies the cell at the top of the component's display area, where the topmost cell has gridy=0.

group - Variable in class javax.swing.DefaultButtonModel

Group - interface java.security.acl.Group.
This interface is used to represent a group of principals.

grow(int, int) - Method in class java.awt.Rectangle
Resizes the Rectangle both horizontally and vertically.

growAbsorb - Variable in class java.awt.font.GlyphJustificationInfo
If true, this glyph absorbs all extra space at this and lower priority levels when it grows.

growLeftLimit - Variable in class java.awt.font.GlyphJustificationInfo
The maximum amount by which the left side of this glyph can grow.

growPriority - Variable in class java.awt.font.GlyphJustificationInfo
The priority level of this glyph as it is growing.

growRightLimit - Variable in class java.awt.font.GlyphJustificationInfo
The maximum amount by which the right side of this glyph can grow.

Guard - interface java.security.Guard.
This interface represents a guard, which is an object that is used to protect access to another object.

GuardedObject - class java.security.GuardedObject.
A GuardedObject is an object that is used to protect access to another object.

GuardedObject(Object, Guard) - Constructor for class java.security.GuardedObject
Constructs a GuardedObject using the specified object and guard.

guessContentTypeFromName(String) - Static method in class java.net.URLConnection
Tries to determine the content type of an object, based on the specified "file" component of a URL.

guessContentTypeFromStream(InputStream) - Static method in class java.net.URLConnection
Tries to determine the type of an input stream based on the characters at the beginning of the input stream.

GUJARATI - Static variable in class java.lang.Character.UnicodeBlock
Constant for the Unicode character block of the same name.

GURMUKHI - Static variable in class java.lang.Character.UnicodeBlock
Constant for the Unicode character block of the same name.

GZIP_MAGIC - Static variable in class java.util.zip.GZIPInputStream
GZIP header magic number.

GZIPInputStream - class java.util.zip.GZIPInputStream.
This class implements a stream filter for reading compressed data in the GZIP format.

GZIPInputStream(InputStream) - Constructor for class java.util.zip.GZIPInputStream
Creates a new input stream with a default buffer size.

GZIPInputStream(InputStream, int) - Constructor for class java.util.zip.GZIPInputStream
Creates a new input stream with the specified buffer size.

GZIPOutputStream - class java.util.zip.GZIPOutputStream.

This class implements a stream filter for writing compressed data in the GZIP file format.

GZIPOutputStream(OutputStream) - Constructor for class java.util.zip.GZIPOutputStream

Creates a new output stream with a default buffer size.

GZIPOutputStream(OutputStream, int) - Constructor for class java.util.zip.GZIPOutputStream

Creates a new output stream with the specified buffer size.

Overview **Package** **Class** **Use** **Tree** **Deprecated** **Index** **Help**

Java™ 2 Platform

PREV LETTER **NEXT LETTER**

FRAMES **NO FRAMES**

Std. Ed. v1.3.1

A **B** **C** **D** **E** **F** **G** **H** **I** **J** **K** **L** **M** **N** **O** **P** **Q** **R** **S** **T** **U** **V** **W** **X** **Y** **Z** **_**

Submit a bug or feature

For further API reference and developer documentation, see Java 2 SDK SE Developer Documentation. That documentation contains more detailed, developer-targeted descriptions, with conceptual overviews, definitions of terms, workarounds, and working code examples.

Java, Java 2D, and JDBC are trademarks or registered trademarks of Sun Microsystems, Inc. in the US and other countries.

Copyright 1993-2001 Sun Microsystems, Inc. 901 San Antonio Road

Palo Alto, California, 94303, U.S.A. All Rights Reserved.

getName() - Method in class [java.io.File](#)
Returns the name of the file or directory denoted by this abstract pathname.

getName() - Method in class [java.io.ObjectStreamClass](#)
The name of the class described by this descriptor.

getName() - Method in class [java.io.ObjectStreamField](#)
Get the name of this field.

getName() - Method in class [java.lang.ThreadGroup](#)
Returns the name of this thread group.

getName() - Method in class [java.lang.Thread](#)
Returns this thread's name.

getName() - Method in class [java.lang.Package](#)
Return the name of this package.

getName() - Method in class [java.lang.Class](#)
Returns the fully-qualified name of the entity (class, interface, array class, primitive type, or void) represented by this Class object, as a String.

getName() - Method in interface [java.lang.reflect.Member](#)
Returns the simple name of the underlying member or constructor represented by this Member.

getName() - Method in class [java.lang.reflect.Method](#)
Returns the name of the method represented by this Method object, as a String.

getName() - Method in class [java.lang.reflect.Field](#)
Returns the name of the field represented by this Field object.

getName() - Method in class [java.lang.reflect.Constructor](#)
Returns the name of this constructor, as a string.

getName() - Method in class [java.security.Permission](#)
Returns the name of this Permission.

getName() - Method in class [java.security.Provider](#)
Returns the name of this provider.

getName() - Method in class [java.security.Identity](#)
Deprecated. Returns this identity's name.

getName() - Method in interface [java.security.Principal](#)
Returns the name of this principal.

getName() - Method in interface [java.security.acl.Acl](#)
Returns the name of this ACL.

getName() - Method in class [java.text.AttributedCharacterIterator.Attribute](#)
Returns the name of the attribute.

getName() - Method in class [java.util.zip.ZipFile](#)
Returns the path name of the ZIP file.

getName() - Method in class [java.util.zip.ZipEntry](#)
Returns the name of the entry.

getName() - Method in class [javax.sound.sampled.Mixer.Info](#)
Obtains the name of the mixer.

getName() - Method in class [javax.sound.sampled.Port.Info](#)
Obtains the name of the port.

getName() - Method in class [javax.sound.midi.SoundbankResource](#)
Obtains the name of the resource.

getName() - Method in interface [javax.sound.midi.Soundbank](#)
Obtains the name of the sound bank.

getName() - Method in class [javax.sound.midi.MidiDevice.Info](#)
Obtains the name of the device.

getName() - Method in class [javax.naming.NameClassPair](#)
Retrieves the name of this binding.

getName() - Method in class [javax.swing.LookAndFeel](#)
Return a short string that identifies this look and feel, e.g.

getName() - Method in class [javax.swing.UIManager.LookAndFeelInfo](#)
Returns the name of the look and feel in a form suitable for a menu or other presentation

getName() - Method in interface [javax.swing.text.Keymap](#)
Fetches the name of the set of key-bindings.

getName() - Method in interface javax.swing.text.Element
Fetches the name of the element.

getName() - Method in interface javax.swing.text.Style
Fetches the name of the style.

getName() - Method in class javax.swing.text.StyleContext.NamedStyle
Fetches the name of the style.

getName() - Method in class javax.swing.text.AbstractDocument.AbstractElement
Gets the name of the element.

getName() - Method in class javax.swing.text.AbstractDocument.BranchElement
Gets the element name.

getName() - Method in class javax.swing.text.AbstractDocument.LeafElement
Gets the element name.

getName() - Method in class javax.swing.text.DefaultStyledDocument.SectionElement
Gets the name of the element.

getName() - Method in class javax.swing.text.html.HTMLDocument.RunElement
Gets the name of the element.

getName() - Method in class javax.swing.text.html.HTMLDocument.BlockElement
Gets the name of the element.

getName() - Method in class javax.swing.text.html.parser.AttributeList

getName() - Method in class javax.swing.text.html.parser.DTD
Get the name of the DTD.

getName() - Method in class javax.swing.text.html.parser.Element
Get the name of the element.

getName() - Method in class javax.swing.text.html.parser.Entity
Get the name of the entity.

getName() - Method in class javax.swing.plaf.metal.MetalLookAndFeel

getName() - Method in class javax.swing.plaf.metal.MetalTheme

getName() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getName() - Method in class javax.swing.plaf.multi.MultiLookAndFeel

getName(File) - Method in class javax.swing.JFileChooser
Returns the filename.

getName(File) - Method in class javax.swing.filechooser.FileView
The name of the file.

getName(File) - Method in class javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView

getName(int) - Method in class java.awt.color.ColorSpace
Returns the name of the component given the component index

getNameInNamespace() - Method in class javax.naming.InitialContext

getNameInNamespace() - Method in interface javax.naming.Context
Retrieves the full name of this context within its own namespace.

getNameParser(Name) - Method in class javax.naming.InitialContext

getNameParser(Name) - Method in interface javax.naming.Context
Retrieves the parser associated with the named context.

getNameParser(String) - Method in class javax.naming.InitialContext

getNameParser(String) - Method in interface javax.naming.Context
Retrieves the parser associated with the named context.

getNaN() - Method in class java.text.DecimalFormatSymbols
Gets the character used to represent NaN.

getNanos() - Method in class java.sql.Timestamp

Gets this Timestamp object's nanos value.

[getNativeContainer\(Component\)](#) - Static method in class java.awt.[Toolkit](#)
Give native peers the ability to query the native container given a native component (eg the direct parent may be lightweight).

[getNativesForFlavors\(DataFlavor\[\]\)](#) - Method in class java.awt.datatransfer.[SystemFlavorMap](#)
map flavors to native data types names

[getNativesForFlavors\(DataFlavor\[\]\)](#) - Method in interface java.awt.datatransfer.[FlavorMap](#)
map flavors to native data types names

[getNeededLocation\(int, int\)](#) - Method in class
javax.swing.plaf.basic.[BasicSplitPaneDivider.DragController](#)
Returns the x argument, since this is used for horizontal splits.

[getNeededLocation\(int, int\)](#) - Method in class
javax.swing.plaf.basic.[BasicSplitPaneDivider.VerticalDragController](#)
Returns the y argument, since this is used for vertical splits.

[getNegativePrefix\(\)](#) - Method in class java.text.[DecimalFormat](#)
Get the negative prefix.

[getNegativeSuffix\(\)](#) - Method in class java.text.[DecimalFormat](#)
Get the negative suffix.

[getNewBinding\(\)](#) - Method in class javax.naming.event.[NamingEvent](#)
Retrieves the binding of the object after the change.

[getNewFolderAction\(\)](#) - Method in class javax.swing.plaf.basic.[BasicFileChooserUI](#)

[getNewLeadSelectionPath\(\)](#) - Method in class javax.swing.event.[TreeSelectionEvent](#)
Returns the current lead path.

[getNewValue\(\)](#) - Method in class java.beans.[PropertyChangeEvent](#)
Sets the new value for the property, expressed as an Object.

[getNext\(\)](#) - Method in class javax.swing.text.html.parser.[AttributeList](#)

[getNextEastWestVisualPositionFrom\(int, Position.Bias, Shape, int, Position.Bias\[\]\)](#) - Method in class
javax.swing.text.[CompositeView](#)
Returns the next visual position for the cursor, in either the east or west direction.

[getNextEntry\(\)](#) - Method in class java.util.jar.[JarInputStream](#)
Reads the next ZIP file entry and positions stream at the beginning of the entry data.

[getNextEntry\(\)](#) - Method in class java.util.zip.[ZipInputStream](#)
Reads the next ZIP file entry and positions stream at the beginning of the entry data.

[getNextEvent\(\)](#) - Method in class java.awt.[EventQueue](#)
Remove an event from the EventQueue and return it.

[getNextException\(\)](#) - Method in class java.sql.[SQLException](#)
Retrieves the exception chained to this SQLException object.

[getNextFocusableComponent\(\)](#) - Method in class javax.swing.[JComponent](#)
Returns the next focusable component or null if the focus manager should choose the next focusable component automatically.

[getNextJarEntry\(\)](#) - Method in class java.util.jar.[JarInputStream](#)
Reads the next JAR file entry and positions the stream at the beginning of the entry data.

[getNextLeaf\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the leaf after this node or null if this node is the last leaf in the tree.

[getNextLeftHit\(int\)](#) - Method in class java.awt.font.[TextLayout](#)
Returns the hit for the next caret to the left (top); if no such hit, returns null.

[getNextLeftHit\(int, TextLayout.CaretPolicy\)](#) - Method in class java.awt.font.[TextLayout](#)
Returns the hit for the next caret to the left (top); if no such hit, returns null.

[getNextLeftHit\(TextHitInfo\)](#) - Method in class java.awt.font.[TextLayout](#)
Returns the hit for the next caret to the left (top); if no such hit, returns null.

[getNextNode\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
Returns the node that follows this node in a preorder traversal of this node's tree.

[getNextNorthSouthVisualPositionFrom\(int, Position.Bias, Shape, int, Position.Bias\[\]\)](#) - Method in
class javax.swing.text.[CompositeView](#)
Returns the next visual position for the cursor, in either the east or west direction.

getNextNorthSouthVisualPositionFrom(int, Position.Bias, Shape, int, Position.Bias[]) - Method in class javax.swing.text.ParagraphView

Overriden from CompositeView.

getNextRightHit(int) - Method in class java.awt.font.TextLayout

Returns the hit for the next caret to the right (bottom); if no such hit, returns null.

getNextRightHit(int, TextLayout.CaretPolicy) - Method in class java.awt.font.TextLayout

Returns the hit for the next caret to the right (bottom); if no such hit, returns null.

getNextRightHit(TextHitInfo) - Method in class java.awt.font.TextLayout

Returns the hit for the next caret to the right (bottom); if there is no such hit, returns null.

getNextSibling() - Method in class javax.swing.tree.DefaultMutableTreeNode

Returns the next sibling of this node in the parent's children array.

getNextTabIndex(int) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getNextUpdate() - Method in class java.security.cert.X509CRL

Gets the nextUpdate date from the CRL.

getNextVisualPositionFrom(GlyphView, int, Position.Bias, Shape, int, Position.Bias[]) - Method in class javax.swing.text.GlyphView.GlyphPainter

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(int, Position.Bias, Shape, int, Position.Bias[]) - Method in class javax.swing.text.View

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(int, Position.Bias, Shape, int, Position.Bias[]) - Method in class javax.swing.text.CompositeView

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(int, Position.Bias, Shape, int, Position.Bias[]) - Method in class javax.swing.text.GlyphView

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(JTextComponent, int, Position.Bias, int, Position.Bias[]) - Method in class javax.swing.plaf.TextUI

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(JTextComponent, int, Position.Bias, int, Position.Bias[]) - Method in class javax.swing.plaf.basic.BasicTextUI

Provides a way to determine the next visually represented model location that one might place a caret.

getNextVisualPositionFrom(JTextComponent, int, Position.Bias, int, Position.Bias[]) - Method in class javax.swing.plaf.multi.MultiTextUI

Provides a way to determine the next visually represented model location that one might place a caret.

getNextWarning() - Method in class java.sql.SQLWarning

Retrieves the warning chained to this SQLWarning object.

getNextWord(JTextComponent, int) - Static method in class javax.swing.text.Utilities

Determines the start of the next word for the given location.

getNodeDimensions() - Method in class javax.swing.tree.AbstractLayoutCache

Returns the object that renders nodes in the tree, and which is responsible for calculating the dimensions of individual nodes.

getNodeDimensions(Object, int, int, boolean, Rectangle) - Method in class javax.swing.tree.AbstractLayoutCache

Returns, by reference in size, the size needed to represent value.

getNodeDimensions(Object, int, int, boolean, Rectangle) - Method in class javax.swing.tree.AbstractLayoutCache.NodeDimensions

Returns, by reference in bounds, the size and x origin to place value at.

getNodeDimensions(Object, int, int, boolean, Rectangle) - Method in class javax.swing.plaf.basic.BasicTreeUI.NodeDimensionsHandler
 Responsible for getting the size of a particular node.

getNonContinuousLayoutDivider() - Method in class javax.swing.plaf.basic.BasicSplitPaneUI
 Returns the divider to use when the splitPane is configured to not continuously layout.

getNonCriticalExtensionOIDs() - Method in interface java.security.cert.X509Extension
 Gets a Set of the OID strings for the extension(s) marked NON-CRITICAL in the certificate/CRL managed by the object implementing this interface.

getNormalBounds() - Method in class javax.swing.JInternalFrame
 If the JInternalFrame is not in maximized state, return getBounds(); otherwise, return the bounds that the JInternalFrame would be restored to.

getNormalizedComponents(int[], int, float[], int) - Method in class java.awt.image.ColorModel
 Returns an array of all of the color/alpha components in normalized form, given an unnormalized component array.

getNormalizingTransform() - Method in class java.awt.GraphicsConfiguration
 Returns a AffineTransform that can be concatenated with the default AffineTransform of a GraphicsConfiguration so that 72 units in user space equals 1 inch in device space.

getNorthPane() - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

getNotAfter() - Method in class java.security.cert.X509Certificate
 Gets the notAfter date from the validity period of the certificate.

getNotBefore() - Method in class java.security.cert.X509Certificate
 Gets the notBefore date from the validity period of the certificate.

getNote() - Method in class javax.swing.ProgressMonitor
 Specifies the additional note that is displayed along with the progress message.

getNotification() - Method in class javax.naming.ldap.UnsolicitedNotificationEvent
 Returns the unsolicited notification.

getNumBands() - Method in class java.awt.image.SampleModel
 Returns the total number of bands of image data.

getNumBands() - Method in class java.awt.image.Raster
 Returns the number of bands (samples per pixel) in this Raster.

getNumBanks() - Method in class java.awt.image.DataBuffer
 Returns the number of banks in this DataBuffer.

getNumberFormat() - Method in class java.text.DateFormat
 Gets the number formatter which this date/time formatter uses to format and parse a time.

getNumberInstance() - Static method in class java.text.NumberFormat
 Returns a general-purpose number format for the current default locale.

getNumberInstance(Locale) - Static method in class java.text.NumberFormat
 Returns a general-purpose number format for the specified locale.

getNumberOfPages() - Method in class java.awt.print.Book
 Returns the number of pages in this Book.

getNumberOfPages() - Method in interface java.awt.print.Pageable
 Returns the number of pages in the set.

getNumChars() - Method in class java.awt.font.LineMetrics
 Returns the number of characters in the text whose metrics are encapsulated by this LineMetrics object.

getNumColorComponents() - Method in class java.awt.image.ColorModel
 Returns the number of color components in this ColorModel.

getNumComponents() - Method in class java.awt.color.ICC_Profile
 Returns the number of color components in the "input" color space of this profile.

getNumComponents() - Method in class java.awt.color.ColorSpace
 Returns the number of components of this ColorSpace.

getNumComponents() - Method in class java.awt.image.LookupTable
 Returns the number of components in the lookup table.

getNumComponents() - Method in class java.awt.image.ColorModel
 Returns the number of components, including alpha, in this ColorModel.

getNumDataElements() - Method in class java.awt.image.SampleModel

Returns the number of data elements needed to transfer a pixel via the `getDataElements` and `setDataElements` methods.

`getNumDataElements()` - Method in class `java.awt.image.ComponentSampleModel`
Returns the number of data elements needed to transfer a pixel via the `getDataElements` and `setDataElements` methods.

`getNumDataElements()` - Method in class `java.awt.image.Raster`
Returns the number of data elements needed to transfer one pixel via the `getDataElements` and `setDataElements` methods.

`getNumDataElements()` - Method in class `java.awt.image.MultiPixelPackedSampleModel`
Returns the number of data elements needed to transfer one pixel via the `MultiPixelPackedSampleModel.getDataElements(int, int, java.lang.Object, java.awt.image.DataBuffer)` and `MultiPixelPackedSampleModel.setDataElements(int, int, java.lang.Object, java.awt.image.DataBuffer)` methods.

`getNumDataElements()` - Method in class `java.awt.image.SinglePixelPackedSampleModel`
Returns the number of data elements needed to transfer one pixel via the `getDataElements` and `setDataElements` methods.

`getNumDesignAxes()` - Method in interface `java.awt.font.MultipleMaster`
Returns the number of multiple master design controls.

`getNumericFunctions()` - Method in interface `java.sql.DatabaseMetaData`
Gets a comma-separated list of math functions.

`getNumericValue(char)` - Static method in class `java.lang.Character`
Returns the Unicode numeric value of the character as a nonnegative integer.

`getNumFactors()` - Method in class `java.awt.image.RescaleOp`
Returns the number of scaling factors and offsets used in this `RescaleOp`.

`getNumGlyphs()` - Method in class `java.awt.Font`
Returns the number of glyphs in this `Font`.

`getNumGlyphs()` - Method in class `java.awt.font.GlyphVector`
Returns the number of glyphs in this `GlyphVector`.

`getNumParameters()` - Method in class `java.awt.image.renderable.ParameterBlock`
Returns the number of parameters (not including source images).

`getNumSources()` - Method in class `java.awt.image.renderable.ParameterBlock`
Returns the number of source images.

`getNumXTiles()` - Method in interface `java.awt.image.RenderedImage`
Returns the number of tiles in the X direction.

`getNumXTiles()` - Method in class `java.awt.image.BufferedImage`
Returns the number of tiles in the x direction.

`getNumYTiles()` - Method in interface `java.awt.image.RenderedImage`
Returns the number of tiles in the Y direction.

`getNumYTiles()` - Method in class `java.awt.image.BufferedImage`
Returns the number of tiles in the y direction.

`getObject()` - Method in class `java.security.GuardedObject`
Retrieves the guarded object, or throws an exception if access to the guarded object is denied by the guard.

`getObject()` - Method in class `java.security.SignedObject`
Retrieves the encapsulated object.

`getObject()` - Method in class `javax.naming.Binding`
Retrieves the object bound to the name of this binding.

`getObject()` - Method in class `javax.naming.spi.DirStateFactory.Result`
Retrieves the object to be bound.

`getObject(int)` - Method in interface `java.sql.CallableStatement`
Gets the value of a parameter as an `Object` in the Java programming language.

`getObject(int)` - Method in interface `java.sql.ResultSet`
Gets the value of the designated column in the current row of this `ResultSet` object as an `Object` in the Java programming language.

`getObject(int, Map)` - Method in interface `java.sql.CallableStatement`
Returns an object representing the value of OUT parameter `i` and uses `map` for the custom mapping of the parameter value.

getObject(int, Map) - Method in interface java.sql.ResultSet
Returns the value of the designated column in the current row of this ResultSet object as an Object in the Java programming language.

getObject(String) - Method in interface java.sql.ResultSet
Gets the value of the designated column in the current row of this ResultSet object as an Object in the Java programming language.

getObject(String) - Method in class java.util.ResourceBundle
Get an object from a ResourceBundle.

getObject(String, Map) - Method in interface java.sql.ResultSet
Returns the value of the designated column in the current row of this ResultSet object as an Object in the Java programming language.

getObjectForLayer(int) - Method in class javax.swing.JLayeredPane
Returns the Integer object associated with a specified layer.

getObjectInstance(Object, Name, Context, Hashtable) - Method in interface javax.naming.spi.ObjectFactory
Creates an object using the location or reference information specified.

getObjectInstance(Object, Name, Context, Hashtable) - Static method in class javax.naming.spi.NamingManager
Creates an instance of an object for the specified object and environment.

getObjectInstance(Object, Name, Context, Hashtable, Attributes) - Static method in class javax.naming.spi.DirectoryManager
Creates an instance of an object for the specified object, attributes, and environment.

getObjectInstance(Object, Name, Context, Hashtable, Attributes) - Method in interface javax.naming.spi.DirObjectFactory
Creates an object using the location or reference information, and attributes specified.

getObjectParameter(int) - Method in class java.awt.image.renderable.ParameterBlock
Gets a parameter as an object.

getObjectStreamClass() - Method in class java.io.ObjectInputStream.GetField
Get the ObjectStreamClass that describes the fields in the stream.

getOffscreenBuffer(Component, int, int) - Method in class javax.swing.RepaintManager
Return the offscreen buffer that should be used as a double buffer with the component c By default there is a double buffer per RepaintManager.

getOffset() - Method in class java.awt.image.DataBuffer
Returns the offset of the default bank in array elements.

getOffset() - Method in class java.awt.image.LookupTable
Returns the offset.

getOffset() - Method in class java.io.ObjectStreamField
Offset of field within instance data.

getOffset() - Method in class java.net.DatagramPacket
Returns the offset of the data to be sent or the offset of the data received.

getOffset() - Method in class java.text.CollationElementIterator
Returns the character offset in the original text corresponding to the next collation element.

getOffset() - Method in interface javax.swing.event.DocumentEvent
Returns the offset within the document of the start of the change.

getOffset() - Method in interface javax.swing.text.Position
Fetches the current offset within the document.

getOffset() - Method in class javax.swing.text.AbstractDocument.DefaultDocumentEvent
Returns the offset within the document of the start of the change.

getOffset() - Method in class javax.swing.text.DefaultStyledDocument.ElementSpec
Gets the starting offset.

getOffset() - Method in class javax.swing.plaf.basic.BasicToolBarUI.DragWindow

getOffset(int, int) - Method in class java.awt.image.ComponentSampleModel
Gets the offset for the first band of pixel (x,y).

getOffset(int, int) - Method in class java.awt.image.MultiPixelPackedSampleModel
Returns the offset of pixel (x, y) in data array elements.

getOffset(int, int) - Method in class java.awt.image.SinglePixelPackedSampleModel

Returns the offset (in data array elements) of pixel (x,y).

getOffset(int, int) - Method in class javax.swing.text.BoxView
Fetch the offset of a particular child's current layout

getOffset(int, int, int) - Method in class java.awt.image.ComponentSampleModel
Gets the offset for band b of pixel (x,y).

getOffset(int, int, int, int, int, int) - Method in class java.util.TimeZone
Gets the time zone offset, for current date, modified in case of daylight savings.

getOffset(int, int, int, int, int, int) - Method in class java.util.SimpleTimeZone
Returns the difference in milliseconds between local time and UTC, taking into account both the raw offset and the effect of daylight savings, for the specified date and time.

getOffsetHit(int) - Method in class java.awt.font.TextHitInfo
Creates a TextHitInfo whose character index is offset by delta from the charIndex of this TextHitInfo.

getOffsets() - Method in class java.awt.image.DataBuffer
Returns the offsets (in array elements) of all the banks.

getOffsets(float[]) - Method in class java.awt.image.RescaleOp
Returns the offsets in the given array.

getOldBinding() - Method in class javax.naming.event.NamingEvent
Retrieves the binding of the object before the change.

getOldLeadSelectionPath() - Method in class javax.swing.event.TreeSelectionEvent
Returns the path that was previously the lead path.

getOldValue() - Method in class java.beans.PropertyChangeEvent
Gets the old value for the property, expressed as an Object.

getOmni() - Method in interface javax.sound.midi.MidiChannel
Obtains the current omni mode status.

getOpenIcon() - Method in class javax.swing.tree.DefaultTreeCellRenderer
Returns the icon used to represent non-leaf nodes that are expanded.

getOperation() - Method in class java.rmi.server.Operation
Deprecated. *no replacement*

getOperations() - Method in interface java.rmi.server.Skeleton
Deprecated. *no replacement*

getOption(int) - Method in interface java.net.SocketOptions
Fetch the value of an option.

getOptions() - Method in class javax.swing.JOptionPane
Returns the choices the user can make.

getOptionType() - Method in class javax.swing.JOptionPane
Returns the type of options that are displayed.

getOrientation() - Method in class java.awt.Scrollbar
Determines the orientation of this scroll bar.

getOrientation() - Method in interface java.awt.Adjustable
Gets the orientation of the adjustable object.

getOrientation() - Method in class java.awt.print.PageFormat
Returns the orientation of this PageFormat.

getOrientation() - Method in class javax.swing.JSeparator
Returns the orientation of this separator.

getOrientation() - Method in class javax.swing.JSplitPane
Returns the orientation.

getOrientation() - Method in class javax.swing.JToolBar
Returns the current orientation of the toolbar.

getOrientation() - Method in class javax.swing.JScrollbar
Returns the component's orientation (horizontal or vertical).

getOrientation() - Method in class javax.swing.JProgressBar
Returns JProgressBar.VERTICAL or JProgressBar.HORIZONTAL, depending on the orientation of the progress bar.

getOrientation() - Method in class javax.swing.JSlider
Return this slider's vertical or horizontal orientation.

getOrientation() - Method in class javax.swing.plaf.basic.BasicSplitPaneUI

Returns the orientation for the JSplitPane.

getOrientation(Locale) - Static method in class java.awt.ComponentOrientation
Return the orientation that is appropriate for the given locale

getOrientation(ResourceBundle) - Static method in class java.awt.ComponentOrientation
Return the orientation appropriate for the given ResourceBundle's localization.

getOrientationRequested() - Method in class java.awt.PageAttributes
Returns the print orientation for pages using these attributes.

getOrigin() - Method in class java.awt.PageAttributes
Returns whether drawing at (0, 0) to pages using these attributes draws at the upper-left corner of the physical page, or at the upper-left corner of the printable area.

getOtherHit() - Method in class java.awt.font.TextHitInfo
Creates a TextHitInfo on the other side of the insertion point.

getOutline() - Method in class java.awt.font.GlyphVector
Returns a Shape whose interior corresponds to the visual representation of this GlyphVector.

getOutline(AffineTransform) - Method in class java.awt.font.TextLayout
Returns a Shape representing the outline of this TextLayout.

getOutline(float, float) - Method in class java.awt.font.GlyphVector
Returns a Shape whose interior corresponds to the visual representation of this GlyphVector, offset to x, y.

getOutputStream() - Method in class java.lang.Process
Gets the output stream of the subprocess.

getOutputStream() - Method in class java.net.URLConnection
Returns an output stream that writes to this connection.

getOutputStream() - Method in class java.net.SocketImpl
Returns an output stream for this socket.

getOutputStream() - Method in class java.net.Socket
Returns an output stream for this socket.

getOutputStream() - Method in interface java.rmi.server.RemoteCall
Deprecated. *no replacement*

getOutputStream() - Method in class java.rmi.server.LogStream
Deprecated. *no replacement*

getOutsideBorder() - Method in class javax.swing.border.CompoundBorder
Returns the outside border object.

getOwnedWindows() - Method in class java.awt.Window
Return an array containing all the windows this window currently owns.

getOwner() - Method in class java.awt.Window
Returns the owner of this window.

getP() - Method in interface java.security.interfaces.DSAParams
Returns the prime, p.

getP() - Method in class java.security.spec.DSAPrivateKeySpec
Returns the prime p.

getP() - Method in class java.security.spec.DSAPublicKeySpec
Returns the prime p.

getP() - Method in class java.security.spec.DSAPrivateKeySpec
Returns the prime p.

getP1() - Method in class java.awt.geom.Line2D
Returns the starting Point2D of this Line2D.

getP1() - Method in class java.awt.geom.Line2D.Float
Returns the start point.

getP1() - Method in class java.awt.geom.Line2D.Double
Returns the starting Point2D of this Line2D.

getP1() - Method in class java.awt.geom.QuadCurve2D
Returns the start point.

getP1() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the start point.

getP1() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the start point.

getP1() - Method in class java.awt.geom.CubicCurve2D
Returns the start point.

getP1() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the start point.

getP1() - Method in class java.awt.geom.CubicCurve2D.Double
Returns the start point.

getP2() - Method in class java.awt.geom.Line2D
Returns the end Point2D of this Line2D.

getP2() - Method in class java.awt.geom.Line2D.Float
Returns the end point.

getP2() - Method in class java.awt.geom.Line2D.Double
Returns the end Point2D of this Line2D.

getP2() - Method in class java.awt.geom.QuadCurve2D
Returns the end point.

getP2() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the end point.

getP2() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the end point.

getP2() - Method in class java.awt.geom.CubicCurve2D
Returns the end point.

getP2() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the end point.

getP2() - Method in class java.awt.geom.CubicCurve2D.Double
Returns the end point.

getPackage() - Method in class java.lang.Class
Gets the package for this class.

getPackage(String) - Static method in class java.lang.Package
Find a package by name in the callers classloader.

getPackage(String) - Method in class java.lang.ClassLoader
Returns a Package that has been defined by this class loader or any of its ancestors.

getPackages() - Static method in class java.lang.Package
Get all the packages currently known for the caller's class loader.

getPackages() - Method in class java.lang.ClassLoader
Returns all of the Packages defined by this class loader and its ancestors.

getPadding() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonAreaLayout

getPage() - Method in class javax.swing.JEditorPane
Gets the current URL being displayed.

getPageDimension() - Method in class java.awt.PrintJob
Returns the dimensions of the page in pixels.

getPageFormat(int) - Method in class java.awt.print.Book
Returns the PageFormat of the page specified by pageIndex.

getPageFormat(int) - Method in interface java.awt.print.Pageable
Returns the PageFormat of the page specified by pageIndex.

getPageIncrement() - Method in class java.awt.Scrollbar
Deprecated. *As of JDK version 1.1, replaced by getBlockIncrement().*

getPageRanges() - Method in class java.awt.JobAttributes
Specifies, for jobs using these attributes, the ranges of pages to be printed, if a range of pages is to be printed.

getPageResolution() - Method in class java.awt.PrintJob
Returns the resolution of the page in pixels per inch.

getPaint() - Method in class java.awt.Graphics2D
Returns the current Paint of the Graphics2D context.

getPainter() - Method in interface javax.swing.text.Highlighter.Highlight
Gets the painter for the highlighter.

getPainter(GlyphView, int, int) - Method in class javax.swing.text.GlyphView.GlyphPainter
Create a painter to use for the given GlyphView.

getPaintLabels() - Method in class javax.swing.JSlider
Tells if labels are to be painted.

getPaintTicks() - Method in class javax.swing.JSlider
Tells if tick marks are to be painted.

getPaintTrack() - Method in class javax.swing.JSlider
Tells if the track (area the slider slides in) is to be painted.

getPaper() - Method in class java.awt.print.PageFormat
Returns a copy of the Paper object associated with this PageFormat.

getParagraphAttributes() - Method in class javax.swing.JTextPane
Fetches the current paragraph attributes in effect at the location of the caret, or null if none.

getParagraphElement(int) - Method in class javax.swing.text.AbstractDocument
Get the paragraph element containing the given position.

getParagraphElement(int) - Method in interface javax.swing.text.StyledDocument
Gets the element that represents the paragraph that encloses the given offset within the document.

getParagraphElement(int) - Method in class javax.swing.text.PlainDocument
Get the paragraph element containing the given position.

getParagraphElement(int) - Method in class javax.swing.text.DefaultStyledDocument
Gets the paragraph element at the offset pos.

getParagraphElement(JTextComponent, int) - Static method in class javax.swing.text.Utilities
Determines the element to use for a paragraph/line.

getParamClasses() - Method in class java.awt.image.renderable.ParameterBlock
Returns an array of Class objects describing the types of the parameters.

getParameter() - Method in class java.sql.DataTruncation
Indicates whether the value truncated was a parameter value or a column value.

getParameter(String) - Method in class java.applet.Applet
Returns the value of the named parameter in the HTML tag.

getParameter(String) - Method in interface java.applet.AppletStub
Returns the value of the named parameter in the HTML tag.

getParameter(String) - Method in class java.awt.datatransfer.DataFlavor

getParameter(String) - Method in class java.security.Signature
Deprecated.

getParameterBlock() - Method in class java.awt.image.renderable.RenderableImageOp
Returns a reference to the current parameter block.

getParameterDescriptors() - Method in class java.beans.MethodDescriptor
Gets the ParameterDescriptor for each of this MethodDescriptor's method's parameters.

getParameterInfo() - Method in class java.applet.Applet
Returns information about the parameters than are understood by this applet.

getParameters() - Method in class java.awt.image.renderable.ParameterBlock
Returns the entire Vector of parameters.

getParameterSpec(Class) - Method in class java.security.AlgorithmParameters
Returns a (transparent) specification of this parameter object.

getParameterTypes() - Method in class java.lang.reflect.Method
Returns an array of Class objects that represent the formal parameter types, in declaration order, of the method represented by this Method object.

getParameterTypes() - Method in class java.lang.reflect.Constructor
Returns an array of Class objects that represent the formal parameter types, in declaration order, of the constructor represented by this Constructor object.

getParams() - Method in interface java.security.interfaces.DSAKey
Returns the DSA-specific key parameters.

getParent() - Method in class java.awt.Component
Gets the parent of this component.

getParent() - Method in class java.awt.MenuComponent
Returns the parent container for this menu component.

getParent() - Method in class java.awt.image.Raster

Returns the parent Raster (if any) of this Raster, or else null.

[getParent\(\)](#) - Method in class [java.io.File](#)
Returns the pathname string of this abstract pathname's parent, or null if this pathname does not name a parent directory.

[getParent\(\)](#) - Method in class [java.lang.ThreadGroup](#)
Returns the parent of this thread group.

[getParent\(\)](#) - Method in class [java.lang.ClassLoader](#)
Returns the parent class loader for delegation.

[getParent\(\)](#) - Method in class [javax.swing.InputMap](#)
Gets this InputMap's parent.

[getParent\(\)](#) - Method in class [javax.swing.ActionMap](#)
Returns this ActionMap's parent.

[getParent\(\)](#) - Method in class [javax.swing.text.View](#)
Returns the parent of the view.

[getParent\(\)](#) - Method in class [javax.swing.text.AbstractDocument.AbstractElement](#)
Returns the parent [TreeNode](#) of the receiver.

[getParent\(\)](#) - Method in class [javax.swing.tree.DefaultMutableTreeNode](#)
Returns this node's parent or null if this node has no parent.

[getParent\(\)](#) - Method in interface [javax.swing.tree.TreeNode](#)
Returns the parent [TreeNode](#) of the receiver.

[getParentDirectory\(File\)](#) - Method in class [javax.swing.filechooser.FileSystemView](#)
Returns the parent directory of dir.

[getParentElement\(\)](#) - Method in interface [javax.swing.text.Element](#)
Fetches the parent element.

[getParentElement\(\)](#) - Method in class [javax.swing.text.AbstractDocument.AbstractElement](#)
Gets the parent of the element.

[getParentFile\(\)](#) - Method in class [java.io.File](#)
Returns the abstract pathname of this abstract pathname's parent, or null if this pathname does not name a parent directory.

[getParentPath\(\)](#) - Method in class [javax.swing.tree.TreePath](#)
Returns a path containing all the elements of this object, except the last path component.

[getParser\(\)](#) - Method in class [javax.swing.text.html.HTMLDocument](#)
Returns the parser that is used when inserting HTML into the existing document.

[getParser\(\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit](#)
Fetch the parser to use for reading HTML streams.

[getPartialSize\(int, int\)](#) - Method in class [javax.swing.text.ParagraphView](#)
Returns the size used by the views between startOffset and endOffset.

[getPartialSpan\(int, int\)](#) - Method in class [javax.swing.text.GlyphView](#)
Determines the span along the same axis as tab expansion for a portion of the view.

[getPartialSpan\(int, int\)](#) - Method in interface [javax.swing.text.TabableView](#)
Determines the span along the same axis as tab expansion for a portion of the view.

[getPassword\(\)](#) - Method in class [java.net.PasswordAuthentication](#)
Returns the user password.

[getPassword\(\)](#) - Method in class [javax.swing.JPasswordField](#)
Returns the text contained in this [TextComponent](#).

[getPasswordAuthentication\(\)](#) - Method in class [java.net.Authenticator](#)
Called when password authorization is needed.

[getPatch\(\)](#) - Method in class [javax.sound.midi.Instrument](#)
Obtains the Patch object that indicates the bank and program numbers where this instrument is to be stored in the synthesizer.

[getPatchList\(\)](#) - Method in class [javax.sound.midi.Sequence](#)
Obtains a list of patches referenced in this sequence.

[getPath\(\)](#) - Method in class [java.io.File](#)
Converts this abstract pathname into a pathname string.

[getPath\(\)](#) - Method in class [java.net.URL](#)
Returns the path part of this URL.

[getPath\(\)](#) - Method in class [javax.swing.event.MenuKeyEvent](#)

Returns the path to the menu item referenced by this event.

[getPath\(\)](#) - Method in class `javax.swing.event.TreeSelectionEvent`
Returns the first path element.

[getPath\(\)](#) - Method in class `javax.swing.event.MenuDragMouseEvent`
Returns the path to the selected menu item.

[getPath\(\)](#) - Method in class `javax.swing.event.TreeExpansionEvent`
Returns the path to the value that has been expanded/collapsed.

[getPath\(\)](#) - Method in class `javax.swing.event.TreeModelEvent`
Convenience method to get the array of objects from the `TreePath` instance that this event wraps.

[getPath\(\)](#) - Method in class `javax.swing.tree.DefaultMutableTreeNode`
Returns the path from the root, to get to this node.

[getPath\(\)](#) - Method in class `javax.swing.tree.TreePath`
Returns an ordered array of Objects containing the components of this `TreePath`.

[getPath\(\)](#) - Method in class `javax.swing.plaf.basic.BasicMenuItemUI`

[getPathBetweenRows\(int, int\)](#) - Method in class `javax.swing.JTree`
Returns `JTreePath` instances representing the path between `index0` and `index1` (including `index1`).

[getPathBounds\(JTree, TreePath\)](#) - Method in class `javax.swing.plaf.TreeUI`
Returns the `Rectangle` enclosing the label portion that the last item in path will be drawn into.

[getPathBounds\(JTree, TreePath\)](#) - Method in class `javax.swing.plaf.basic.BasicTreeUI`
Returns the `Rectangle` enclosing the label portion that the last item in path will be drawn into.

[getPathBounds\(JTree, TreePath\)](#) - Method in class `javax.swing.plaf.multi.MultiTreeUI`
Call `getPathBounds` on each UI handled by this `MultiUI`.

[getPathBounds\(TreePath\)](#) - Method in class `javax.swing.JTree`
Returns the `Rectangle` that the specified node will be drawn into.

[getPathClosestTo\(int, int\)](#) - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns the path to the node that is closest to `x,y`.

[getPathClosestTo\(int, int\)](#) - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns the path to the node that is closest to `x,y`.

[getPathClosestTo\(int, int\)](#) - Method in class `javax.swing.tree.FixedHeightLayoutCache`
Returns the path to the node that is closest to `x,y`.

[getPathComponent\(int\)](#) - Method in class `javax.swing.tree.TreePath`
Returns the path component at the specified index.

[getPathCount\(\)](#) - Method in class `javax.swing.tree.TreePath`
Returns the number of elements in the path.

[getPathForLocation\(int, int\)](#) - Method in class `javax.swing.JTree`
Returns the path for the node at the specified location.

[getPathForRow\(int\)](#) - Method in class `javax.swing.JTree`
Returns the path for the specified row.

[getPathForRow\(int\)](#) - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns the path for passed in row.

[getPathForRow\(int\)](#) - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns the path for passed in row.

[getPathForRow\(int\)](#) - Method in class `javax.swing.tree.FixedHeightLayoutCache`
Returns the path for passed in row.

[getPathForRow\(JTree, int\)](#) - Method in class `javax.swing.plaf.TreeUI`
Returns the path for passed in row.

[getPathForRow\(JTree, int\)](#) - Method in class `javax.swing.plaf.basic.BasicTreeUI`
Returns the path for passed in row.

[getPathForRow\(JTree, int\)](#) - Method in class `javax.swing.plaf.multi.MultiTreeUI`
Call `getPathForRow` on each UI handled by this `MultiUI`.

[getPathIterator\(AffineTransform\)](#) - Method in class `java.awt.Polygon`
Returns an iterator object that iterates along the boundary of this `Polygon` and provides

access to the geometry of the outline of this Polygon.

[getPathIterator\(AffineTransform\)](#) - Method in interface [java.awt.Shape](#)
Returns an iterator object that iterates along the Shape boundary and provides access to the geometry of the Shape outline.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.Rectangle2D](#)
Returns an iteration object that defines the boundary of this Rectangle2D.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.RoundRectangle2D](#)
Returns an iteration object that defines the boundary of this RoundRectangle2D.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.Area](#)
Creates a [PathIterator](#) for the outline of this Area object.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.Line2D](#)
Returns an iteration object that defines the boundary of this Line2D.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.Arc2D](#)
Returns an iteration object that defines the boundary of the arc.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.Ellipse2D](#)
Returns an iteration object that defines the boundary of this Ellipse2D.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.GeneralPath](#)
Returns a PathIterator object that iterates along the boundary of this Shape and provides access to the geometry of the outline of this Shape.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.QuadCurve2D](#)
Returns an iteration object that defines the boundary of this QuadCurve2D.

[getPathIterator\(AffineTransform\)](#) - Method in class [java.awt.geom.CubicCurve2D](#)
Returns an iteration object that defines the boundary of the shape.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.Polygon](#)
Returns an iterator object that iterates along the boundary of the Shape and provides access to the geometry of the outline of the Shape.

[getPathIterator\(AffineTransform, double\)](#) - Method in interface [java.awt.Shape](#)
Returns an iterator object that iterates along the Shape boundary and provides access to a flattened view of the Shape outline geometry.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.RectangularShape](#)
Returns an iterator object that iterates along the Shape object's boundary and provides access to a flattened view of the outline of the Shape object's geometry.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.Rectangle2D](#)
Returns an iteration object that defines the boundary of the flattened Rectangle2D.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.Area](#)
Creates a PathIterator for the flattened outline of this Area object.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.Line2D](#)
Returns an iteration object that defines the boundary of this flattened Line2D.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.GeneralPath](#)
Returns a PathIterator object that iterates along the boundary of the flattened Shape and provides access to the geometry of the outline of the Shape.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.QuadCurve2D](#)
Returns an iteration object that defines the boundary of the flattened shape of this QuadCurve2D.

[getPathIterator\(AffineTransform, double\)](#) - Method in class [java.awt.geom.CubicCurve2D](#)
Return an iteration object that defines the boundary of the flattened shape.

[getPaths\(\)](#) - Method in class [javax.swing.event.TreeSelectionEvent](#)
Returns the paths that have been added or removed from the selection.

[getPathToRoot\(TreeNode\)](#) - Method in class [javax.swing.tree.DefaultTreeModel](#)
Builds the parents of node up to and including the root node, where the original node is the last element in the returned array.

[getPathToRoot\(TreeNode, int\)](#) - Method in class [javax.swing.tree.DefaultMutableTreeModel](#)
Builds the parents of node up to and including the root node, where the original node is the last element in the returned array.

[getPathToRoot\(TreeNode, int\)](#) - Method in class [javax.swing.tree.DefaultTreeModel](#)
Builds the parents of node up to and including the root node, where the original node is the last element in the returned array.

getPatternSeparator() - Method in class java.text.DecimalFormatSymbols
Gets the character used to separate positive and negative subpatterns in a pattern.

getPCSType() - Method in class java.awt.color.ICC_Profile
Returns the color space type of the Profile Connection Space (PCS).

getPeer() - Method in class java.awt.Component
Deprecated. *As of JDK version 1.1, programs should not directly manipulate peers. replaced by boolean isDisplayable().*

getPeer() - Method in class java.awt.MenuComponent
Deprecated. *As of JDK version 1.1, programs should not directly manipulate peers.*

getPeer() - Method in class java.awt.Font
Deprecated. *Font rendering is now platform independent.*

getPercent() - Method in class java.text.DecimalFormatSymbols
Gets the character used for percent sign.

getPercentComplete() - Method in class javax.swing.JProgressBar
Returns the percentage/percent complete for the progress bar.

getPercentInstance() - Static method in class java.text.NumberFormat
Returns a percentage format for the current default locale.

getPercentInstance(Locale) - Static method in class java.text.NumberFormat
Returns a percentage format for the specified locale.

getPerMill() - Method in class java.text.DecimalFormatSymbols
Gets the character used for mille percent sign.

getPermission() - Method in class java.net.URLConnection
Returns a permission object representing the permission necessary to make the connection represented by this object.

getPermission() - Method in class java.net.HttpURLConnection

getPermission() - Method in class java.security.AccessControlException
Gets the Permission object associated with this exception, or null if there was no corresponding Permission object.

getPermissions() - Method in class java.security.ProtectionDomain
Returns the permissions of this domain.

getPermissions(CodeSource) - Method in class java.net.URLClassLoader
Returns the permissions for the given codesource object.

getPermissions(CodeSource) - Method in class java.security.SecureClassLoader
Returns the permissions for the given CodeSource object.

getPermissions(CodeSource) - Method in class java.security.Policy
Evaluates the global policy and returns a PermissionCollection object specifying the set of permissions allowed for code from the specified code source.

getPermissions(Principal) - Method in interface java.security.acl.Acl
Returns an enumeration for the set of allowed permissions for the specified principal (representing an entity such as an individual or a group).

getPitchBend() - Method in interface javax.sound.midi.MidiChannel
Obtains the upward of downward pitch offset for this channel.

getPixel(int, int, double[]) - Method in class java.awt.image.Raster
Returns the samples in an array of double for the specified pixel.

getPixel(int, int, double[], DataBuffer) - Method in class java.awt.image.SampleModel
Returns the samples for the specified pixel in an array of double.

getPixel(int, int, float[]) - Method in class java.awt.image.Raster
Returns the samples in an array of float for the specified pixel.

getPixel(int, int, float[], DataBuffer) - Method in class java.awt.image.SampleModel
Returns the samples for the specified pixel in an array of float.

getPixel(int, int, int[]) - Method in class java.awt.image.Raster
Returns the samples in an array of int for the specified pixel.

getPixel(int, int, int[], DataBuffer) - Method in class java.awt.image.SampleModel
Returns the samples for a specified pixel in an int array, one sample per array element.

getPixel(int, int, int[], DataBuffer) - Method in class java.awt.image.ComponentSampleModel
Returns all samples for the specified pixel in an int array, one sample per array element.

[getPixel\(int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.BandedSampleModel
Returns all samples for the specified pixel in an int array.

[getPixel\(int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.MultiPixelPackedSampleModel
Returns the specified single band pixel in the first element of an int array.

[getPixel\(int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.SinglePixelPackedSampleModel
Returns all samples in for the specified pixel in an int array.

[getPixelBitStride\(\)](#) - Method in class java.awt.image.MultiPixelPackedSampleModel
Returns the pixel bit stride in bits.

[getPixelColor\(int, int\)](#) - Method in class java.awt.Robot
Returns the color of a pixel at the given screen coordinates.

[getPixels\(\)](#) - Method in class java.awt.image.PixelGrabber
Get the pixel buffer.

[getPixels\(int, int, int, int, double\[\]\)](#) - Method in class java.awt.image.Raster
Returns a double array containing all samples for a rectangle of pixels, one sample per array element.

[getPixels\(int, int, int, int, double\[\], DataBuffer\)](#) - Method in class java.awt.image.SampleModel
Returns all samples for a rectangle of pixels in a double array, one sample per array element.

[getPixels\(int, int, int, int, float\[\]\)](#) - Method in class java.awt.image.Raster
Returns a float array containing all samples for a rectangle of pixels, one sample per array element.

[getPixels\(int, int, int, int, float\[\], DataBuffer\)](#) - Method in class java.awt.image.SampleModel
Returns all samples for a rectangle of pixels in a float array, one sample per array element.

[getPixels\(int, int, int, int, int\[\]\)](#) - Method in class java.awt.image.Raster
Returns an int array containing all samples for a rectangle of pixels, one sample per array element.

[getPixels\(int, int, int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.SampleModel
Returns all samples for a rectangle of pixels in an int array, one sample per array element.

[getPixels\(int, int, int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.ComponentSampleModel
Returns all samples for the specified rectangle of pixels in an int array, one sample per array element.

[getPixels\(int, int, int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.BandedSampleModel
Returns all samples for the specified rectangle of pixels in an int array, one sample per data array element.

[getPixels\(int, int, int, int, int\[\], DataBuffer\)](#) - Method in class java.awt.image.SinglePixelPackedSampleModel
Returns all samples for the specified rectangle of pixels in an int array, one sample per array element.

[getPixelSize\(\)](#) - Method in class java.awt.image.ColorModel
Returns the number of bits per pixel described by this ColorModel.

[getPixelStride\(\)](#) - Method in class java.awt.image.ComponentSampleModel
Returns the pixel stride of this ComponentSampleModel.

[getPoint\(\)](#) - Method in class java.awt.event.MouseEvent
Returns the x,y position of the event relative to the source component.

[getPoint1\(\)](#) - Method in class java.awt.GradientPaint
Returns a copy of the point P1 that anchors the first color.

[getPoint2\(\)](#) - Method in class java.awt.GradientPaint
Returns a copy of the point P2 which anchors the second color.

[getPoint2D\(Point2D, Point2D\)](#) - Method in class java.awt.image.LookupOp
Returns the location of the destination point given a point in the source.

[getPoint2D\(Point2D, Point2D\)](#) - Method in interface java.awt.image.BufferedImageOp
Returns the location of the destination point given a point in the source image.

[getPoint2D\(Point2D, Point2D\)](#) - Method in class java.awt.image.ConvolveOp
Returns the location of the destination point given a point in the source.

[getPoint2D\(Point2D, Point2D\)](#) - Method in class java.awt.image.BandCombineOp
Returns the location of the corresponding destination point given a point in the source Raster.

getPoint2D(Point2D, Point2D) - Method in class java.awt.image.AffineTransformOp
Returns the location of the corresponding destination point given a point in the source.

getPoint2D(Point2D, Point2D) - Method in interface java.awt.image.RasterOp
Returns the location of the destination point given a point in the source Raster.

getPoint2D(Point2D, Point2D) - Method in class java.awt.image.ColorConvertOp
Returns the location of the destination point given a point in the source.

getPoint2D(Point2D, Point2D) - Method in class java.awt.image.RescaleOp
Returns the location of the destination point given a point in the source.

getPointSize(int) - Method in class javax.swing.text.html.StyleSheet
Returns the point size, given a size index.

getPointSize(String) - Method in class javax.swing.text.html.StyleSheet
Given a string such as "+2", "-2", or "2", returns a point size value.

getPolicy() - Static method in class java.security.Policy
Returns the installed Policy object.

getPolyPressure(int) - Method in interface javax.sound.midi.MidiChannel
Obtains the pressure with which the specified key is being depressed.

getPopupHeightForRowCount(int) - Method in class javax.swing.plaf.basic.BasicComboPopup

getPopupMenu() - Method in class javax.swing.JMenu
Returns the popupmenu associated with this menu.

getPopupMenuOrigin() - Method in class javax.swing.JMenu
Computes the origin for the JMenu's popup menu.

getPort() - Method in class java.net.DatagramSocket
Returns the port for this socket.

getPort() - Method in class java.net.SocketImpl
Returns the value of this socket's port field.

getPort() - Method in class java.net.Socket
Returns the remote port to which this socket is connected.

getPort() - Method in class java.net.URL
Returns the port number of this URL.

getPort() - Method in class java.net.DatagramPacket
Returns the port number on the remote host to which this datagram is being sent or from which the datagram was received.

getPosition() - Method in class java.awt.font.LineBreakMeasurer
Returns the current position of this LineBreakMeasurer.

getPosition() - Method in class javax.swing.text.TabStop

getPosition(Component) - Method in class javax.swing.JLayeredPane
Get the relative position of the component within its layer.

getPosition(int) - Method in class javax.swing.SizeSequence
Returns the start position for the specified entry.

getPositionAbove(JTextComponent, int, int) - Static method in class javax.swing.text.Utilities
Determines the position in the model that is closest to the given view location in the row above.

getPositionBelow(JTextComponent, int, int) - Static method in class javax.swing.text.Utilities
Determines the position in the model that is closest to the given view location in the row below.

getPositionsInRange(Vector, int, int) - Method in class javax.swing.text.StringContent
Returns a Vector containing instances of UndoPosRef for the Positions in the range offset to offset + length.

getPositionsInRange(Vector, int, int) - Method in class javax.swing.text.GapContent
Returns a Vector containing instances of UndoPosRef for the Positions in the range offset to offset + length.

getPositivePrefix() - Method in class java.text.DecimalFormat
Get the positive prefix.

getPositiveSuffix() - Method in class java.text.DecimalFormat
Get the positive suffix.

getPrecision() - Method in class `javax.sound.sampled.FloatControl`
Obtains the resolution or granularity of the control, in the units that the control measures.

getPrecision(int) - Method in interface `java.sql.ResultSetMetaData`
Get the designated column's number of decimal digits.

getPredefinedCursor(int) - Static method in class `java.awt.Cursor`
Returns a cursor object with the specified predefined type.

getPreferredSize(AbstractButton, int) - Static method in class `javax.swing.plaf.basic.BasicGraphicsUtils`

getPreferredHeight() - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns the preferred height.

getPreferredHeight() - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns the preferred height.

getPreferredHorizontalSize() - Method in class `javax.swing.plaf.basic.BasicSliderUI`

getPreferredInnerHorizontal() - Method in class `javax.swing.plaf.basic.BasicProgressbarUI`

getPreferredInnerVertical() - Method in class `javax.swing.plaf.basic.BasicProgressbarUI`

getPreferredSize(JComponent, Icon, Icon, int) - Method in class `javax.swing.plaf.basic.BasicMenuItemUI`

getPreferredMinSize() - Method in class `javax.swing.plaf.basic.BasicTreeUI`
Returns the minimum preferred size.

getPreferredScrollableViewportSize() - Method in class `javax.swing.JList`
Computes the size of the viewport needed to display visibleRowCount rows.

getPreferredScrollableViewportSize() - Method in class `javax.swing.JTree`
Returns the preferred display size of a JTree.

getPreferredScrollableViewportSize() - Method in interface `javax.swing.Scrollable`
Returns the preferred size of the viewport for a view component.

getPreferredScrollableViewportSize() - Method in class `javax.swing.JTable`
Returns the preferred size of the viewport for this table.

getPreferredScrollableViewportSize() - Method in class `javax.swing.JTextArea`
Returns the preferred size of the viewport if this component is embedded in a JScrollPane.

getPreferredScrollableViewportSize() - Method in class `javax.swing.text.JTextComponent`
Returns the preferred size of the viewport for a view component.

getPreferredSize() - Method in class `java.awt.Component`
Gets the preferred size of this component.

getPreferredSize() - Method in class `java.awt.Container`
Returns the preferred size of this container.

getPreferredSize() - Method in class `java.awt.List`
Gets the preferred size of this scrolling list.

getPreferredSize() - Method in class `java.awt.TextField`
Gets the preferred size of this text field.

getPreferredSize() - Method in class `java.awt.TextArea`
Determines the preferred size of this text area.

getPreferredSize() - Method in class `javax.swing.JComponent`
If the preferredSize has been set to a non-null value just returns it.

getPreferredSize() - Method in class `javax.swing.JEditorPane`
Returns the preferred size for the JEditorPane.

getPreferredSize() - Method in class `javax.swing.JTextField`
Returns the preferred size Dimensions needed for this TextField.

getPreferredSize() - Method in class `javax.swing.JToolBar.Separator`
Returns the preferred size for the separator.

getPreferredSize() - Method in class `javax.swing.JTextArea`
Returns the preferred size of the TextArea.

getPreferredSize() - Method in class `javax.swing.Box.Filler`

Returns the preferred size of the component.

[getPreferredSize\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellRenderer](#)

Overrides JComponent.getPreferredSize to return slightly wider preferred size value.

[getPreferredSize\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellEditor](#).[DefaultTextField](#)

Overrides JTextField.getPreferredSize to return the preferred size based on current font, if set, or else use renderer's font.

[getPreferredSize\(\)](#) - Method in class javax.swing.tree.[DefaultTreeCellEditor](#).[EditorContainer](#)

Returns the preferred size for the Container.

[getPreferredSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicComboBoxRenderer](#)

[getPreferredSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSplitPaneDivider](#)

Returns dividerSize x dividerSize

[getPreferredSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicArrowButton](#)

[getPreferredSize\(\)](#) - Method in class javax.swing.plaf.metal.[MetalScrollbar](#)

[getPreferredSize\(int\)](#) - Method in class java.awt.[List](#)

Gets the preferred dimensions for a list with the specified number of rows.

[getPreferredSize\(int\)](#) - Method in class java.awt.[TextField](#)

Gets the preferred size of this text field with the specified number of columns.

[getPreferredSize\(int, int\)](#) - Method in class java.awt.[TextArea](#)

Determines the preferred size of a text area with the specified number of rows and columns.

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.[ComponentUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTextUI](#)

Gets the preferred size for the editor component.

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicSeparatorUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicMenuItemUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicButtonUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicRadioButtonUI](#)

The preferred size of the radio button

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarSeparatorUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicProgressBarUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicOptionPaneUI](#)

If c is the JOptionPane the receiver is contained in, the preferred size that is returned is the maximum of the preferred size of the LayoutManager for the JOptionPane, and getMinimumOptionPaneSize.

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicPopupMenuUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicTableUI](#)

Return the preferred size of the table.

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolTipUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicScrollbarUI](#)

A vertical scrollbar's preferred width is the maximum of preferred widths of the (non null) increment/decrement buttons, and the minimum width of the thumb.

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicToolBarUI](#)

[getPreferredSize\(JComponent\)](#) - Method in class javax.swing.plaf.basic.[BasicInternalFrameUI](#)

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopPaneUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicListUI
The preferredSize of a list is total height of the rows and the maximum width of the cells.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicLabelUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicComboBoxUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTableHeaderUI
Return the preferred size of the header.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicMenuBarUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicPopupMenuSeparatorUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicTreeUI
Returns the preferred size to properly display the tree, this is a cover method for
getPreferredSize(c, false).

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSplitPaneUI
Returns the preferred size for the passed in component, This is passed off to the current
layoutmanager.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicScrollPaneUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicDesktopIconUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.basic.BasicSliderUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalSeparatorUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalPopupMenuSeparatorUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalFileChooserUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalScrollBarUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalDesktopIconUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.metal.MetalToolTipUI

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiListUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiSeparatorUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiLabelUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPopupMenuUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiPanelUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiScrollBarUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTextUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiComboBoxUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiTableHeaderUI
Call getPreferredSize on each UI handled by this MultiUI.

getPreferredSize(JComponent) - Method in class javax.swing.plaf.multi.MultiFileChooserUI

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiColorChooserUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiTreeUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiViewportUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiTabbedPaneUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiProgressBarUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiScrollPaneUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiOptionPaneUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiSplitPaneUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiButtonUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiToolBarUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiSliderUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiDesktopPaneUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiTableUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiDesktopIconUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuItemUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiInternalFrameUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiToolTipUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent)` - Method in class `javax.swing.plaf.multi.MultiMenuBarUI`

Call `getPreferredSize` on each UI handled by this `MultiUI`.

`getPreferredSize(JComponent, boolean)` - Method in class `javax.swing.plaf.basic.BasicTreeUI`

Returns the preferred size to represent the tree in *c*.

`getPreferredSizeOfComponent(Component)` - Method in class `javax.swing.plaf.basic.BasicSplitPaneUI`.
`BasicHorizontalLayoutManager`

Returns the width of the passed in Components preferred size.

`getPreferredSpan(int)` - Method in class `javax.swing.text.View`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.GlyphView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.BoxView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.PlainView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.FieldView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.AsyncBoxView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.ComponentView`

Determines the preferred span for this view along an axis.

`getPreferredSpan(int)` - Method in class `javax.swing.text.IconView`

Determines the preferred span for this view along an axis.

[getPreferredSpan\(int\)](#) - Method in class javax.swing.text.[WrappedPlainView](#)
 Determines the preferred span for this view along an axis.

[getPreferredSpan\(int\)](#) - Method in class javax.swing.text.html.[ParagraphView](#)
 Determines the preferred span for this view.

[getPreferredVerticalSize\(\)](#) - Method in class javax.swing.plaf.basic.[BasicSliderUI](#)

[getPreferredWidth\(\)](#) - Method in class javax.swing.table.[TableColumn](#)
 Returns the preferred width of the TableColumn.

[getPreferredWidth\(Rectangle\)](#) - Method in class javax.swing.tree.[AbstractLayoutCache](#)
 Returns the preferred width for the passed in region.

[getPreferredWidth\(Rectangle\)](#) - Method in class javax.swing.tree.[VariableHeightLayoutCache](#)
 Returns the preferred width and height for the region in visibleRegion.

[getPrefix\(int\)](#) - Method in interface javax.naming.[Name](#)
 Creates a name whose components consist of a prefix of the components of this name.

[getPrefix\(int\)](#) - Method in class javax.naming.[CompoundName](#)
 Creates a compound name whose components consist of a prefix of the components in this compound name.

[getPrefix\(int\)](#) - Method in class javax.naming.[CompositeName](#)
 Creates a composite name whose components consist of a prefix of the components in this composite name.

[getPresentationName\(\)](#) - Method in class javax.swing.text.[AbstractDocument.DefaultDocumentEvent](#)
 Provides a localized, human readable description of this edit suitable for use in, say, a change log.

[getPresentationName\(\)](#) - Method in class javax.swing.undo.[AbstractUndoableEdit](#)
 This default implementation returns "".

[getPresentationName\(\)](#) - Method in class javax.swing.undo.[CompoundEdit](#)
 Returns getPresentationName from the last UndoableEdit added to edits.

[getPresentationName\(\)](#) - Method in class javax.swing.undo.[StateEdit](#)
 Gets the presentation name for this edit

[getPresentationName\(\)](#) - Method in interface javax.swing.undo.[UndoableEdit](#)
 Provide a localized, human readable description of this edit suitable for use in, say, a change log.

[getPreservesUnknownTags\(\)](#) - Method in class javax.swing.text.html.[HTMLDocument](#)

[getPressedIcon\(\)](#) - Method in class javax.swing.[AbstractButton](#)
 Returns the pressed icon for the button.

[getPreviewPanel\(\)](#) - Method in class javax.swing.[JColorChooser](#)
 Returns the preview panel that shows a chosen color.

[getPreviewPanel\(\)](#) - Static method in class javax.swing.colorchooser.[ColorChooserComponentFactory](#)

[getPreviousBounds\(JInternalFrame\)](#) - Method in class javax.swing.[DefaultDesktopManager](#)

[getPreviousLeaf\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
 Returns the leaf before this node or null if this node is the first leaf in the tree.

[getPreviousNode\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
 Returns the node that precedes this node in a preorder traversal of this node's tree.

[getPreviousSibling\(\)](#) - Method in class javax.swing.tree.[DefaultMutableTreeNode](#)
 Returns the previous sibling of this node in the parent's children array.

[getPreviousTabIndex\(int\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getPreviousWord\(JTextComponent, int\)](#) - Static method in class javax.swing.text.[Utilities](#)
 Determine the start of the prev word for the given location.

[getPrimaryl\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getPrimaryl\(\)](#) - Method in class javax.swing.plaf.metal.[DefaultMetalTheme](#)

getPrimary2() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimary2() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getPrimary3() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimary3() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getPrimaryControl() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getPrimaryControl() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimaryControlDarkShadow() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getPrimaryControlDarkShadow() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimaryControlHighlight() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getPrimaryControlHighlight() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimaryControlInfo() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getPrimaryControlInfo() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimaryControlShadow() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getPrimaryControlShadow() - Method in class javax.swing.plaf.metal.MetalTheme

getPrimaryKeys(String, String, String) - Method in interface java.sql.DatabaseMetaData
Gets a description of a table's primary key columns.

getPrimaryType() - Method in class java.awt.datatransfer.DataFlavor

getPrimeExponentP() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the primeExponentP.

getPrimeExponentP() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the primeExponentP.

getPrimeExponentQ() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the primeExponentQ.

getPrimeExponentQ() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the primeExponentQ.

getPrimeP() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the primeP.

getPrimeP() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the primeP.

getPrimeQ() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the primeQ.

getPrimeQ() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the primeQ.

getPrincipal() - Method in interface java.security.Certificate
Deprecated. Returns the principal of the principal-key pair being guaranteed by the guarantor.

getPrincipal() - Method in interface java.security.acl.ACLEntry
Returns the principal for which permissions are granted or denied by this ACL entry.

getPrintable(int) - Method in class java.awt.print.Book
Returns the Printable instance responsible for rendering the page specified by pageIndex.

getPrintable(int) - Method in interface java.awt.print.Pageable
Returns the Printable instance responsible for rendering the page specified by pageIndex.

getPrinter() - Method in class java.awt.JobAttributes

Returns the destination printer for jobs using these attributes.

[getPrinterJob\(\)](#) - Method in interface [java.awt.print.PrinterGraphics](#)
Returns the PrinterJob that is controlling the current rendering request.

[getPrinterJob\(\)](#) - Static method in class [java.awt.print.PrinterJob](#)
Creates and returns a PrinterJob.

[getPrinterResolution\(\)](#) - Method in class [java.awt.PageAttributes](#)
Returns the print resolution for pages using these attributes.

[getPrintJob\(\)](#) - Method in interface [java.awt.PrintGraphics](#)
Returns the PrintJob object from which this PrintGraphics object originated.

[getPrintJob\(Frame, String, JobAttributes, PageAttributes\)](#) - Method in class [java.awt.Toolkit](#)
Gets a PrintJob object which is the result of initiating a print operation on the toolkit's platform.

[getPrintJob\(Frame, String, Properties\)](#) - Method in class [java.awt.Toolkit](#)
Gets a PrintJob object which is the result of initiating a print operation on the toolkit's platform.

[getPrintQuality\(\)](#) - Method in class [java.awt.PageAttributes](#)
Returns the print quality for pages using these attributes.

[getPriority\(\)](#) - Method in class [java.lang.Thread](#)
Returns this thread's priority.

[getPrivate\(\)](#) - Method in class [java.security.KeyPair](#)
Returns a reference to the private key component of this key pair.

[getPrivateExponent\(\)](#) - Method in interface [java.security.interfaces.RSAPrivateKey](#)
Returns the private exponent.

[getPrivateExponent\(\)](#) - Method in class [java.security.spec.RSAPrivateKeySpec](#)
Returns the private exponent.

[getPrivateKey\(\)](#) - Method in class [java.security.Signer](#)
Deprecated. Returns this signer's private key.

[getProcedureColumns\(String, String, String, String\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
Gets a description of a catalog's stored procedure parameters and result columns.

[getProcedures\(String, String, String\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
Gets a description of the stored procedures available in a catalog.

[getProcedureTerm\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
What's the database vendor's preferred term for "procedure"?

[getProfile\(\)](#) - Method in class [java.awt.color.ICC_ColorSpace](#)
Returns the ICC_Profile for this ICC_ColorSpace.

[getProfileClass\(\)](#) - Method in class [java.awt.color.ICC_Profile](#)
Returns the profile class.

[getProgram\(\)](#) - Method in class [javax.sound.midi.Patch](#)
Returns the index, within a bank, of the instrument whose location this Patch specifies.

[getProgram\(\)](#) - Method in interface [javax.sound.midi.MidiChannel](#)
Obtains the current program number for this channel.

[getProgressBarBorder\(\)](#) - Static method in class [javax.swing.plaf.basic.BasicBorders](#)

[getProgressMonitor\(\)](#) - Method in class [javax.swing.ProgressMonitorInputStream](#)
Get the ProgressMonitor object being used by this stream.

[getPropagatedFrom\(\)](#) - Method in class [java.beans.beancontext.BeanContextEvent](#)
Gets the BeanContext from which this event was propagated.

[getPropagationId\(\)](#) - Method in class [java.beans.PropertyChangeEvent](#)
The "propagationId" field is reserved for future use.

[getProperties\(\)](#) - Static method in class [java.lang.System](#)
Determines the current system properties.

[getProperty\(Object\)](#) - Method in interface [javax.swing.text.Document](#)
Gets properties associated with the document.

[getProperty\(Object\)](#) - Method in class [javax.swing.text.AbstractDocument](#)
A convenience method for looking up a property value.

[getProperty\(ParameterBlock, String\)](#) - Method in interface [java.awt.image.renderable.ContextualRenderedImageFactory](#)

Gets the appropriate instance of the property specified by the name parameter.

getProperty(String) - Method in interface java.awt.image.RenderedImage
Gets a property from the property set of this image.

getProperty(String) - Method in class java.awt.image.BufferedImage
Returns a property of the image by name.

getProperty(String) - Method in class java.awt.image.renderable.RenderableImageOp
Gets a property from the property set of this image.

getProperty(String) - Method in interface java.awt.image.renderable.RenderableImage
Gets a property from the property set of this image.

getProperty(String) - Static method in class java.lang.System
Gets the system property indicated by the specified key.

getProperty(String) - Static method in class java.security.Security
Gets a security property value.

getProperty(String) - Method in class java.util.Properties
Searches for the property with the specified key in this property list.

getProperty(String, ImageObserver) - Method in class java.awt.Image
Gets a property of this image by name.

getProperty(String, ImageObserver) - Method in class java.awt.image.BufferedImage
Returns a property of the image by name.

getProperty(String, String) - Static method in class java.awt.Toolkit
Gets a property with the specified key and default.

getProperty(String, String) - Static method in class java.lang.System
Gets the system property indicated by the specified key.

getProperty(String, String) - Method in class java.util.Properties
Searches for the property with the specified key in this property list.

getPropertyChangeEvent() - Method in class java.beans.PropertyVetoException
Gets the vetoed PropertyChangeEvent.

getPropertyDescriptors() - Method in interface java.beans.BeanInfo
Gets the beans PropertyDescriptors.

getPropertyDescriptors() - Method in class java.beans.SimpleBeanInfo
Deny knowledge of properties.

getPropertyEditorClass() - Method in class java.beans.PropertyDescriptor
Gets any explicit PropertyEditor Class that has been registered for this property.

getPropertyInfo(String, Properties) - Method in interface java.sql.Driver
Gets information about the possible properties for this driver.

getPropertyName() - Method in class java.beans.PropertyChangeEvent
Gets the programmatic name of the property that was changed.

getPropertyNames() - Method in interface java.awt.image.RenderedImage
Returns an array of names recognized by getProperty(String) or null, if no property names are recognized.

getPropertyNames() - Method in class java.awt.image.BufferedImage
Returns an array of names recognized by getProperty(String) or null, if no property names are recognized.

getPropertyNames() - Method in interface java.awt.image.renderable.ContextualRenderedImageFactory
Returns a list of names recognized by getProperty.

getPropertyNames() - Method in class java.awt.image.renderable.RenderableImageOp
Return a list of names recognized by getProperty.

getPropertyNames() - Method in interface java.awt.image.renderable.RenderableImage
Returns a list of names recognized by getProperty.

getPropertyOverrides() - Method in class java.rmi.activation.ActivationGroupDesc
Returns the group's property-override list.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicTextUI
Gets the name used as a key to look up properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicEditorPaneUI
Fetches the name used as a key to lookup properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicTextPaneUI
Fetches the name used as a key to lookup properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicMenuItemUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicRadioButtonMenuItemUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicButtonUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicToggleButtonUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicRadioButtonUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicMenuUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicCheckBoxMenuItemUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicTextFieldUI

Fetches the name used as a key to lookup properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicPasswordFieldUI

Fetches the name used as a key to look up properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicCheckBoxUI

getPropertyPrefix() - Method in class javax.swing.plaf.basic.BasicTextAreaUI

Fetches the name used as a key to look up properties through the UIManager.

getPropertyPrefix() - Method in class javax.swing.plaf.metal.MetalCheckBoxUI

getPropertyType() - Method in class java.beans.PropertyDescriptor

Gets the Class object for the property.

getProtectionDomain() - Method in class java.lang.Class

Returns the ProtectionDomain of this class.

getProtocol() - Method in class java.net.URL

Returns the protocol name of this URL.

getPrototypeCellValue() - Method in class javax.swing.JList

Returns the cell width of the "prototypical cell" -- a cell used for the calculation of cell widths, because it has the same value as all other list items.

getProvider() - Method in class java.security.KeyFactory

Returns the provider of this key factory object.

getProvider() - Method in class java.security.KeyPairGenerator

Returns the provider of this key pair generator object.

getProvider() - Method in class java.security.SecureRandom

Returns the provider of this SecureRandom object.

getProvider() - Method in class java.security.AlgorithmParameters

Returns the provider of this parameter object.

getProvider() - Method in class java.security.AlgorithmParameterGenerator

Returns the provider of this algorithm parameter generator object.

getProvider() - Method in class java.security.KeyStore

Returns the provider of this keystore.

getProvider() - Method in class java.security.MessageDigest

Returns the provider of this message digest object.

getProvider() - Method in class java.security.Signature

Returns the provider of this signature object.

getProvider() - Method in class java.security.cert.CertificateFactory

Returns the provider of this certificate factory.

getProvider(String) - Static method in class java.security.Security

Returns the provider installed with the specified name, if any.

getProviders() - Static method in class java.security.Security

Returns an array containing all the installed providers.

getProviders(Map) - Static method in class java.security.Security

Returns an array containing all installed providers that satisfy the specified selection

criteria, or null if no such providers have been installed.

getProviders(String) - Static method in class java.security.Security
Returns an array containing all installed providers that satisfy the specified selection criterion, or null if no such providers have been installed.

getProxyClass(ClassLoader, Class[]) - Static method in class java.lang.reflect.Proxy
Returns the java.lang.Class object for a proxy class given a class loader and an array of interfaces.

getPSName() - Method in class java.awt.Font
Returns the postscript name of this Font.

getPublic() - Method in class java.security.KeyPair
Returns a reference to the public key component of this key pair.

getPublicExponent() - Method in interface java.security.interfaces.RSAPublicKey
Returns the public exponent.

getPublicExponent() - Method in interface java.security.interfaces.RSAPrivateCrtKey
Returns the public exponent.

getPublicExponent() - Method in class java.security.spec.RSAPrivateCrtKeySpec
Returns the public exponent.

getPublicExponent() - Method in class java.security.spec.RSAKeyGenParameterSpec
Returns the public-exponent value.

getPublicExponent() - Method in class java.security.spec.RSAPublicKeySpec
Returns the public exponent.

getPublicKey() - Method in class java.security.Identity
Deprecated. Returns this identity's public key.

getPublicKey() - Method in interface java.security.Certificate
Deprecated. Returns the key of the principal-key pair being guaranteed by the guarantor.

getPublicKey() - Method in class java.security.cert.Certificate
Gets the public key from this certificate.

getQ() - Method in interface java.security.interfaces.DSAPrivateKey
Returns the subprime, q.

getQ() - Method in class java.security.spec.DSAPrivateKeySpec
Returns the sub-prime q.

getQ() - Method in class java.security.spec.DSAPublicKeySpec
Returns the sub-prime q.

getQ() - Method in class java.security.spec.DSAPrivateKeySpec
Returns the sub-prime q.

getQuery() - Method in class java.net.URL
Returns the query part of this URL.

getQueryTimeout() - Method in interface java.sql.Statement
Retrieves the number of seconds the driver will wait for a Statement object to execute.

getRadioButtonBorder() - Static method in class javax.swing.plaf.basic.BasicBorders

getRadioButtonIcon() - Static method in class javax.swing.plaf.basic.BasicIconFactory

getRadioButtonIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getRadioButtonMenuItemIcon() - Static method in class javax.swing.plaf.basic.BasicIconFactory

getRadioButtonMenuItemIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getRaisedBevelBorderUIResource() - Static method in class javax.swing.plaf.BorderUIResource

getRaster() - Method in class java.awt.image.BufferedImage
Returns the WritableRaster.

getRaster(int, int, int, int) - Method in interface java.awt.PaintContext
Returns a Raster containing the colors generated for the graphics operation.

getRawOffset() - Method in class java.util.TimeZone
Gets unmodified offset, NOT modified in case of daylight savings.

getRawOffset() - Method in class java.util.SimpleTimeZone
 Overrides TimeZone Gets the GMT offset for this time zone.

getRead() - Method in class java.sql.DataTruncation
 Indicates whether or not the value was truncated on a read.

getReader(int) - Method in class javax.swing.text.html.HTMLDocument
 Fetches the reader for the parser to use to load the document with HTML.

getReader(int, int, int, HTML.Tag) - Method in class javax.swing.text.html.HTMLDocument
 Fetches the reader for the parser to use to load the document with HTML.

getReaderForText(Transferable) - Method in class java.awt.datatransfer.DataFlavor
 Gets a reader for an input stream, decoded for the expected charset (encoding).

getReadMethod() - Method in class java.beans.PropertyDescriptor
 Gets the method that should be used to read the property value.

getReceiveBufferSize() - Method in class java.net.DatagramSocket
 Get value of the SO_RCVBUF option for this DatagramSocket, that is the buffer size used by the platform for input on this DatagramSocket.

getReceiveBufferSize() - Method in class java.net.Socket
 Gets the value of the SO_RCVBUF option for this Socket, that is the buffer size used by the platform for input on this Socket.

getReceiver() - Static method in class javax.sound.midi.MidiSystem
 Obtains a MIDI receiver from an external MIDI port or other default source.

getReceiver() - Method in interface javax.sound.midi.Transmitter
 Obtains the current receiver to which this transmitter will deliver MIDI messages.

getReceiver() - Method in interface javax.sound.midi.MidiDevice
 Obtains a MIDI IN receiver through which the MIDI device may receive MIDI data.

getRecursionLimit() - Method in class java.awt.geom.FlatteningPathIterator
 Returns the recursion limit of this iterator.

getRed() - Method in class java.awt.Color
 Returns the red component in the range 0-255 in the default sRGB space.

getRed(int) - Method in class java.awt.image.ColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(int) - Method in class java.awt.image.ComponentColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(int) - Method in class java.awt.image.DirectColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(int) - Method in class java.awt.image.IndexColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(Object) - Method in class java.awt.image.ColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(Object) - Method in class java.awt.image.ComponentColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRed(Object) - Method in class java.awt.image.DirectColorModel
 Returns the red color component for the specified pixel, scaled from 0 to 255 in the default RGB ColorSpace, sRGB.

getRedMask() - Method in class java.awt.image.DirectColorModel
 Returns the mask indicating which bits in an int pixel representation contain the red color component.

getRedoPresentationName() - Method in class javax.swing.text.AbstractDocument.DefaultDocumentEvent
 Provides a localized, human readable description of the redoable form of this edit, e.g.

getRedoPresentationName() - Method in class javax.swing.undo.AbstractUndoableEdit
 If getPresentationName() returns "", returns AbstractUndoableEdit.RedoName.

getRedoPresentationName() - Method in class javax.swing.undo.CompoundEdit

Returns `getRedoPresentationName` from the last `UndoableEdit` added to edits.

`getRedoPresentationName()` - Method in class `javax.swing.undo.UndoManager`
 If `InProgress`, returns `getRedoPresentationName` of the significant edit that will be redone when `redo()` is invoked.

`getRedoPresentationName()` - Method in interface `javax.swing.undo.UndoableEdit`
 Provide a localized, human readable description of the redoable form of this edit, e.g.

`getReds(byte[])` - Method in class `java.awt.image.IndexColorModel`
 Copies the array of red color components into the specified array.

`getRef()` - Method in class `java.net.URL`
 Returns the anchor (also known as the "reference") of this URL.

`getRef()` - Method in class `java.rmi.server.RemoteObject`
 Returns the remote reference for the remote object.

`getRef(int)` - Method in interface `java.sql.CallableStatement`
 Gets the value of a JDBC REF(<structured-type>) parameter as a `Ref` object in the Java programming language.

`getRef(int)` - Method in interface `java.sql.ResultSet`
 Returns the value of the designated column in the current row of this `ResultSet` object as a `Ref` object in the Java programming language.

`getRef(String)` - Method in interface `java.sql.ResultSet`
 Returns the value of the designated column in the current row of this `ResultSet` object as a `Ref` object in the Java programming language.

`getRefClass(ObjectOutput)` - Method in interface `java.rmi.server.RemoteRef`
 Returns the class name of the ref type to be serialized onto the stream 'out'.

`getReference()` - Method in interface `javax.naming.Referenceable`
 Retrieves the Reference of this object.

`getReferralContext()` - Method in class `javax.naming.ReferralException`
 Retrieves the context at which to continue the method.

`getReferralContext()` - Method in class `javax.naming.ldap.LdapReferralException`
 Retrieves the context at which to continue the method using the context's environment and no controls.

`getReferralContext(Hashtable)` - Method in class `javax.naming.ReferralException`
 Retrieves the context at which to continue the method using environment properties.

`getReferralContext(Hashtable)` - Method in class `javax.naming.ldap.LdapReferralException`
 Retrieves the context at which to continue the method using environment properties and no controls.

`getReferralContext(Hashtable, Control[])` - Method in class `javax.naming.ldap.LdapReferralException`
 Retrieves the context at which to continue the method using request controls and environment properties.

`getReferralInfo()` - Method in class `javax.naming.ReferralException`
 Retrieves information (such as URLs) related to this referral.

`getReferrals()` - Method in interface `javax.naming.ldap.UnsolicitedNotification`
 Retrieves the referral(s) sent by the server.

`getRegisteredKeyStrokes()` - Method in class `javax.swing.JComponent`
 Returns the `KeyStrokes` that will initiate registered actions.

`getRegistry()` - Static method in class `java.rmi.registry.LocateRegistry`
 Returns a reference to the the remote object Registry for the local host on the default registry port of 1099.

`getRegistry(int)` - Static method in class `java.rmi.registry.LocateRegistry`
 Returns a reference to the the remote object Registry for the local host on the specified port.

`getRegistry(String)` - Static method in class `java.rmi.registry.LocateRegistry`
 Returns a reference to the remote object Registry on the specified host on the default registry port of 1099.

`getRegistry(String, int)` - Static method in class `java.rmi.registry.LocateRegistry`
 Returns a reference to the remote object Registry on the specified host and port.

`getRegistry(String, int, RMIClientSocketFactory)` - Static method in class `java.rmi.registry.LocateRegistry`

Returns a locally created remote reference to the remote object Registry on the specified host and port.

[getRemaining\(\)](#) - Method in class `java.util.zip.Inflater`
Returns the total number of bytes remaining in the input buffer.

[getRemainingName\(\)](#) - Method in class `javax.naming.NamingException`
Retrieves the remaining unresolved portion of the name.

[getRemainingName\(\)](#) - Method in class `javax.naming.spi.ResolveResult`
Retrieves the remaining unresolved portion of the name.

[getRemainingNewName\(\)](#) - Method in class `javax.naming.CannotProceedException`
Retrieves the "remaining new name" field of this exception, which is used when this exception is thrown during a `rename()` operation.

[getRemoveListenerMethod\(\)](#) - Method in class `java.beans.EventSetDescriptor`
Gets the method used to remove event listeners.

[getRenderableSource\(int\)](#) - Method in class `java.awt.image.renderable.ParameterBlock`
A convenience method to return a source as a `RenderableImage`.

[getRenderedSource\(int\)](#) - Method in class `java.awt.image.renderable.ParameterBlock`
A convenience method to return a source as a `RenderedImage`.

[getRenderer\(\)](#) - Method in class `javax.swing.JComboBox`
Returns the renderer used to display the selected item in the `JComboBox` field.

[getRenderingHint\(RenderingHints.Key\)](#) - Method in class `java.awt.Graphics2D`
Returns the value of a single preference for the rendering algorithms.

[getRenderingHints\(\)](#) - Method in class `java.awt.Graphics2D`
Gets the preferences for the rendering algorithms.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.LookupOp`
Returns the rendering hints for this op.

[getRenderingHints\(\)](#) - Method in interface `java.awt.image.BufferedImageOp`
Returns the rendering hints for this `BufferedImageOp`.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.ConvolveOp`
Returns the rendering hints for this op.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.BandCombineOp`
Returns the rendering hints for this operation.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.AffineTransformOp`
Returns the rendering hints used by this transform operation.

[getRenderingHints\(\)](#) - Method in interface `java.awt.image.RasterOp`
Returns the rendering hints for this `RasterOp`.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.ColorConvertOp`
Returns the rendering hints used by this op.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.RescaleOp`
Returns the rendering hints for this op.

[getRenderingHints\(\)](#) - Method in class `java.awt.image.renderable.RenderContext`
Gets the rendering hints of this `RenderContext`.

[getReorderingAllowed\(\)](#) - Method in class `javax.swing.table.JTableHeader`
Returns true if the user is allowed to rearrange columns by dragging their headers, false otherwise.

[getRepresentationClass\(\)](#) - Method in class `java.awt.datatransfer.DataFlavor`
Returns the Class which objects supporting this `DataFlavor` will return when this `DataFlavor` is requested.

[getRequestControls\(\)](#) - Method in class `javax.naming.ldap.InitialLdapContext`

[getRequestControls\(\)](#) - Method in interface `javax.naming.ldap.LdapContext`
Retrieves the request controls in effect for this context.

[getRequestingPort\(\)](#) - Method in class `java.net.Authenticator`
Gets the port number for the requested connection.

[getRequestingPrompt\(\)](#) - Method in class `java.net.Authenticator`
Gets the prompt string given by the requestor.

[getRequestingProtocol\(\)](#) - Method in class `java.net.Authenticator`
Give the protocol that's requesting the connection.

getRequestingScheme() - Method in class java.net.Authenticator
 Gets the scheme of the requestor (the HTTP scheme for an HTTP firewall, for example).

getRequestingSite() - Method in class java.net.Authenticator
 Gets the InetAddress of the site requesting authorization, or null if not available.

getRequestMethod() - Method in class java.net.HttpURLConnection
 Get the request method.

getRequestProperty(String) - Method in class java.net.URLConnection
 Returns the value of the named general request property for this connection.

getReshowDelay() - Method in class javax.swing.ToolTipManager
 Returns the reshow delay value.

getResizable() - Method in class javax.swing.table.TableColumn
 Returns true if the user is allowed to resize the TableColumn's width, false otherwise.

getResizeWeight() - Method in class javax.swing.JSplitPane
 Returns the number that determines how extra space is distributed.

getResizeWeight(int) - Method in class javax.swing.text.View
 Determines the resizability of the view along the given axis.

getResizeWeight(int) - Method in class javax.swing.text.BoxView
 Gets the resize weight.

getResizeWeight(int) - Method in class javax.swing.text.FieldView
 Determines the resizability of the view along the given axis.

getResizeWeight(int) - Method in class javax.swing.text.TableView.TableRow
 Determines the resizability of the view along the given axis.

getResizeWeight(int) - Method in class javax.swing.text.html.BlockView
 Gets the resize weight.

getResizingAllowed() - Method in class javax.swing.table.JTableHeader
 Returns true if the user is allowed to resize columns by dragging between their headers, false otherwise.

getResizingColumn() - Method in class javax.swing.table.JTableHeader
 Returns the resizing column.

getResolution() - Method in class javax.sound.midi.Sequence
 Obtains the timing resolution for this sequence.

getResolution() - Method in class javax.sound.midi.MidiFileFormat
 Obtains the timing resolution for the MIDI file.

getResolvedName() - Method in class javax.naming.NamingException
 Retrieves the leading portion of the name that was resolved successfully.

getResolvedObj() - Method in class javax.naming.NamingException
 Retrieves the object to which resolution was successful.

getResolvedObj() - Method in class javax.naming.spi.ResolveResult
 Retrieves the Object to which resolution was successful.

getResolveParent() - Method in interface javax.swing.text.Keymap
 Fetches the parent keymap used to resolve key-bindings.

getResolveParent() - Method in class javax.swing.text.SimpleAttributeSet
 Gets the resolving parent.

getResolveParent() - Method in class javax.swing.text.StyleContext.SmallAttributeSet
 If not overridden, the resolving parent defaults to the parent element.

getResolveParent() - Method in class javax.swing.text.StyleContext.NamedStyle
 Gets attributes from the parent.

getResolveParent() - Method in class javax.swing.text.AbstractDocument.AbstractElement
 Gets the resolving parent.

getResolveParent() - Method in interface javax.swing.text.AttributeSet
 Gets the resolving parent.

getResolveParent() - Method in class javax.swing.text.html.HTMLDocument.RunElement
 Gets the resolving parent.

getResolveParent() - Method in class javax.swing.text.html.HTMLDocument.BlockElement
 Gets the resolving parent.

getResource(String) - Method in class java.lang.ClassLoader
 Finds the resource with the given name.

getResource(String) - Method in class java.lang.Class

Finds a resource with a given name.

getResource(String, BeanContextChild) - Method in class java.beans.beancontext.BeanContextSupport

getResource(String, BeanContextChild) - Method in interface java.beans.beancontext.BeanContext

Analogous to java.lang.ClassLoader.getResource(), this method allows a BeanContext implementation to interpose behavior between the child Component and underlying ClassLoader.

getResourceAsStream(String) - Method in class java.lang.ClassLoader

Returns an input stream for reading the specified resource.

getResourceAsStream(String) - Method in class java.lang.Class

Finds a resource with a given name.

getResourceAsStream(String, BeanContextChild) - Method in class java.beans.beancontext.BeanContextSupport

getResourceAsStream(String, BeanContextChild) - Method in interface java.beans.beancontext.BeanContext

Analogous to java.lang.ClassLoader.getResourceAsStream(), this method allows a BeanContext implementation to interpose behavior between the child Component and underlying ClassLoader.

getResources() - Method in interface javax.sound.midi.Soundbank

Extracts a list of non-Instrument resources contained in the sound bank.

getResources(String) - Method in class java.lang.ClassLoader

Finds all the resources with the given name.

getResponseCode() - Method in class java.net.HttpURLConnection

Gets HTTP response status from responses like:

getResponseControls() - Method in class javax.naming.ldap.InitialLdapContext

getResponseControls() - Method in interface javax.naming.ldap.LdapContext

Retrieves the response controls produced as a result of the last method invoked on this context.

getResponseMessage() - Method in class java.net.HttpURLConnection

Gets the HTTP response message, if any, returned along with the response code from a server.

getRestartMode() - Method in class java.rmi.activation.ActivationDesc

Returns the "restart" mode of the object associated with this activation descriptor.

getResultSet() - Method in interface java.sql.Statement

Returns the current result as a ResultSet object.

getResultSet() - Method in interface java.sql.Array

Returns a result set that contains the elements of the SQL ARRAY value designated by this Array object.

getResultSet(long, int) - Method in interface java.sql.Array

Returns a result set holding the elements of the subarray that starts at index index and contains up to count successive elements.

getResultSet(long, int, Map) - Method in interface java.sql.Array

Returns a result set holding the elements of the subarray that starts at index index and contains up to count successive elements.

getResultSet(Map) - Method in interface java.sql.Array

Returns a result set that contains the elements of the SQL ARRAY value designated by this Array object.

getResultSetConcurrency() - Method in interface java.sql.Statement

Retrieves the result set concurrency for ResultSet objects generated by this Statement object.

getResultSetType() - Method in interface java.sql.Statement

Retrieves the result set type for ResultSet objects generated by this Statement object.

getResultStream(boolean) - Method in interface java.rmi.server.RemoteCall

Deprecated. *no replacement*

getReturningAttributes() - Method in class javax.naming.directory.SearchControls

Retrieves the attributes that will be returned as part of the search.

getReturningObjFlag() - Method in class javax.naming.directory.SearchControls

Determines whether objects will be returned as part of the result.

[getReturnType\(\)](#) - Method in class java.lang.reflect.[Method](#)
Returns a Class object that represents the formal return type of the method represented by this Method object.

[getRevocationDate\(\)](#) - Method in class java.security.cert.X509CRL[Entry](#)
Gets the revocation date from this X509CRL[Entry](#), the *revocationDate*.

[getRevokedCertificate\(BigInteger\)](#) - Method in class java.security.cert.X509CRL
Gets the CRL entry, if any, with the given certificate serialNumber.

[getRevokedCertificates\(\)](#) - Method in class java.security.cert.X509CRL
Gets all the entries from this CRL.

[getRGB\(\)](#) - Method in class java.awt.[Color](#)
Returns the RGB value representing the color in the default sRGB [ColorModel](#).

[getRGB\(\)](#) - Method in class java.awt.[SystemColor](#)
Gets the "current" RGB value representing the symbolic color.

[getRGB\(int\)](#) - Method in class java.awt.image.[ColorModel](#)
Returns the color/alpha components of the pixel in the default RGB color model format.

[getRGB\(int\)](#) - Method in class java.awt.image.[ComponentColorModel](#)
Returns the color/alpha components of the pixel in the default RGB color model format.

[getRGB\(int\)](#) - Method in class java.awt.image.[DirectColorModel](#)
Returns the color/alpha components of the pixel in the default RGB color model format.

[getRGB\(int\)](#) - Method in class java.awt.image.[IndexColorModel](#)
Returns the color/alpha components of the pixel in the default RGB color model format.

[getRGB\(int, int\)](#) - Method in class java.awt.image.[BufferedImage](#)
Returns an integer pixel in the default RGB color model (TYPE_INT_ARGB) and default sRGB colorspace.

[getRGB\(int, int, int, int, int, int\[\], int, int\)](#) - Method in class java.awt.image.[BufferedImage](#)
Returns an array of integer pixels in the default RGB color model (TYPE_INT_ARGB) and default sRGB color space, from a portion of the image data.

[getRGB\(Object\)](#) - Method in class java.awt.image.[ColorModel](#)
Returns the color/alpha components for the specified pixel in the default RGB color model format.

[getRGB\(Object\)](#) - Method in class java.awt.image.[ComponentColorModel](#)
Returns the color/alpha components for the specified pixel in the default RGB color model format.

[getRGB\(Object\)](#) - Method in class java.awt.image.[DirectColorModel](#)
Returns the color/alpha components for the specified pixel in the default RGB color model format.

[getRGBColorComponents\(float\[\]\)](#) - Method in class java.awt.[Color](#)
Returns a float array containing only the color components of the Color, in the default sRGB color space.

[getRGBComponents\(float\[\]\)](#) - Method in class java.awt.[Color](#)
Returns a float array containing the color and alpha components of the Color, as represented in the default sRGB color space.

[getRGBdefault\(\)](#) - Static method in class java.awt.image.[ColorModel](#)
Returns a [DirectColorModel](#) that describes the default format for integer RGB values used in many of the methods in the AWT image interfaces for the convenience of the programmer.

[getRGBs\(int\[\]\)](#) - Method in class java.awt.image.[IndexColorModel](#)
Converts data for each index from the color and alpha component arrays to an int in the default RGB [ColorModel](#) format and copies the resulting 32-bit ARGB values into the specified array.

[getRightChildIndent\(\)](#) - Method in class javax.swing.plaf.basic.[BasicTreeUI](#)

[getRightComponent\(\)](#) - Method in class javax.swing.JSplitPane
Returns the component to the right (or below) the divider.

[getRightIndent\(AttributeSet\)](#) - Static method in class javax.swing.text.[StyleConstants](#)
Gets the right indent setting.

[getRightInset\(\)](#) - Method in class javax.swing.text.[CompositeView](#)
Gets the right inset.

[getRightInset\(\)](#) - Method in class [javax.swing.text.AsyncBoxView](#)
Get the right part of the margin around the view.

[getRMIRepositoryID\(Class\)](#) - Method in interface [javax.rmi.CORBA.ValueHandler](#)
Returns the CORBA RepositoryId for the given Java class.

[getRolloverIcon\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the rollover icon for the button.

[getRolloverSelectedIcon\(\)](#) - Method in class [javax.swing.AbstractButton](#)
Returns the rollover selection icon for the button.

[getRoot\(\)](#) - Method in class [javax.swing.tree.DefaultMutableTreeNode](#)
Returns the root of the tree that contains this node.

[getRoot\(\)](#) - Method in interface [javax.swing.tree.TreeModel](#)
Returns the root of the tree.

[getRoot\(\)](#) - Method in class [javax.swing.tree.DefaultTreeModel](#)
Returns the root of the tree.

[getRoot\(Component\)](#) - Static method in class [javax.swing.SwingUtilities](#)
Returns the root component for the current component tree.

[getRootCause\(\)](#) - Method in class [javax.naming.NamingException](#)
Retrieves the root cause of this NamingException, if any.

[getRootElement\(\)](#) - Method in class [javax.swing.text.DefaultStyledDocument.ElementBuffer](#)
Gets the root element.

[getRootElements\(\)](#) - Method in interface [javax.swing.text.Document](#)
Returns all of the root elements that are defined.

[getRootElements\(\)](#) - Method in class [javax.swing.text.AbstractDocument](#)
Gets all root elements defined.

[getRootFrame\(\)](#) - Static method in class [javax.swing.JOptionPane](#)
Returns the Frame to use for the class methods in which a frame is not provided.

[getRootPane\(\)](#) - Method in class [javax.swing.JComponent](#)
Returns the JRootPane ancestor for a component

[getRootPane\(\)](#) - Method in class [javax.swing.JWindow](#)
Returns the rootPane object for this window.

[getRootPane\(\)](#) - Method in class [javax.swing.JApplet](#)
Returns the rootPane object for this applet.

[getRootPane\(\)](#) - Method in class [javax.swing.JInternalFrame](#)
Returns the rootPane object for this frame.

[getRootPane\(\)](#) - Method in class [javax.swing.JFrame](#)
Returns the rootPane object for this frame.

[getRootPane\(\)](#) - Method in interface [javax.swing.RootPaneContainer](#)
Return this component's single JRootPane child.

[getRootPane\(\)](#) - Method in class [javax.swing.JDialog](#)
Returns the rootPane object for this dialog.

[getRootPane\(Component\)](#) - Static method in class [javax.swing.SwingUtilities](#)
If c is a JRootPane descendant return its JRootPane ancestor.

[getRoots\(\)](#) - Method in class [javax.swing.filechooser.FileSystemView](#)
Returns all root partitions on this system.

[getRootView\(JTextComponent\)](#) - Method in class [javax.swing.plaf.TextUI](#)
Fetches a View with the allocation of the associated text component (i.e.

[getRootView\(JTextComponent\)](#) - Method in class [javax.swing.plaf.basic.BasicTextUI](#)
Fetches a View with the allocation of the associated text component (i.e.

[getRootView\(JTextComponent\)](#) - Method in class [javax.swing.plaf.multi.MultiTextUI](#)
Call getRootView on each UI handled by this MultiUI.

[getRotateInstance\(double\)](#) - Static method in class [java.awt.geom.AffineTransform](#)
Returns a transform representing a rotation transformation.

[getRotateInstance\(double, double, double\)](#) - Static method in class [java.awt.geom.AffineTransform](#)
Returns a transform that rotates coordinates around an anchor point.

[getRoundedCorners\(\)](#) - Method in class [javax.swing.border.LineBorder](#)
Returns whether this border will be drawn with rounded corners.

[getRow\(\)](#) - Method in interface [java.sql.ResultSet](#)

Retrieves the current row number.

[getRowBounds\(int\)](#) - Method in class [javax.swing.JTree](#)
Returns the Rectangle that the node at the specified row is drawn in.

[getRowCount\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the number of rows that are currently being displayed.

[getRowCount\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the number of rows in this table's model.

[getRowCount\(\)](#) - Method in class [javax.swing.table.DefaultTableModel](#)
Returns the number of rows in this data table.

[getRowCount\(\)](#) - Method in interface [javax.swing.table.TableModel](#)
Returns the number of rows in the model.

[getRowCount\(\)](#) - Method in class [javax.swing.text.TableView.TableCell](#)
Deprecated. Gets the number of rows this cell spans (that is, the grid height).

[getRowCount\(\)](#) - Method in class [javax.swing.tree.AbstractLayoutCache](#)
Number of rows being displayed.

[getRowCount\(\)](#) - Method in class [javax.swing.tree.VariableHeightLayoutCache](#)
Returns the number of visible rows.

[getRowCount\(\)](#) - Method in class [javax.swing.tree.FixedHeightLayoutCache](#)
Returns the number of visible rows.

[getRowCount\(JTree\)](#) - Method in class [javax.swing.plaf.TreeUI](#)
Returns the number of rows that are being displayed.

[getRowCount\(JTree\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)
Returns the number of rows that are being displayed.

[getRowCount\(JTree\)](#) - Method in class [javax.swing.plaf.multi.MultiTreeUI](#)
Call [getRowCount](#) on each UI handled by this MultiUI.

[getRowEnd\(JTextComponent, int\)](#) - Static method in class [javax.swing.text.Utilities](#)
Determines the ending row model position of the row that contains the specified model position.

[getRowForLocation\(int, int\)](#) - Method in class [javax.swing.JTree](#)
Returns the row for the specified location.

[getRowForPath\(JTree, TreePath\)](#) - Method in class [javax.swing.plaf.TreeUI](#)
Returns the row that the last item identified in path is visible at.

[getRowForPath\(JTree, TreePath\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)
Returns the row that the last item identified in path is visible at.

[getRowForPath\(JTree, TreePath\)](#) - Method in class [javax.swing.plaf.multi.MultiTreeUI](#)
Call [getRowForPath](#) on each UI handled by this MultiUI.

[getRowForPath\(TreePath\)](#) - Method in class [javax.swing.JTree](#)
Returns the row that displays the node identified by the specified path.

[getRowForPath\(TreePath\)](#) - Method in class [javax.swing.tree.AbstractLayoutCache](#)
Returns the row that the last item identified in path is visible at.

[getRowForPath\(TreePath\)](#) - Method in class [javax.swing.tree.VariableHeightLayoutCache](#)
Returns the row that the last item identified in path is visible at.

[getRowForPath\(TreePath\)](#) - Method in class [javax.swing.tree.FixedHeightLayoutCache](#)
Returns the row that the last item identified in path is visible at.

[getRowHeader\(\)](#) - Method in class [javax.swing.ScrollPaneLayout](#)
Returns the JViewport object that is the row header.

[getRowHeader\(\)](#) - Method in class [javax.swing.JScrollPane](#)
Returns the row header.

[getRowHeight\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the height of each row.

[getRowHeight\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the height of a table row, in pixels.

[getRowHeight\(\)](#) - Method in class [javax.swing.JTextArea](#)
Defines the meaning of the height of a row.

[getRowHeight\(\)](#) - Method in class [javax.swing.tree.AbstractLayoutCache](#)
Returns the height of each row.

[getRowHeight\(\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI](#)

[getHeight\(int\)](#) - Method in class [javax.swing.JTable](#)
Returns the height, in pixels, of the cells in row.

[getHeight\(int\)](#) - Method in class [javax.swing.plaf.basic.BasicListUI](#)
Returns the height of the specified row based on the current layout.

[getRowMapper\(\)](#) - Method in class [javax.swing.tree.DefaultTreeSelectionModel](#)
Returns the RowMapper instance that is able to map a TreePath to a row.

[getRowMapper\(\)](#) - Method in interface [javax.swing.tree.TreeSelectionModel](#)
Returns the RowMapper instance that is able to map a TreePath to a row.

[getRowMargin\(\)](#) - Method in class [javax.swing.JTable](#)
Gets the amount of empty space, in pixels, between cells.

[getRows\(\)](#) - Method in class [java.awt.GridLayout](#)
Gets the number of rows in this layout.

[getRows\(\)](#) - Method in class [java.awt.List](#)
Get the number of visible lines in this list.

[getRows\(\)](#) - Method in class [java.awt.TextArea](#)
Gets the number of rows in the text area.

[getRows\(\)](#) - Method in class [javax.swing.JTextArea](#)
Returns the number of rows in the TextArea.

[getRowSelectionAllowed\(\)](#) - Method in class [javax.swing.JTable](#)
Returns true if rows can be selected.

[getRowsForPaths\(TreePath\[\]\)](#) - Method in class [javax.swing.tree.AbstractLayoutCache](#)
Returns the rows that the TreePath instances in path are being displayed at.

[getRowsForPaths\(TreePath\[\]\)](#) - Method in interface [javax.swing.tree.RowMapper](#)
Returns the rows that the TreePath instances in path are being displayed at.

[getRowStart\(JTextComponent, int\)](#) - Static method in class [javax.swing.text.Utilities](#)
Determines the starting row model position of the row that contains the specified model position.

[getRowX\(int, int\)](#) - Method in class [javax.swing.plaf.basic.BasicTreeUI.NodeDimensionsHandler](#)

[getRSB\(\)](#) - Method in class [java.awt.font.GlyphMetrics](#)
Returns the right (bottom) side bearing of the glyph.

[getRule\(\)](#) - Method in class [java.awt.AlphaComposite](#)
Returns the compositing rule of this AlphaComposite.

[getRule\(HTML.Tag, Element\)](#) - Method in class [javax.swing.text.html.StyleSheet](#)
Fetches the style to use to render the given type of HTML tag.

[getRule\(String\)](#) - Method in class [javax.swing.text.html.StyleSheet](#)
Fetches the rule that best matches the selector given in string form.

[getRules\(\)](#) - Method in class [java.text.RuleBasedCollator](#)
Gets the table-based rules for the collation object.

[getRunForTab\(int, int\)](#) - Method in class [javax.swing.plaf.basic.BasicTabbedPaneUI](#)

[getRunLimit\(\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)
Returns the index of the first character following the run with respect to all attributes containing the current character.

[getRunLimit\(AttributedCharacterIterator.Attribute\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)
Returns the index of the first character following the run with respect to the given attribute containing the current character.

[getRunLimit\(Set\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)
Returns the index of the first character following the run with respect to the given attributes containing the current character.

[getRunStart\(\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)
Returns the index of the first character of the run with respect to all attributes containing the current character.

[getRunStart\(AttributedCharacterIterator.Attribute\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)

Returns the index of the first character of the run with respect to the given attribute containing the current character.

[getRunStart\(Set\)](#) - Method in interface [java.text.AttributedCharacterIterator](#)
Returns the index of the first character of the run with respect to the given attributes containing the current character.

[getRuntime\(\)](#) - Static method in class [java.lang.Runtime](#)
Returns the runtime object associated with the current Java application.

[getRunTimeCodeBase\(\)](#) - Method in interface [javax.rmi.CORBA.ValueHandler](#)
Returns the CodeBase for this ValueHandler.

[getSample\(int, int, int\)](#) - Method in class [java.awt.image.Raster](#)
Returns the sample in a specified band for the pixel located at (x,y) as an int.

[getSample\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the sample in a specified band for the pixel located at (x,y) as an int.

[getSample\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns as int the sample in a specified band for the pixel located at (x,y).

[getSample\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.BandedSampleModel](#)
Returns as int the sample in a specified band for the pixel located at (x,y).

[getSample\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.MultiPixelPackedSampleModel](#)
Returns as int the sample in a specified band for the pixel located at (x, y).

[getSample\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.SinglePixelPackedSampleModel](#)
Returns as int the sample in a specified band for the pixel located at (x,y).

[getSampleDouble\(int, int, int\)](#) - Method in class [java.awt.image.Raster](#)
Returns the sample in a specified band for a pixel located at (x,y) as a double.

[getSampleDouble\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the sample in a specified band for a pixel located at (x,y) as a double.

[getSampleDouble\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the sample in a specified band for a pixel located at (x,y) as a double.

[getSampleDouble\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.BandedSampleModel](#)
Returns the sample in a specified band for a pixel located at (x,y) as a double.

[getSampleFloat\(int, int, int\)](#) - Method in class [java.awt.image.Raster](#)
Returns the sample in a specified band for the pixel located at (x,y) as a float.

[getSampleFloat\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the sample in a specified band for the pixel located at (x,y) as a float.

[getSampleFloat\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the sample in a specified band for the pixel located at (x,y) as a float.

[getSampleFloat\(int, int, int, DataBuffer\)](#) - Method in class [java.awt.image.BandedSampleModel](#)
Returns the sample in a specified band for the pixel located at (x,y) as a float.

[getSampleModel\(\)](#) - Method in interface [java.awt.image.RenderedImage](#)
Returns the SampleModel associated with this image.

[getSampleModel\(\)](#) - Method in class [java.awt.image.BufferedImage](#)
Returns the SampleModel associated with this BufferedImage.

[getSampleModel\(\)](#) - Method in class [java.awt.image.Raster](#)
Returns the SampleModel that describes the layout of the image data.

[getSampleModelTranslateX\(\)](#) - Method in class [java.awt.image.Raster](#)
Returns the X translation from the coordinate system of the SampleModel to that of the Raster.

[getSampleModelTranslateY\(\)](#) - Method in class [java.awt.image.Raster](#)
Returns the Y translation from the coordinate system of the SampleModel to that of the Raster.

[getSampleRate\(\)](#) - Method in class [javax.sound.sampled.AudioFormat](#)
Obtains the sample rate.

[getSamples\(int, int, int, int, int, double\[\]\)](#) - Method in class [java.awt.image.Raster](#)
Returns the samples for a specified band for a specified rectangle of pixels in a double array, one sample per array element.

[getSamples\(int, int, int, int, int, double\[\], DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the samples for a specified band for a specified rectangle of pixels in a double array, one sample per array element.

[getSamples\(int, int, int, int, int, float\[\]\)](#) - Method in class [java.awt.image.Raster](#)

Returns the samples for a specified band for the specified rectangle of pixels in a float array, one sample per array element.

[getSamples\(int, int, int, int, int, float\[\], DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the samples for a specified band for the specified rectangle of pixels in a float array, one sample per array element.

[getSamples\(int, int, int, int, int, int\[\]\)](#) - Method in class [java.awt.image.Raster](#)
Returns the samples for a specified band for the specified rectangle of pixels in an int array, one sample per array element.

[getSamples\(int, int, int, int, int, int\[\], DataBuffer\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the samples for a specified band for the specified rectangle of pixels in an int array, one sample per array element.

[getSamples\(int, int, int, int, int, int\[\], DataBuffer\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the samples in a specified band for the specified rectangle of pixels in an int array, one sample per data array element.

[getSamples\(int, int, int, int, int, int\[\], DataBuffer\)](#) - Method in class [java.awt.image.BandedSampleModel](#)
Returns the samples in a specified band for the specified rectangle of pixels in an int array, one sample per data array element.

[getSamples\(int, int, int, int, int, int\[\], DataBuffer\)](#) - Method in class [java.awt.image.SinglePixelPackedSampleModel](#)
Returns the samples for a specified band for the specified rectangle of pixels in an int array, one sample per array element.

[getSampleSize\(\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the size in bits of samples for all bands.

[getSampleSize\(\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the number of bits per sample for all bands.

[getSampleSize\(\)](#) - Method in class [java.awt.image.MultiPixelPackedSampleModel](#)
Returns the number of bits per sample for all bands.

[getSampleSize\(\)](#) - Method in class [java.awt.image.SinglePixelPackedSampleModel](#)
Returns the number of bits per sample for all bands.

[getSampleSize\(int\)](#) - Method in class [java.awt.image.SampleModel](#)
Returns the size in bits of samples for the specified band.

[getSampleSize\(int\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the number of bits per sample for the specified band.

[getSampleSize\(int\)](#) - Method in class [java.awt.image.MultiPixelPackedSampleModel](#)
Returns the number of bits per sample for the specified band.

[getSampleSize\(int\)](#) - Method in class [java.awt.image.SinglePixelPackedSampleModel](#)
Returns the number of bits per sample for the specified band.

[getSampleSizeInBits\(\)](#) - Method in class [javax.sound.sampled.AudioFormat](#)
Obtains the size of a sample.

[getScale\(int\)](#) - Method in interface [java.sql.ResultSetMetaData](#)
Gets the designated column's number of digits to right of the decimal point.

[getScaledInstance\(int, int, int\)](#) - Method in class [java.awt.Image](#)
Creates a scaled version of this image.

[getScaleFactors\(float\[\]\)](#) - Method in class [java.awt.image.RescaleOp](#)
Returns the scale factors in the given array.

[getScaleInstance\(double, double\)](#) - Static method in class [java.awt.geom.AffineTransform](#)
Returns a transform representing a scaling transformation.

[getScaleX\(\)](#) - Method in class [java.awt.geom.AffineTransform](#)
Returns the X coordinate scaling element (m00) of the 3x3 affine transformation matrix.

[getScaleY\(\)](#) - Method in class [java.awt.geom.AffineTransform](#)
Returns the Y coordinate scaling element (m11) of the 3x3 affine transformation matrix.

[getScanlineStride\(\)](#) - Method in class [java.awt.image.ComponentSampleModel](#)
Returns the scanline stride of this ComponentSampleModel.

[getScanlineStride\(\)](#) - Method in class [java.awt.image.MultiPixelPackedSampleModel](#)

Returns the scanline stride.

[getScanlineStride\(\)](#) - Method in class `java.awt.image.SinglePixelPackedSampleModel`
Returns the scanline stride of this `SinglePixelPackedSampleModel`.

[getSchema\(Name\)](#) - Method in interface `javax.naming.directory.DirContext`
Retrieves the schema associated with the named object.

[getSchema\(Name\)](#) - Method in class `javax.naming.directory.InitialDirContext`

[getSchema\(String\)](#) - Method in interface `javax.naming.directory.DirContext`
Retrieves the schema associated with the named object.

[getSchema\(String\)](#) - Method in class `javax.naming.directory.InitialDirContext`

[getSchemaClassDefinition\(Name\)](#) - Method in interface `javax.naming.directory.DirContext`
Retrieves a context containing the schema objects of the named object's class definitions.

[getSchemaClassDefinition\(Name\)](#) - Method in class `javax.naming.directory.InitialDirContext`

[getSchemaClassDefinition\(String\)](#) - Method in interface `javax.naming.directory.DirContext`
Retrieves a context containing the schema objects of the named object's class definitions.

[getSchemaClassDefinition\(String\)](#) - Method in class `javax.naming.directory.InitialDirContext`

[getSchemaName\(int\)](#) - Method in interface `java.sql.ResultSetMetaData`
Get the designated column's table's schema.

[getSchemas\(\)](#) - Method in interface `java.sql.DatabaseMetaData`
Gets the schema names available in this database.

[getSchemaTerm\(\)](#) - Method in interface `java.sql.DatabaseMetaData`
What's the database vendor's preferred term for "schema"?

[getScope\(\)](#) - Method in class `java.security.Identity`
Deprecated. Returns this identity's scope.

[getScreenDevices\(\)](#) - Method in class `java.awt.GraphicsEnvironment`
Returns an array of all of the screen `GraphicsDevice` objects.

[getScreenResolution\(\)](#) - Method in class `java.awt.Toolkit`
Returns the screen resolution in dots-per-inch.

[getScreenSize\(\)](#) - Method in class `java.awt.Toolkit`
Gets the size of the screen.

[getScrollableBlockIncrement\(Rectangle, int, int\)](#) - Method in class `javax.swing.JList`
Returns the block increment amount.

[getScrollableBlockIncrement\(Rectangle, int, int\)](#) - Method in class `javax.swing.JTree`
Returns the amount for a block increment, which is the height or width of `visibleRect`, based on orientation.

[getScrollableBlockIncrement\(Rectangle, int, int\)](#) - Method in interface `javax.swing.Scrollable`
Components that display logical rows or columns should compute the scroll increment that will completely expose one block of rows or columns, depending on the value of orientation.

[getScrollableBlockIncrement\(Rectangle, int, int\)](#) - Method in class `javax.swing.JTable`
Returns `visibleRect.height` or `visibleRect.width`, depending on this table's orientation.

[getScrollableBlockIncrement\(Rectangle, int, int\)](#) - Method in class `javax.swing.text.JTextComponent`
Components that display logical rows or columns should compute the scroll increment that will completely expose one block of rows or columns, depending on the value of orientation.

[getScrollableTracksViewportHeight\(\)](#) - Method in class `javax.swing.JEditorPane`
Returns true if a viewport should always force the height of this `Scrollable` to match the height of the viewport.

[getScrollableTracksViewportHeight\(\)](#) - Method in class `javax.swing.JList`
Returns true if this `JList` is displayed in a `JViewport` and the viewport is taller than `JList`'s preferred height; otherwise returns false.

[getScrollableTracksViewportHeight\(\)](#) - Method in class `javax.swing.JTree`
Returns false to indicate that the height of the viewport does not determine the height of the table, unless the preferred height of the tree is smaller than the viewport's height.

[getScrollableTracksViewportHeight\(\)](#) - Method in interface `javax.swing.Scrollable`
Return true if a viewport should always force the height of this `Scrollable` to match the

height of the viewport.

[getScrollableTracksViewportHeight\(\)](#) - Method in class javax.swing.JTable

Returns false to indicate that the height of the viewport does not determine the height of the table.

[getScrollableTracksViewportHeight\(\)](#) - Method in class javax.swing.text.JTextComponent

Return true if a viewport should always force the height of this Scrollable to match the height of the viewport.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.JEditorPane

Returns true if a viewport should always force the width of this Scrollable to match the width of the viewport.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.JList

Returns true if this JList is displayed in a JViewport and the viewport is wider than JList's preferred width; otherwise returns false.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.JTree

Returns false to indicate that the width of the viewport does not determine the width of the table, unless the preferred width of the tree is smaller than the viewports width.

[getScrollableTracksViewportWidth\(\)](#) - Method in interface javax.swing.Scrollable

Return true if a viewport should always force the width of this Scrollable to match the width of the viewport.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.JTable

Returns false to indicate that the width of the viewport does not determine the width of the table.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.JTextArea

Returns true if a viewport should always force the width of this Scrollable to match the width of the viewport.

[getScrollableTracksViewportWidth\(\)](#) - Method in class javax.swing.text.JTextComponent

Return true if a viewport should always force the width of this Scrollable to match the width of the viewport.

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in class javax.swing.JList

Returns the distance to scroll to expose the next or previous row (for vertical scrolling) or character (for horizontal scrolling).

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in class javax.swing.JTree

Returns the amount to increment when scrolling.

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in interface javax.swing.Scrollable

Components that display logical rows or columns should compute the scroll increment that will completely expose one new row or column, depending on the value of orientation.

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in class javax.swing.JTable

Returns the scroll increment (in pixels) that completely exposes one new row or column (depending on the orientation).

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in class javax.swing.JTextArea

Components that display logical rows or columns should compute the scroll increment that will completely expose one new row or column, depending on the value of orientation.

[getScrollableUnitIncrement\(Rectangle, int, int\)](#) - Method in class javax.swing.text.JTextComponent

Components that display logical rows or columns should compute the scroll increment that will completely expose one new row or column, depending on the value of orientation.

[getScrollbarDisplayPolicy\(\)](#) - Method in class java.awt.ScrollPane

Returns the display policy for the scrollbars.

[getScrollbarVisibility\(\)](#) - Method in class java.awt.TextArea

Gets an enumerated value that indicates which scroll bars the text area uses.

[getScrollMode\(\)](#) - Method in class javax.swing.JViewport

Returns the current scrolling mode.

[getScrollOffset\(\)](#) - Method in class javax.swing.JTextField

Gets the scroll offset.

[getScrollPane\(\)](#) - Method in class javax.swing.plaf.basic.BasicTreeUI.ComponentHandler

Returns the JScrollPane housing the JTree, or null if one isn't found.

[getScrollPosition\(\)](#) - Method in class java.awt.ScrollPane

Returns the current x,y position within the child which is displayed at the 0,0 location of

the scrolled panel's view port.

[getScrollsOnExpand\(\)](#) - Method in class `javax.swing.JTree`
Returns true if the tree scrolls to show previously hidden children.

[getSearchScope\(\)](#) - Method in class `javax.naming.directory.SearchControls`
Retrieves the search scope of these `SearchControls`.

[getSearchStringEscape\(\)](#) - Method in interface `java.sql.DatabaseMetaData`
Gets the string that can be used to escape wildcard characters.

[getSecondary1\(\)](#) - Method in class `javax.swing.plaf.metal.MetalTheme`

[getSecondary1\(\)](#) - Method in class `javax.swing.plaf.metal.DefaultMetalTheme`

[getSecondary2\(\)](#) - Method in class `javax.swing.plaf.metal.MetalTheme`

[getSecondary2\(\)](#) - Method in class `javax.swing.plaf.metal.DefaultMetalTheme`

[getSecondary3\(\)](#) - Method in class `javax.swing.plaf.metal.MetalTheme`

[getSecondary3\(\)](#) - Method in class `javax.swing.plaf.metal.DefaultMetalTheme`

[getSeconds\(\)](#) - Method in class `java.sql.Date`
Deprecated.

[getSeconds\(\)](#) - Method in class `java.util.Date`
Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.SECOND)`.*

[getSecurityContext\(\)](#) - Method in class `java.lang.SecurityManager`
Creates an object that encapsulates the current execution environment.

[getSecurityContext\(ClassLoader\)](#) - Static method in class `java.rmi.server.RMIClassLoader`
Deprecated. *no replacement. As of the Java 2 platform v1.2, RMI no longer uses this method to obtain a class loader's security context.*

[getSecurityContext\(ClassLoader\)](#) - Method in interface `java.rmi.server.LoaderHandler`
Deprecated. *no replacement*

[getSecurityManager\(\)](#) - Static method in class `java.lang.System`
Gets the system security interface.

[getSeed\(int\)](#) - Static method in class `java.security.SecureRandom`
Returns the given number of seed bytes, computed using the seed generation algorithm that this class uses to seed itself.

[getSelectColor\(\)](#) - Method in class `javax.swing.plaf.metal.MetalToggleButtonUI`

[getSelectColor\(\)](#) - Method in class `javax.swing.plaf.metal.MetalRadioButtonUI`

[getSelectColor\(\)](#) - Method in class `javax.swing.plaf.metal.MetalButtonUI`

[getSelectedAccessibleColumns\(\)](#) - Method in interface `javax.accessibility.AccessibleTable`
Returns the selected columns in a table.

[getSelectedAccessibleColumns\(\)](#) - Method in class `javax.swing.JTable.AccessibleJTable`
Returns the selected columns in a table.

[getSelectedAccessibleRows\(\)](#) - Method in interface `javax.accessibility.AccessibleTable`
Returns the selected rows in a table.

[getSelectedAccessibleRows\(\)](#) - Method in class `javax.swing.JTable.AccessibleJTable`
Returns the selected rows in a table.

[getSelectedCheckbox\(\)](#) - Method in class `java.awt.CheckboxGroup`
Gets the current choice from this check box group.

[getSelectedColor\(\)](#) - Method in class `javax.swing.colorchooser.DefaultColorSelectionModel`

[getSelectedColor\(\)](#) - Method in interface `javax.swing.colorchooser.ColorSelectionModel`

[getSelectedColumn\(\)](#) - Method in class `javax.swing.JTable`
Returns the index of the first selected column, -1 if no column is selected.

getSelectedColumnCount() - Method in class javax.swing.JTable
Returns the number of selected columns.

getSelectedColumnCount() - Method in class javax.swing.table.DefaultTableColumnModel
Returns the number of columns selected.

getSelectedColumnCount() - Method in interface javax.swing.table.TableColumnModel
Returns the number of selected columns.

getSelectedColumns() - Method in class javax.swing.JTable
Returns the indices of all selected columns.

getSelectedColumns() - Method in class javax.swing.table.DefaultTableColumnModel
Returns an array of selected columns.

getSelectedColumns() - Method in interface javax.swing.table.TableColumnModel
Returns an array of indices of all selected columns.

getSelectedComponent() - Method in class javax.swing.JTabbedPane
Returns the currently selected component for this tabbedpane.

getSelectedFile() - Method in class javax.swing.JFileChooser
Returns the selected file.

getSelectedFiles() - Method in class javax.swing.JFileChooser
Returns a list of selected files if the file chooser is set to allow multiple selection.

getSelectedFrame() - Method in class javax.swing.JDesktopPane
return the currently active JInternalFrame in this JDesktopPane, or null if no JInternalFrame is currently active.

getSelectedIcon() - Method in class javax.swing.AbstractButton
Returns the selected icon for the button.

getSelectedIndex() - Method in class java.awt.List
Gets the index of the selected item on the list,

getSelectedIndex() - Method in class java.awt.Choice
Returns the index of the currently selected item.

getSelectedIndex() - Method in class javax.swing.DefaultSingleSelectionModel

getSelectedIndex() - Method in class javax.swing.JTabbedPane
Returns the currently selected index for this tabbedpane.

getSelectedIndex() - Method in interface javax.swing.SingleSelectionModel
Returns the model's selection.

getSelectedIndex() - Method in class javax.swing.JComboBox
Returns the first item in the list that matches the given item.

getSelectedIndex() - Method in class javax.swing.JList
Returns the first selected index; returns -1 if there is no selected item.

getSelectedIndexes() - Method in class java.awt.List
Gets the selected indexes on the list.

getSelectedIndices() - Method in class javax.swing.JList
Returns an array of all of the selected indices in increasing order.

getSelectedItem() - Method in class java.awt.List
Get the selected item on this scrolling list.

getSelectedItem() - Method in class java.awt.Choice
Gets a representation of the current choice as a string.

getSelectedItem() - Method in class javax.swing.DefaultComboBoxModel

getSelectedItem() - Method in class javax.swing.JComboBox
Returns the currently selected item.

getSelectedItem() - Method in interface javax.swing.ComboBoxModel
Return the selected item

getSelectedItem() - Method in class javax.swing.plaf.metal.MetalFileChooserUI.DirectoryComboBoxModel

getSelectedItem() - Method in class javax.swing.plaf.metal.MetalFileChooserUI.FilterComboBoxModel

getSelectedItems() - Method in class java.awt.List
Get the selected items on this scrolling list.

getSelectedObjects() - Method in class java.awt.Checkbox
Returns an array (length 1) containing the checkbox label or null if the checkbox is not selected.

getSelectedObjects() - Method in class java.awt.List
Returns the selected items on the list in an array of Objects.

getSelectedObjects() - Method in class java.awt.Choice
Returns an array (length 1) containing the currently selected item.

getSelectedObjects() - Method in interface java.awt.ItemSelectable
Returns the selected items or null if no items are selected.

getSelectedObjects() - Method in class java.awt.CheckboxMenuItem
Returns the array (length 1) containing the checkbox menu item label or null if the checkbox is not selected.

getSelectedObjects() - Method in class javax.swing.AbstractButton
Returns an array (length 1) containing the label or null if the button is not selected.

getSelectedObjects() - Method in class javax.swing.JCheckBoxMenuItem
Returns an array (length 1) containing the check box menu item label or null if the check box is not selected.

getSelectedObjects() - Method in class javax.swing.JComboBox
Returns an array containing the selected item.

getSelectedObjects() - Method in class javax.swing.DefaultButtonModel
Overriden to return null

getSelectedPath() - Method in class javax.swing.MenuSelectionManager
Returns the path to the currently selected menu item

getSelectedRow() - Method in class javax.swing.JTable
Returns the index of the first selected row, -1 if no row is selected.

getSelectedRowCount() - Method in class javax.swing.JTable
Returns the number of selected rows.

getSelectedRows() - Method in class javax.swing.JTable
Returns the indices of all selected rows.

getSelectedTabPadInsets(int) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getSelectedText() - Method in class java.awt.TextComponent
Gets the selected text from the text that is presented by this text component.

getSelectedText() - Method in class java.awt.TextComponent.AccessibleAWTTextComponent
Returns the portion of the text that is selected.

getSelectedText() - Method in interface javax.accessibility.AccessibleText
Returns the portion of the text that is selected.

getSelectedText() - Method in class javax.swing.AbstractButton.AccessibleAbstractButton
Returns the portion of the text that is selected.

getSelectedText() - Method in class javax.swing.JLabel.AccessibleJLabel
Returns the portion of the text that is selected.

getSelectedText() - Method in class javax.swing.text.JTextComponent
Returns the selected text contained in this TextComponent.

getSelectedText() - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent
Returns the portion of the text that is selected.

getSelectedText(AttributedCharacterIterator.Attribute[]) - Method in interface java.awt.im.InputMethodRequests
Gets the currently selected text from the text editing component.

getSelectedTextColor() - Method in class javax.swing.text.JTextComponent
Fetches the current color used to render the selected text.

getSelectedValue() - Method in class javax.swing.JList
Returns the first selected value, or null if the selection is empty.

getSelectedValues() - Method in class javax.swing.JList
Returns an array of the values for the selected cells.

getSelection() - Method in class javax.swing.ButtonGroup
Return the selected button model.

getSelectionBackground() - Method in class javax.swing.JList

Returns the background color for selected cells.

[getSelectionBackground\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the background color for selected cells.

[getSelectionBackground\(\)](#) - Method in class [javax.swing.plaf.basic.BasicProgressBarUI](#)
The "selectionBackground" is the color of the text when it is drawn over an unfilled area of the progress bar.

[getSelectionColor\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)
Fetches the current color used to render the selection.

[getSelectionCount\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the number of nodes selected.

[getSelectionCount\(\)](#) - Method in class [javax.swing.tree.DefaultTreeSelectionModel](#)
Returns the number of paths that are selected.

[getSelectionCount\(\)](#) - Method in interface [javax.swing.tree.TreeSelectionModel](#)
Returns the number of paths that are selected.

[getSelectionEnd\(\)](#) - Method in class [java.awt.TextComponent](#)
Gets the end position of the selected text in this text component.

[getSelectionEnd\(\)](#) - Method in class [java.awt.TextComponent.AccessibleAWTTextComponent](#)
Returns the end offset within the selected text.

[getSelectionEnd\(\)](#) - Method in interface [javax.accessibility.AccessibleText](#)
Returns the end offset within the selected text.

[getSelectionEnd\(\)](#) - Method in class [javax.swing.AbstractButton.AccessibleAbstractButton](#)
Returns the end offset within the selected text.

[getSelectionEnd\(\)](#) - Method in class [javax.swing.JLabel.AccessibleJLabel](#)
Returns the end offset within the selected text.

[getSelectionEnd\(\)](#) - Method in class [javax.swing.text.JTextComponent](#)
Returns the selected text's end position.

[getSelectionEnd\(\)](#) - Method in class [javax.swing.text.JTextComponent.AccessibleJTextComponent](#)
Returns the end offset within the selected text.

[getSelectionForeground\(\)](#) - Method in class [javax.swing.JList](#)
Returns the selection foreground color.

[getSelectionForeground\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the foreground color for selected cells.

[getSelectionForeground\(\)](#) - Method in class [javax.swing.plaf.basic.BasicProgressBarUI](#)
The "selectionForeground" is the color of the text when it is drawn over a filled area of the progress bar.

[getSelectionMode\(\)](#) - Method in class [javax.swing.DefaultListSelectionModel](#)
Returns the selection mode.

[getSelectionMode\(\)](#) - Method in class [javax.swing.JList](#)
Returns whether single-item or multiple-item selections are allowed.

[getSelectionMode\(\)](#) - Method in interface [javax.swing.ListSelectionModel](#)
Returns the current selection mode.

[getSelectionMode\(\)](#) - Method in class [javax.swing.tree.DefaultTreeSelectionModel](#)
Returns the selection mode, one of SINGLE_TREE_SELECTION, DISCONTIGUOUS_TREE_SELECTION or CONTIGUOUS_TREE_SELECTION.

[getSelectionMode\(\)](#) - Method in interface [javax.swing.tree.TreeSelectionModel](#)
Returns the current selection mode, one of SINGLE_TREE_SELECTION, CONTIGUOUS_TREE_SELECTION or DISCONTIGUOUS_TREE_SELECTION.

[getSelectionModel\(\)](#) - Method in class [javax.swing.JColorChooser](#)
Returns the data model that handles color selections.

[getSelectionModel\(\)](#) - Method in class [javax.swing.JPopupMenu](#)
Returns the model object that handles single selections.

[getSelectionModel\(\)](#) - Method in class [javax.swing.JList](#)
Returns the value of the current selection model.

[getSelectionModel\(\)](#) - Method in class [javax.swing.JTree](#)
Returns the model for selections.

[getSelectionModel\(\)](#) - Method in class [javax.swing.JTable](#)
Returns the ListSelectionModel that is used to maintain row selection state.

getSelectionModel() - Method in class javax.swing.JMenuBar
Returns the model object that handles single selections.

getSelectionModel() - Method in class javax.swing.table.DefaultTableColumnModel
Returns the ListSelectionModel that is used to maintain column selection state.

getSelectionModel() - Method in interface javax.swing.table.TableColumnModel
Returns the current selection model.

getSelectionModel() - Method in class javax.swing.tree.AbstractLayoutCache
Returns the model used to maintain the selection.

getSelectionModel() - Method in class javax.swing.plaf.basic.BasicTreeUI

getSelectionPainter() - Method in class javax.swing.text.DefaultCaret
Gets the painter for the Highlighter.

getSelectionPath() - Method in class javax.swing.JTree
Returns the path to the first selected node.

getSelectionPath() - Method in class javax.swing.tree.DefaultTreeSelectionModel
Returns the first path in the selection.

getSelectionPath() - Method in interface javax.swing.tree.TreeSelectionModel
Returns the first path in the selection.

getSelectionPaths() - Method in class javax.swing.JTree
Returns the paths of all selected values.

getSelectionPaths() - Method in class javax.swing.tree.DefaultTreeSelectionModel
Returns the paths in the selection.

getSelectionPaths() - Method in interface javax.swing.tree.TreeSelectionModel
Returns the paths in the selection.

getSelectionRows() - Method in class javax.swing.JTree
Returns all of the currently selected rows.

getSelectionRows() - Method in class javax.swing.tree.DefaultTreeSelectionModel
Returns all of the currently selected rows.

getSelectionRows() - Method in interface javax.swing.tree.TreeSelectionModel
Returns all of the currently selected rows.

getSelectionStart() - Method in class java.awt.TextComponent
Gets the start position of the selected text in this text component.

getSelectionStart() - Method in class java.awt.TextComponent.AccessibleAWTTextComponent
Returns the start offset within the selected text.

getSelectionStart() - Method in interface javax.accessibility.AccessibleText
Returns the start offset within the selected text.

getSelectionStart() - Method in class javax.swing.AbstractButton.AccessibleAbstractButton
Returns the start offset within the selected text.

getSelectionStart() - Method in class javax.swing.JLabel.AccessibleJLabel
Returns the start offset within the selected text.

getSelectionStart() - Method in class javax.swing.text.JTextComponent
Returns the selected text's start position.

getSelectionStart() - Method in class javax.swing.text.JTextComponent.AccessibleJTextComponent
Returns the start offset within the selected text.

getSelectionValues() - Method in class javax.swing.JOptionPane
Returns the selection values.

getSendBufferSize() - Method in class java.net.DatagramSocket
Get value of the SO_SNDBUF option for this DatagramSocket, that is the buffer size used by the platform for output on this DatagramSocket.

getSendBufferSize() - Method in class java.net.Socket
Get value of the SO_SNDBUF option for this Socket, that is the buffer size used by the platform for output on this Socket.

getSentenceInstance() - Static method in class java.text.BreakIterator
Create BreakIterator for sentence-breaks using default locale Returns an instance of a BreakIterator implementing sentence breaks.

getSentenceInstance(Locale) - Static method in class java.text.BreakIterator
Create BreakIterator for sentence-breaks using specified locale Returns an instance of a

BreakIterator implementing sentence breaks.

getSeparatorBackground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getSeparatorBackground() - Method in class javax.swing.plaf.metal.MetalTheme

getSeparatorForeground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getSeparatorForeground() - Method in class javax.swing.plaf.metal.MetalTheme

getSeparatorSize() - Method in class javax.swing.JToolBar.Separator
Returns the size of the separator

getSequence() - Method in interface javax.sound.midi.Sequencer
Obtains the sequence on which the Sequencer is currently operating.

getSequence(File) - Static method in class javax.sound.midi.MidiSystem
Obtains a MIDI sequence from the specified File.

getSequence(File) - Method in class javax.sound.midi.spi.MidiFileReader
Obtains a MIDI sequence from the File provided.

getSequence(InputStream) - Static method in class javax.sound.midi.MidiSystem
Obtains a MIDI sequence from the specified input stream.

getSequence(InputStream) - Method in class javax.sound.midi.spi.MidiFileReader
Obtains a MIDI sequence from the input stream provided.

getSequence(URL) - Static method in class javax.sound.midi.MidiSystem
Obtains a MIDI sequence from the specified URL.

getSequence(URL) - Method in class javax.sound.midi.spi.MidiFileReader
Obtains a MIDI sequence from the URL provided.

getSequencer() - Static method in class javax.sound.midi.MidiSystem
Obtains the default sequencer.

getSerialNumber() - Method in class java.security.cert.X509Certificate
Gets the serialNumber value from the certificate.

getSerialNumber() - Method in class java.security.cert.X509CRLEntry
Gets the serial number from this X509CRLEntry, the *userCertificate*.

getSerialVersionUID() - Method in class java.io.ObjectStreamClass
Return the serialVersionUID for this class.

getService(BeanContextChild, Object, Class, Object, BeanContextServiceRevokedListener) - Method in class java.beans.beancontext.BeanContextServicesSupport
obtain a service which may be delegated

getService(BeanContextChild, Object, Class, Object, BeanContextServiceRevokedListener) - Method in interface java.beans.beancontext.BeanContextServices
A BeanContextChild, or any arbitrary object associated with a BeanContextChild, may obtain a reference to a currently registered service from its nesting BeanContextServices via invocation of this method.

getService(BeanContextServices, Object, Class, Object) - Method in class java.beans.beancontext.BeanContextServicesSupport.BCSSProxyServiceProvider

getService(BeanContextServices, Object, Class, Object) - Method in interface java.beans.beancontext.BeanContextServiceProvider
Invoked by BeanContextServices, this method requests an instance of a service from this BeanContextServiceProvider.

getServiceClass() - Method in class java.beans.beancontext.BeanContextServiceAvailableEvent
Gets the service class that is the subject of this notification.

getServiceClass() - Method in class java.beans.beancontext.BeanContextServiceRevokedEvent
Gets the service class that is the subject of this notification

getServiceProvider() - Method in class java.beans.beancontext.BeanContextServicesSupport.BCSSServiceProvider

getServicesBeanInfo() - Method in interface java.beans.beancontext.BeanContextServiceProviderBeanInfo

Gets a BeanInfo array, one for each service class or interface statically available from this ServiceProvider.

getShadowColor() - Method in class javax.swing.border.EtchedBorder
Returns the shadow color of the etched border.

getShadowColor() - Method in class javax.swing.plaf.basic.BasicSliderUI

getShadowColor(Component) - Method in class javax.swing.border.EtchedBorder
Returns the shadow color of the etched border when rendered on the specified component.

getShadowInnerColor() - Method in class javax.swing.border.BevelBorder
Returns the inner shadow color of the bevel border.

getShadowInnerColor(Component) - Method in class javax.swing.border.BevelBorder
Returns the inner shadow color of the bevel border when rendered on the specified component.

getShadowOuterColor() - Method in class javax.swing.border.BevelBorder
Returns the outer shadow color of the bevel border.

getShadowOuterColor(Component) - Method in class javax.swing.border.BevelBorder
Returns the outer shadow color of the bevel border when rendered on the specified component.

getSharedAncestor(DefaultMutableTreeNode) - Method in class javax.swing.tree.DefaultMutableTreeNode
Returns the nearest common ancestor to this node and aNode.

getShearInstance(double, double) - Static method in class java.awt.geom.AffineTransform
Returns a transform representing a shearing transformation.

getShearX() - Method in class java.awt.geom.AffineTransform
Returns the X coordinate shearing element (m01) of the 3x3 affine transformation matrix.

getShearY() - Method in class java.awt.geom.AffineTransform
Returns the Y coordinate shearing element (m10) of the 3x3 affine transformation matrix.

getShift() - Method in class javax.swing.plaf.metal.MetalIconFactory.FolderIcon16

getShift() - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeFolderIcon

getShift() - Method in class javax.swing.plaf.metal.MetalIconFactory.FileIcon16

getShift() - Method in class javax.swing.plaf.metal.MetalIconFactory.TreeLeafIcon

getShort(int) - Method in interface java.sql.CallableStatement
Gets the value of a JDBC SMALLINT parameter as a short in the Java programming language.

getShort(int) - Method in interface java.sql.ResultSet
Gets the value of the designated column in the current row of this ResultSet object as a short in the Java programming language.

getShort(Object) - Method in class java.lang.reflect.Field
Gets the value of a field as a short on the specified object.

getShort(Object, int) - Static method in class java.lang.reflect.Array
Returns the value of the indexed component in the specified array object, as a short.

getShort(String) - Method in interface java.sql.ResultSet
Gets the value of the designated column in the current row of this ResultSet object as a short in the Java programming language.

getShortcut() - Method in class java.awt.MenuItem
Get the MenuShortcut object associated with this menu item,

getShortcutMenuItem(MenuShortcut) - Method in class java.awt.MenuBar
Gets the instance of MenuItem associated with the specified MenuShortcut object, or null if none of the menu items being managed by this menu bar is associated with the specified menu shortcut.

getShortDescription() - Method in class java.beans.FeatureDescriptor
Gets the short description of this feature.

getShortMonths() - Method in class java.text.DateFormatSymbols
Gets short month strings.

getShortParameter(int) - Method in class java.awt.image.renderable.ParameterBlock
A convenience method to return a parameter as a short.

getShortWeekdays() - Method in class java.text.DateFormatSymbols

Gets short weekday strings.

getShowHorizontalLines() - Method in class javax.swing.JTable
Returns true if the table draws horizontal lines between cells, false if it doesn't.

getShowsRootHandles() - Method in class javax.swing.JTree
Returns true if handles for the root nodes are displayed.

getShowsRootHandles() - Method in class javax.swing.plaf.basic.BasicTreeUI

getShowVerticalLines() - Method in class javax.swing.JTable
Returns true if the table draws vertical lines between cells, false if it doesn't.

getSiblingCount() - Method in class javax.swing.tree.DefaultMutableTreeNode
Returns the number of siblings of this node.

getSides() - Method in class java.awt.JobAttributes
Returns how consecutive pages should be imposed upon the sides of the print medium for jobs using these attributes.

getSigAlgName() - Method in class java.security.cert.X509Certificate
Gets the signature algorithm name for the certificate signature algorithm.

getSigAlgName() - Method in class java.security.cert.X509CRL
Gets the signature algorithm name for the CRL signature algorithm.

getSigAlgOID() - Method in class java.security.cert.X509Certificate
Gets the signature algorithm OID string from the certificate.

getSigAlgOID() - Method in class java.security.cert.X509CRL
Gets the signature algorithm OID string from the CRL.

getSigAlgParams() - Method in class java.security.cert.X509Certificate
Gets the DER-encoded signature algorithm parameters from this certificate's signature algorithm.

getSigAlgParams() - Method in class java.security.cert.X509CRL
Gets the DER-encoded signature algorithm parameters from this CRL's signature algorithm.

getSignature() - Method in class java.security.SignedObject
Retrieves the signature on the signed object, in the form of a byte array.

getSignature() - Method in class java.security.cert.X509Certificate
Gets the signature value (the raw signature bits) from the certificate.

getSignature() - Method in class java.security.cert.X509CRL
Gets the signature value (the raw signature bits) from the CRL.

getSigners() - Method in class java.lang.Class
Gets the signers of this class.

getSize() - Method in class java.awt.Component
Returns the size of this component in the form of a Dimension object.

getSize() - Method in class java.awt.Component.AccessibleAWTComponent
Returns the size of this object in the form of a Dimension object.

getSize() - Method in class java.awt.MenuComponent.AccessibleAWTMenuComponent
Returns the size of this object in the form of a Dimension object.

getSize() - Method in class java.awt.Font
Returns the point size of this Font, rounded to an integer.

getSize() - Method in class java.awt.List.AccessibleAWTList.AccessibleAWTListChild
Returns the size of this object in the form of a Dimension object.

getSize() - Method in class java.awt.Dimension
Gets the size of this Dimension object.

getSize() - Method in class java.awt.Rectangle
Gets the size of this Rectangle, represented by the returned Dimension.

getSize() - Method in class java.awt.image.DataBuffer
Returns the size (in array elements) of all banks.

getSize() - Method in class java.util.zip.ZipEntry
Returns the uncompressed size of the entry data, or -1 if not known.

getSize() - Method in interface javax.accessibility.AccessibleComponent
Returns the size of this object in the form of a Dimension object.

getSize() - Method in interface javax.swing.ListModel
Returns the length of the list.

getSize() - Method in class javax.swing.DefaultComboBoxModel

getSize() - Method in class javax.swing.JList.AccessibleJList.AccessibleJListChild

getSize() - Method in class javax.swing.JTree.AccessibleJTree.AccessibleJTreeNode

getSize() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableCell

getSize() - Method in class javax.swing.DefaultListModel
Returns the number of components in this list.

getSize() - Method in class javax.swing.table.JTableHeader.AccessibleJTableHeader.AccessibleJTableHeaderEntry

getSize() - Method in class javax.swing.plaf.basic.BasicDirectoryModel

getSize() - Method in class javax.swing.plaf.metal.MetalFileChooserUI.DirectoryComboBoxModel

getSize() - Method in class javax.swing.plaf.metal.MetalFileChooserUI.FilterComboBoxModel

getSize(Dimension) - Method in class java.awt.Component
Store the width/height of this component into "return value" rv and return rv.

getSize(Dimension) - Method in class javax.swing.JComponent
Stores the width/height of this component into "return value" rv and returns rv.

getSize(int) - Method in class javax.swing.SizeSequence
Returns the size of the specified entry.

getSize2D() - Method in class java.awt.Font
Returns the point size of this Font in float value.

getSizeButtonsToSameWidth() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI
Returns true, basic L&F wants all the buttons to have the same width.

getSizeOfComponent(Component) - Method in class javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager
Returns the width of the passed in component.

getSizes() - Method in class javax.swing.SizeSequence
Returns the size of all entries.

getSizes() - Method in class javax.swing.plaf.basic.BasicSplitPaneUI.BasicHorizontalLayoutManager
Returns the sizes of the components.

getSlaveSyncMode() - Method in interface javax.sound.midi.Sequencer
Obtains the current slave synchronization mode for this sequencer.

getSlaveSyncModes() - Method in interface javax.sound.midi.Sequencer
Obtains the set of slave synchronization modes supported by the sequencer.

getSmallDisplayIcon() - Method in class javax.swing.colorchooser.AbstractColorChooserPanel
Returns the large display icon for the panel.

getSnapToTicks() - Method in class javax.swing.JSlider
Returns true if the knob (and the data value it represents) resolve to the closest tick mark next to where the user positioned the knob.

getSocketFactory() - Static method in class java.rmi.server.RMISocketFactory
Returns the socket factory set by the setSocketFactory method.

getSoLinger() - Method in class java.net.Socket
Returns setting for SO_LINGER.

getSolo() - Method in interface javax.sound.midi.MidiChannel
Obtains the current solo state for this channel.

getSoTimeout() - Method in class java.net.DatagramSocket
Retrive setting for SO_TIMEOUT.

getSoTimeout() - Method in class java.net.Socket
Returns setting for SO_TIMEOUT.

getSoTimeout() - Method in class java.net.ServerSocket
Retrive setting for SO_TIMEOUT.

[getSoundbank\(\)](#) - Method in class javax.sound.midi.[SoundbankResource](#)
Obtains the sound bank that contains this [SoundbankResource](#).

[getSoundbank\(File\)](#) - Static method in class javax.sound.midi.[MidiSystem](#)
Constructs a Soundbank by reading it from the specified File.

[getSoundbank\(File\)](#) - Method in class javax.sound.midi.spi.[SoundbankReader](#)
Obtains a soundbank object from the File provided.

[getSoundbank\(InputStream\)](#) - Static method in class javax.sound.midi.[MidiSystem](#)
Constructs a MIDI sound bank by reading it from the specified stream.

[getSoundbank\(InputStream\)](#) - Method in class javax.sound.midi.spi.[SoundbankReader](#)
Obtains a soundbank object from the InputStream provided.

[getSoundbank\(URL\)](#) - Static method in class javax.sound.midi.[MidiSystem](#)
Constructs a Soundbank by reading it from the specified URL.

[getSoundbank\(URL\)](#) - Method in class javax.sound.midi.spi.[SoundbankReader](#)
Obtains a soundbank object from the URL provided.

[getSource\(\)](#) - Method in class java.awt.[Image](#)
Gets the object that produces the pixels for the image.

[getSource\(\)](#) - Method in class java.awt.image.[BufferedImage](#)
Returns the object that produces the pixels for the image.

[getSource\(\)](#) - Method in class java.util.[EventObject](#)
The object on which the Event initially occurred.

[getSource\(int\)](#) - Method in class java.awt.image.renderable.[ParameterBlock](#)
Returns a source as a general Object.

[getSourceActions\(\)](#) - Method in class java.awt.dnd.[DragGestureRecognizer](#)
This method returns an int representing the type of action(s) this Drag and Drop operation will support.

[getSourceActions\(\)](#) - Method in class java.awt.dnd.[DropTargetDropEvent](#)
This method returns an int representing the action(s) supported by the source.

[getSourceActions\(\)](#) - Method in class java.awt.dnd.[DragSourceContext](#)
This method returns an int representing the current action(s) associated with this DragSourceContext.

[getSourceActions\(\)](#) - Method in class java.awt.dnd.[DropTargetDragEvent](#)
This method returns an int representing set of actions supported by the source.

[getSourceAsBeanContextServices\(\)](#) - Method in class java.beans.beancontext.[BeanContextServiceAvailableEvent](#)
Gets the source as a reference of type BeanContextServices.

[getSourceAsBeanContextServices\(\)](#) - Method in class java.beans.beancontext.[BeanContextServiceRevokedEvent](#)
Gets the source as a reference of type BeanContextServices

[getSourceAsDragGestureRecognizer\(\)](#) - Method in class java.awt.dnd.[DragGestureEvent](#)
This method returns the source as a DragGestureRecognizer.

[getSourceElement\(\)](#) - Method in class javax.swing.text.html.[HTMLFrameHyperlinkEvent](#)
returns the element that corresponds to the source of the event.

[getSourceEncodings\(\)](#) - Method in class javax.sound.sampled.spi.[FormatConversionProvider](#)
Obtains the set of source format encodings from which format conversion services are provided by this provider.

[getSourceLineInfo\(\)](#) - Method in interface javax.sound.sampled.[Mixer](#)
Obtains information about the set of source lines supported by this mixer.

[getSourceLineInfo\(Line.Info\)](#) - Method in interface javax.sound.sampled.[Mixer](#)
Obtains information about source lines of a particular type supported by the mixer.

[getSourceLineInfo\(Line.Info\)](#) - Static method in class javax.sound.sampled.[AudioSystem](#)
Obtains information about source lines of a particular type that are supported by any installed mixer.

[getSourceLines\(\)](#) - Method in interface javax.sound.sampled.[Mixer](#)
Obtains the set of all source lines currently open to this mixer.

[getSources\(\)](#) - Method in interface java.awt.image.[RenderedImage](#)
Returns a vector of RenderedImages that are the immediate sources of image data for this RenderedImage.

getSources() - Method in class [java.awt.image.BufferedImage](#)
Returns a [Vector](#) of [RenderedImage](#) objects that are the immediate sources, not the sources of these immediate sources, of image data for this [BufferedImage](#).

getSources() - Method in class [java.awt.image.renderable.RenderableImageOp](#)
Returns a vector of [RenderableImages](#) that are the sources of image data for this [RenderableImage](#).

getSources() - Method in interface [java.awt.image.renderable.RenderableImage](#)
Returns a vector of [RenderableImages](#) that are the sources of image data for this [RenderableImage](#).

getSources() - Method in class [java.awt.image.renderable.ParameterBlock](#)
Returns the entire [Vector](#) of sources.

getSourceString() - Method in class [java.text.CollationKey](#)
Returns the [String](#) that this [CollationKey](#) represents.

getSouthPane() - Method in class [javax.swing.plaf.basic.BasicInternalFrameUI](#)

getSpaceAbove(AttributeSet) - Static method in class [javax.swing.text.StyleConstants](#)
Gets the space above setting.

getSpaceBelow(AttributeSet) - Static method in class [javax.swing.text.StyleConstants](#)
Gets the space below setting.

getSpan(GlyphView, int, int, TabExpander, float) - Method in class [javax.swing.text.GlyphView.GlyphPainter](#)
Determine the span the glyphs given a start location (for tab expansion).

getSpan(int, int) - Method in class [javax.swing.text.BoxView](#)
Fetch the span of a particular child's current layout

getSpecificationTitle() - Method in class [java.lang.Package](#)
Return the title of the specification that this package implements.

getSpecificationVendor() - Method in class [java.lang.Package](#)
Return the name of the organization, vendor, or company that owns and maintains the specification of the classes that implement this package.

getSpecificationVersion() - Method in class [java.lang.Package](#)
Returns the version number of the specification that this package implements.

getSplitPane() - Method in class [javax.swing.plaf.basic.BasicSplitPaneUI](#)
Returns the splitpane this instance is currently contained in.

getSplitPaneBorder() - Static method in class [javax.swing.plaf.basic.BasicBorders](#)

getSplitPaneDividerBorder() - Static method in class [javax.swing.plaf.basic.BasicBorders](#)
Returns a border instance for a [JSplitPane](#) divider

getSQLKeywords() - Method in interface [java.sql.DatabaseMetaData](#)
Gets a comma-separated list of all a database's SQL keywords that are NOT also SQL92 keywords.

getSQLState() - Method in class [java.sql.SQLException](#)
Retrieves the SQLState for this [SQLException](#) object.

getSQLTypeName() - Method in interface [java.sql.SQLData](#)
Returns the fully-qualified name of the SQL user-defined type that this object represents.

getSQLTypeName() - Method in interface [java.sql.Struct](#)
Retrieves the SQL type name of the SQL structured type that this [Struct](#) object represents.

getStartIndex() - Method in class [javax.accessibility.AccessibleHyperlink](#)
Gets the index with the hypertext document at which this link begins

getStartIndex() - Method in class [javax.swing.JEditorPane.JEditorPaneAccessibleHypertextSupport.HTMLLink](#)
Get the index with the hypertext document at which this link begins

getStartOffset() - Method in class [javax.swing.text.View](#)
Fetches the portion of the model that this view is responsible for.

getStartOffset() - Method in interface [javax.swing.text.Element](#)
Fetches the offset from the beginning of the document that this element begins at.

getStartOffset() - Method in class [javax.swing.text.GlyphView](#)
Fetches the portion of the model that this view is responsible for.

getStartOffset() - Method in interface [javax.swing.text.Highlighter.Highlight](#)

Gets the starting model offset for the highlight.

getStartOffset() - Method in class javax.swing.text.AbstractWriter
Returns the first offset to be output.

getStartOffset() - Method in class javax.swing.text.AbstractDocument.AbstractElement
Gets the starting offset in the model for the element.

getStartOffset() - Method in class javax.swing.text.AbstractDocument.BranchElement
Gets the starting offset in the model for the element.

getStartOffset() - Method in class javax.swing.text.AbstractDocument.LeafElement
Gets the starting offset in the model for the element.

getStartOffset() - Method in class javax.swing.text.html.HTMLDocument.Iterator
Start of the range for which the current occurrence of the tag is defined and has the same attributes.

getStartPoint() - Method in class java.awt.geom.Arc2D
Returns the starting point of the arc.

getStartPosition() - Method in interface javax.swing.text.Document
Returns a position that represents the start of the document.

getStartPosition() - Method in class javax.swing.text.AbstractDocument
Returns a position that represents the start of the document.

getState() - Method in class java.awt.Checkbox
Determines whether this check box is in the "on" or "off" state.

getState() - Method in class java.awt.Frame
Gets the state of this frame.

getState() - Method in class java.awt.CheckboxMenuItem
Determines whether the state of this check box menu item is "on" or "off."

getState() - Method in class java.awt.im.InputMethodHighlight
Returns the conversion state of the text range.

getState() - Method in class javax.swing.JCheckBoxMenuItem
Returns the selected-state of the item.

getStateChange() - Method in class java.awt.event.ItemEvent
Returns the type of state change (selected or deselected).

getStateLabel(boolean) - Method in class javax.sound.sampled.BooleanControl
Obtains the label for the specified state.

getStatement() - Method in interface java.sql.ResultSet
Returns the Statement object that produced this ResultSet object.

getStateToBind(Object, Name, Context, Hashtable) - Method in interface javax.naming.spi.StateFactory
Retrieves the state of an object for binding.

getStateToBind(Object, Name, Context, Hashtable) - Static method in class javax.naming.spi.NamingManager
Retrieves the state of an object for binding.

getStateToBind(Object, Name, Context, Hashtable, Attributes) - Static method in class javax.naming.spi.DirectoryManager
Retrieves the state of an object for binding when given the original object and its attributes.

getStateToBind(Object, Name, Context, Hashtable, Attributes) - Method in interface javax.naming.spi.DirStateFactory
Retrieves the state of an object for binding given the object and attributes to be transformed.

getStaticAttribute(Object) - Static method in class javax.swing.text.StyleContext
Returns the object previously registered with registerStaticAttributeKey.

getStaticAttributeKey(Object) - Static method in class javax.swing.text.StyleContext
Returns the String that key will be registered with

getStatus() - Method in class java.awt.image.PixelGrabber
Return the status of the pixels.

getStatus() - Method in class javax.sound.midi.MidiMessage
Obtains the status byte for the MIDI message.

getStream(URL) - Method in class javax.swing.JEditorPane
Fetches a stream for the given URL, which is about to be loaded by the setPage method.

[getStrength\(\)](#) - Method in class [java.text.Collator](#)
Returns this Collator's strength property.

[getStrikethroughOffset\(\)](#) - Method in class [java.awt.font.LineMetrics](#)
Returns the position of the strike-through line relative to the baseline.

[getStrikethroughThickness\(\)](#) - Method in class [java.awt.font.LineMetrics](#)
Returns the thickness of the strike-through line.

[getString\(\)](#) - Method in class [javax.swing.JProgressBar](#)
Returns the current value of the Progress String.

[getString\(\)](#) - Method in class [javax.swing.text.html.parser.Entity](#)
Return the data as a string.

[getString\(int\)](#) - Method in interface [java.sql.CallableStatement](#)
Retrieves the value of a JDBC CHAR, VARCHAR, or LONGVARCHAR parameter as a String in the Java programming language.

[getString\(int\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a String in the Java programming language.

[getString\(int, int\)](#) - Method in interface [javax.swing.text.AbstractDocument.Content](#)
Fetches a string of characters contained in the sequence.

[getString\(int, int\)](#) - Method in class [javax.swing.text.StringContent](#)
Retrieves a portion of the content.

[getString\(int, int\)](#) - Method in class [javax.swing.text.GapContent](#)
Retrieves a portion of the content.

[getString\(Object\)](#) - Method in class [javax.swing.UIDefaults](#)
If the value of key is a String return it, otherwise return null.

[getString\(Object\)](#) - Static method in class [javax.swing.UIManager](#)
Returns a string from the defaults table.

[getString\(String\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a String in the Java programming language.

[getString\(String\)](#) - Method in class [java.util.ResourceBundle](#)
Get an object from a ResourceBundle.

[getStringArray\(String\)](#) - Method in class [java.util.ResourceBundle](#)
Get an object from a ResourceBundle.

[getStringBounds\(char\[\], int, int, FontRenderContext\)](#) - Method in class [java.awt.Font](#)
Returns the bounds of the specified array of characters in the specified FontRenderContext.

[getStringBounds\(char\[\], int, int, Graphics\)](#) - Method in class [java.awt.FontMetrics](#)
Returns the bounds of the specified array of characters in the specified Graphics context.

[getStringBounds\(CharacterIterator, int, int, FontRenderContext\)](#) - Method in class [java.awt.Font](#)
Returns the bounds of the characters indexed in the specified CharacterIterator in the specified FontRenderContext.

[getStringBounds\(CharacterIterator, int, int, Graphics\)](#) - Method in class [java.awt.FontMetrics](#)
Returns the bounds of the characters indexed in the specified CharacterIterator in the specified Graphics context.

[getStringBounds\(String, FontRenderContext\)](#) - Method in class [java.awt.Font](#)
Returns the bounds of the specified String in the specified FontRenderContext.

[getStringBounds\(String, Graphics\)](#) - Method in class [java.awt.FontMetrics](#)
Returns the bounds of the specified String in the specified Graphics context.

[getStringBounds\(String, int, int, FontRenderContext\)](#) - Method in class [java.awt.Font](#)
Returns the bounds of the specified String in the specified FontRenderContext.

[getStringBounds\(String, int, int, Graphics\)](#) - Method in class [java.awt.FontMetrics](#)
Returns the bounds of the specified String in the specified Graphics context.

[getStringFunctions\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
Gets a comma-separated list of string functions.

[getStringPlacement\(Graphics, String, int, int, int, int\)](#) - Method in class [javax.swing.plaf.basic.BasicProgressBarUI](#)
Designate the place where the progress string will be drawn.

[getStroke\(\)](#) - Method in class [java.awt.Graphics2D](#)

Returns the current Stroke in the Graphics2D context.

[getStrongCaret\(TextHitInfo, TextHitInfo, TextLayout\)](#) - Method in class [java.awt.font.TextLayout.CaretPolicy](#)
 Chooses one of the specified TextHitInfo instances as a strong caret in the specified TextLayout.

[getStyle\(\)](#) - Method in class [java.awt.Font](#)
 Returns the style of this Font.

[getStyle\(\)](#) - Method in class [java.awt.im.InputMethodHighlight](#)
 Returns the rendering style attributes for the text range, or null.

[getStyle\(String\)](#) - Method in class [javax.swing.JTextPane](#)
 Fetches a named non-null style previously added.

[getStyle\(String\)](#) - Method in class [javax.swing.text.StyleContext](#)
 Fetches a named style previously added to the document

[getStyle\(String\)](#) - Method in interface [javax.swing.text.StyledDocument](#)
 Fetches a named style previously added.

[getStyle\(String\)](#) - Method in class [javax.swing.text.DefaultStyledDocument](#)
 Fetches a named style previously added.

[getStyledDocument\(\)](#) - Method in class [javax.swing.JTextPane](#)
 Fetches the model associated with the editor.

[getStyledDocument\(JEditorPane\)](#) - Method in class [javax.swing.text.StyledEditorKit.StyledTextAction](#)
 Gets the document associated with an editor pane.

[getStyledEditorKit\(\)](#) - Method in class [javax.swing.JTextPane](#)
 Gets the editor kit.

[getStyledEditorKit\(JEditorPane\)](#) - Method in class [javax.swing.text.StyledEditorKit.StyledTextAction](#)
 Gets the editor kit associated with an editor pane.

[getStyleNames\(\)](#) - Method in class [javax.swing.text.StyleContext](#)
 Fetches the names of the styles defined.

[getStyleNames\(\)](#) - Method in class [javax.swing.text.DefaultStyledDocument](#)
 Fetches the list of of style names.

[getStyleSheet\(\)](#) - Method in class [javax.swing.text.html.ParagraphView](#)

[getStyleSheet\(\)](#) - Method in class [javax.swing.text.html.BlockView](#)

[getStyleSheet\(\)](#) - Method in class [javax.swing.text.html.InlineView](#)

[getStyleSheet\(\)](#) - Method in class [javax.swing.text.html.HTMLDocument](#)
 Fetches the StyleSheet with the document-specific display rules (CSS) that were specified in the HTML document itself.

[getStyleSheet\(\)](#) - Method in class [javax.swing.text.html.HTMLEditorKit](#)
 Get the set of styles currently being used to render the HTML elements.

[getStyleSheets\(\)](#) - Method in class [javax.swing.text.html.StyleSheet](#)
 Returns an array of the linked StyleSheets.

[getSubElements\(\)](#) - Method in class [javax.swing.JMenuItem](#)
 This method returns an array containing the sub-menu components for this menu component.

[getSubElements\(\)](#) - Method in class [javax.swing.JMenu](#)
 Returns an array of MenuElements containing the submenu for this menu component.

[getSubElements\(\)](#) - Method in class [javax.swing.JPopupMenu](#)
 Returns an array of MenuElements containing the submenu for this menu component.

[getSubElements\(\)](#) - Method in class [javax.swing.JMenuBar](#)
 Implemented to be a MenuElement -- returns the menus in this menu bar.

[getSubElements\(\)](#) - Method in interface [javax.swing.MenuElement](#)
 This method should return an array containing the sub-elements for the receiving menu element

[getSubimage\(int, int, int, int\)](#) - Method in class [java.awt.image.BufferedImage](#)
 Returns a subimage defined by a specified rectangular region.

[getSubjectDN\(\)](#) - Method in class [java.security.cert.X509Certificate](#)
 Gets the subject (subject distinguished name) value from the certificate.

[getSubjectUniqueID\(\)](#) - Method in class [java.security.cert.X509Certificate](#)

Gets the subjectUniqueID value from the certificate.

getSubString(long, int) - Method in interface java.sql.Clob
Returns a copy of the specified substring in the CLOB value designated by this Clob object.

getSubTextFont() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getSubTextFont() - Method in class javax.swing.plaf.metal.MetalTheme

getSubTextFont() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getSubType() - Method in class java.awt.datatransfer.DataFlavor

getSuffix(int) - Method in interface javax.naming.Name
Creates a name whose components consist of a suffix of the components in this name.

getSuffix(int) - Method in class javax.naming.CompoundName
Creates a compound name whose components consist of a suffix of the components in this compound name.

getSuffix(int) - Method in class javax.naming.CompositeName
Creates a composite name whose components consist of a suffix of the components in this composite name.

getSuperclass() - Method in class java.lang.Class
Returns the Class representing the superclass of the entity (class, interface, primitive type or void) represented by this Class.

getSyncAllWidths() - Method in class javax.swing.plaf.basic.BasicOptionPaneUI.ButtonAreaLayout

getSynthesizer() - Static method in class javax.sound.midi.MidiSystem
Obtains the default synthesizer.

getSystem() - Method in class java.rmi.activation.ActivationGroupID
Returns the group's activation system.

getSystem() - Static method in class java.rmi.activation.ActivationGroup
Returns the activation system for the VM.

getSystemClassLoader() - Static method in class java.lang.ClassLoader
Returns the system class loader for delegation.

getSystemClipboard() - Method in class java.awt.Toolkit
Gets the singleton instance of the system Clipboard which interfaces with clipboard facilities provided by the native platform.

getSystemCustomCursor(String) - Static method in class java.awt.Cursor

getSystemEventQueue() - Method in class java.awt.Toolkit
Get the application's or applet's EventQueue instance.

getSystemEventQueueImpl() - Method in class java.awt.Toolkit

getSystemFunctions() - Method in interface java.sql.DatabaseMetaData
Gets a comma-separated list of system functions.

getSystemLookAndFeelClassName() - Static method in class javax.swing.UIManager
Returns the name of the LookAndFeel class that implements the native systems look and feel if there is one, otherwise the name of the default cross platform LookAndFeel class.

getSystemResource(String) - Static method in class java.lang.ClassLoader
Find a resource of the specified name from the search path used to load classes.

getSystemResourceAsStream(String) - Static method in class java.lang.ClassLoader
Open for reading, a resource of the specified name from the search path used to load classes.

getSystemResources(String) - Static method in class java.lang.ClassLoader
Finds all resources of the specified name from the search path used to load classes.

getSystemScope() - Static method in class java.security.IdentityScope
Deprecated. Returns the system's identity scope.

getSystemTextColor() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getSystemTextColor() - Method in class javax.swing.plaf.metal.MetalTheme

[getSystemTextFont\(\)](#) - Static method in class javax.swing.plaf.metal.[MetalLookAndFeel](#)

[getSystemTextFont\(\)](#) - Method in class javax.swing.plaf.metal.[MetalTheme](#)

[getSystemTextFont\(\)](#) - Method in class javax.swing.plaf.metal.[DefaultMetalTheme](#)

[getTab\(int\)](#) - Method in class javax.swing.text.[TabSet](#)
Returns the TabStop at index index.

[getTabAfter\(float\)](#) - Method in class javax.swing.text.[TabSet](#)
Returns the Tab instance after location.

[getTabAreaInsets\(int\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getTabBase\(\)](#) - Method in class javax.swing.text.[ParagraphView](#)

[getTabbedSpan\(float, TabExpander\)](#) - Method in class javax.swing.text.[GlyphView](#)
Determines the desired span when using the given tab expansion implementation.

[getTabbedSpan\(float, TabExpander\)](#) - Method in interface javax.swing.text.[TabableView](#)
Determines the desired span when using the given tab expansion implementation.

[getTabbedTextOffset\(Segment, FontMetrics, int, int, TabExpander, int\)](#) - Static method in class javax.swing.text.[Utilities](#)
Determines the relative offset into the given text that best represents the given span in the view coordinate system.

[getTabbedTextOffset\(Segment, FontMetrics, int, int, TabExpander, int, boolean\)](#) - Static method in class javax.swing.text.[Utilities](#)

[getTabbedTextWidth\(Segment, FontMetrics, int, TabExpander, int\)](#) - Static method in class javax.swing.text.[Utilities](#)
Determines the width of the given segment of text taking tabs into consideration.

[getTabBounds\(JTabbedPane, int\)](#) - Method in class javax.swing.plaf.[TabbedPaneUI](#)

[getTabBounds\(JTabbedPane, int\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getTabBounds\(JTabbedPane, int\)](#) - Method in class javax.swing.plaf.multi.[MultiTabbedPaneUI](#)
Call getTabBounds on each UI handled by this MultiUI.

[getTabCount\(\)](#) - Method in class javax.swing.[JTabbedPane](#)
Returns the number of tabs in this tabbedpane.

[getTabCount\(\)](#) - Method in class javax.swing.text.[TabSet](#)
Returns the number of Tab instances the receiver contains.

[getTabExpander\(\)](#) - Method in class javax.swing.text.[GlyphView](#)
Fetch the TabExpander to use if tabs are present in this view.

[getTabIndex\(TabStop\)](#) - Method in class javax.swing.text.[TabSet](#)

[getTabIndexAfter\(float\)](#) - Method in class javax.swing.text.[TabSet](#)
Returns the index of the Tab to be used after location.

[getTabInsets\(int, int\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getTabLabelShiftX\(int, int, boolean\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getTabLabelShiftX\(int, int, boolean\)](#) - Method in class javax.swing.plaf.metal.[MetalTabbedPaneUI](#)
Overridden to do nothing for the Java L&F.

[getTabLabelShiftY\(int, int, boolean\)](#) - Method in class javax.swing.plaf.basic.[BasicTabbedPaneUI](#)

[getTabLabelShiftY\(int, int, boolean\)](#) - Method in class javax.swing.plaf.metal.[MetalTabbedPaneUI](#)
Overridden to do nothing for the Java L&F.

[getTable\(\)](#) - Method in class java.awt.image.[ByteLookupTable](#)
Returns the lookup table data by reference.

getTable() - Method in class java.awt.image.LookupOp
Returns the LookupTable.

getTable() - Method in class java.awt.image.ShortLookupTable
Returns the lookup table data by reference.

getTable() - Method in class javax.swing.table.JTableHeader
Returns the table associated with this header.

getTableCellEditorComponent(JTable, Object, boolean, int, int) - Method in class javax.swing.DefaultCellEditor

getTableCellEditorComponent(JTable, Object, boolean, int, int) - Method in interface javax.swing.table.TableCellEditor
Sets an initial value for the editor.

getTableCellRendererComponent(JTable, Object, boolean, boolean, int, int) - Method in interface javax.swing.table.TableCellRenderer
Returns the component used for drawing the cell.

getTableCellRendererComponent(JTable, Object, boolean, boolean, int, int) - Method in class javax.swing.table.DefaultTableCellRenderer
Returns the default table cell renderer.

getTableHeader() - Method in class javax.swing.JTable
Returns the tableHeader used by this JTable.

getTableName(int) - Method in interface java.sql.ResultSetMetaData
Gets the designated column's table name.

getTablePrivileges(String, String, String) - Method in interface java.sql.DatabaseMetaData
Gets a description of the access rights for each table available in a catalog.

getTables(String, String, String, String[]) - Method in interface java.sql.DatabaseMetaData
Gets a description of tables available in a catalog.

getTableTypes() - Method in interface java.sql.DatabaseMetaData
Gets the table types available in this database.

getTabPlacement() - Method in class javax.swing.JTabbedPane
Returns the placement of the tabs for this tabbedpane.

getTabRunCount() - Method in class javax.swing.JTabbedPane
Returns the number of tab runs currently used to display the tabs.

getTabRunCount(JTabbedPane) - Method in class javax.swing.plaf.TabbedPaneUI

getTabRunCount(JTabbedPane) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getTabRunCount(JTabbedPane) - Method in class javax.swing.plaf.multi.MultiTabbedPaneUI
Call getTabRunCount on each UI handled by this MultiUI.

getTabRunIndent(int, int) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getTabRunOffset(int, int, int, boolean) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getTabRunOverlay(int) - Method in class javax.swing.plaf.basic.BasicTabbedPaneUI

getTabRunOverlay(int) - Method in class javax.swing.plaf.metal.MetalTabbedPaneUI

getTabSet() - Method in class javax.swing.text.ParagraphView
Gets the Tabset to be used in calculating tabs.

getTabSet(AttributeSet) - Static method in class javax.swing.text.StyleConstants
Gets the TabSet.

getTabSize() - Method in class javax.swing.JTextArea
Gets the number of characters used to expand tabs.

getTabSize() - Method in class javax.swing.text.PlainView
Returns the tab size set for the document, defaulting to 8.

getTabSize() - Method in class javax.swing.text.WrappedPlainView
Returns the tab size set for the document, defaulting to 8.

getTag() - Method in class javax.swing.text.html.HTMLDocument.Iterator

Type of tag this iterator represents.

getTag(String) - Static method in class `javax.swing.text.html.HTML`
Fetch a tag constant for a well-known tag name (i.e.

getTags() - Method in interface `java.beans.PropertyEditor`
If the property value must be one of a set of known tagged values, then this method should return an array of the tags.

getTags() - Method in class `java.beans.PropertyEditorSupport`
If the property value must be one of a set of known tagged values, then this method should return an array of the tag values.

getTarget() - Method in class `javax.accessibility.AccessibleRelation`
Returns the target objects for this relation

getTarget() - Method in interface `javax.rmi.CORBA.Tie`
Returns the target for this tie.

getTarget() - Method in class `javax.swing.text.html.HTMLFrameHyperlinkEvent`
returns the target for the link.

getTargetActions() - Method in class `java.awt.dnd.DropTargetContext`
This method returns an int representing the current actions this DropTarget will accept.

getTargetActions() - Method in class `java.awt.dnd.DragSourceDragEvent`
This method returns the logical intersection of the current target, source, and user actions.

getTargetEncodings() - Method in class `javax.sound.sampled.spi.FormatConversionProvider`
Obtains the set of target format encodings to which format conversion services are provided by this provider.

getTargetEncodings(AudioFormat.Encoding) - Static method in class `javax.sound.sampled.AudioSystem`
Obtains the encodings that the system can obtain from an audio input stream with the specified encoding using the set of installed format converters.

getTargetEncodings(AudioFormat) - Static method in class `javax.sound.sampled.AudioSystem`
Obtains the encodings that the system can obtain from an audio input stream with the specified format using the set of installed format converters.

getTargetEncodings(AudioFormat) - Method in class `javax.sound.sampled.spi.FormatConversionProvider`
Obtains the set of target format encodings supported by the format converter given a particular source format.

getTargetException() - Method in class `java.lang.reflect.InvocationTargetException`
Get the thrown target exception.

getTargetFormats(AudioFormat.Encoding, AudioFormat) - Static method in class `javax.sound.sampled.AudioSystem`
Obtains the formats that have a particular encoding and that the system can obtain from a stream of the specified format using the set of installed format converters.

getTargetFormats(AudioFormat.Encoding, AudioFormat) - Method in class `javax.sound.sampled.spi.FormatConversionProvider`
Obtains the set of target formats with the encoding specified supported by the format converter. If no target formats with the specified encoding are supported for this source format, an array of length 0 is returned.

getTargetLineInfo() - Method in interface `javax.sound.sampled.Mixer`
Obtains information about the set of target lines supported by this mixer.

getTargetLineInfo(Line.Info) - Method in interface `javax.sound.sampled.Mixer`
Obtains information about target lines of a particular type supported by the mixer.

getTargetLineInfo(Line.Info) - Static method in class `javax.sound.sampled.AudioSystem`
Obtains information about target lines of a particular type that are supported by any installed mixer.

getTargetLines() - Method in interface `javax.sound.sampled.Mixer`
Obtains the set of all target lines currently open from this mixer.

getTBSCertificate() - Method in class `java.security.cert.X509Certificate`
Gets the DER-encoded certificate information, the tbsCertificate from this certificate.

getTBSCertList() - Method in class `java.security.cert.X509CRL`
Gets the DER-encoded CRL information, the tbsCertList from this CRL.

getTcpNoDelay() - Method in class `java.net.Socket`
Tests if TCP_NODELAY is enabled.

getTempoFactor() - Method in interface [javax.sound.midi.Sequencer](#)
Returns the current tempo factor for the sequencer.

getTempoInBPM() - Method in interface [javax.sound.midi.Sequencer](#)
Obtains the current tempo, expressed in beats per minute.

getTempoInMPQ() - Method in interface [javax.sound.midi.Sequencer](#)
Obtains the current tempo, expressed in microseconds per quarter note.

getText() - Method in class [java.awt.TextComponent](#)
Gets the text that is presented by this text component.

getText() - Method in class [java.awt.Label](#)
Gets the text of this label.

getText() - Method in class [java.awt.event.InputMethodEvent](#)
Gets the combined committed and composed text.

getText() - Method in class [java.text.BreakIterator](#)
Get the text being scanned

getText() - Method in class [javax.swing.JEditorPane](#)
Returns the text contained in this [TextComponent](#) in terms of the content type of this editor.

getText() - Method in class [javax.swing.AbstractButton](#)
Returns the button's text.

getText() - Method in class [javax.swing.JPasswordField](#)
Deprecated. *As of Java 2 platform v1.2, replaced by [getPassword\(\)](#).*

getText() - Method in class [javax.swing.JLabel](#)
Returns the text string that the label displays.

getText() - Method in class [javax.swing.text.JTextComponent](#)
Returns the text contained in this [TextComponent](#).

getText(Element) - Method in class [javax.swing.text.AbstractWriter](#)
Returns the text associated with the element.

getText(int, int) - Method in class [javax.swing.JPasswordField](#)
Deprecated. *As of Java 2 platform v1.2, replaced by [getPassword\(\)](#).*

getText(int, int) - Method in class [javax.swing.text.JTextComponent](#)
Fetches a portion of the text represented by the component.

getText(int, int) - Method in interface [javax.swing.text.Document](#)
Fetches the text contained within the given portion of the document.

getText(int, int) - Method in class [javax.swing.text.GlyphView](#)
Fetch a reference to the text that occupies the given range.

getText(int, int) - Method in class [javax.swing.text.AbstractDocument](#)
Gets a sequence of text from the document.

getText(int, int, Segment) - Method in interface [javax.swing.text.Document](#)
Fetches the text contained within the given portion of the document.

getText(int, int, Segment) - Method in class [javax.swing.text.AbstractDocument](#)
Gets some text from the document potentially without making a copy.

getTextBorder() - Static method in class [javax.swing.plaf.metal.MetalBorders](#)
Returns a border instance for a text component

getTextComponent(ActionEvent) - Method in class [javax.swing.text.TextAction](#)
Determines the component to use for the action.

getTextFieldBorder() - Static method in class [javax.swing.plaf.basic.BasicBorders](#)

getTextFieldBorder() - Static method in class [javax.swing.plaf.metal.MetalBorders](#)
Returns a border instance for a [JTextField](#)

getTextHighlightColor() - Static method in class [javax.swing.plaf.metal.MetalLookAndFeel](#)

getTextHighlightColor() - Method in class [javax.swing.plaf.metal.MetalTheme](#)

getTextLocation(TextHitInfo) - Method in interface [java.awt.im.InputMethodRequests](#)
Gets the location of a specified offset in the current composed text, or of the selection in committed text.

getTextNonSelectionColor() - Method in class [javax.swing.tree.DefaultTreeCellRenderer](#)
Returns the color the text is drawn with when the node isn't selected.

getPlainTextUnicodeFlavor() - Static method in class java.awt.datatransfer.DataFlavor

getTextSelectionColor() - Method in class javax.swing.tree.DefaultTreeCellRenderer

Returns the color the text is drawn with when the node is selected.

getTextShiftOffset() - Method in class javax.swing.plaf.basic.BasicButtonUI

getThickness() - Method in class javax.swing.border.LineBorder

Returns the thickness of the border.

getThisUpdate() - Method in class java.security.cert.X509CRL

Gets the thisUpdate date from the CRL.

getThreadGroup() - Method in class java.lang.Thread

Returns the thread group to which this thread belongs.

getThreadGroup() - Method in class java.lang.SecurityManager

Returns the thread group into which to instantiate any new thread being created at the time this is being called.

getThumbBounds() - Method in class javax.swing.plaf.basic.BasicScrollBarUI

Return the current size/location of the thumb.

getThumbOverhang() - Method in class javax.swing.plaf.metal.MetalSliderUI

Returns the amount that the thumb goes past the slide bar.

getThumbSize() - Method in class javax.swing.plaf.basic.BasicSliderUI

getThumbSize() - Method in class javax.swing.plaf.metal.MetalSliderUI

getTick() - Method in class javax.sound.midi.MidiEvent

Obtains the time-stamp for the event, in MIDI ticks

getTickLength() - Method in class javax.sound.midi.Sequence

Obtains the duration of this sequence, expressed in MIDI ticks.

getTickLength() - Method in interface javax.sound.midi.Sequencer

Obtains the length of the current sequence, expressed in MIDI ticks.

getTickLength() - Method in class javax.swing.plaf.basic.BasicSliderUI

Gets the height of the tick area for horizontal sliders and the width of the tick area for vertical sliders.

getTickLength() - Method in class javax.swing.plaf.metal.MetalSliderUI

Gets the height of the tick area for horizontal sliders and the width of the tick area for vertical sliders.

getTickPosition() - Method in interface javax.sound.midi.Sequencer

Obtains the current position in the sequence, expressed in MIDI ticks.

getTie(Remote) - Static method in class javax.rmi.CORBA.Util

Returns the tie (if any) for a given target object.

getTie(Remote) - Method in interface javax.rmi.CORBA.UtilDelegate

Delegation call for Util.getTie(java.rmi.Remote).

getTile(int, int) - Method in interface java.awt.image.RenderedImage

Returns tile (tileX, tileY).

getTile(int, int) - Method in class java.awt.image.BufferedImage

Returns tile (tileX, tileY).

getTiledSizeRequirements(SizeRequirements[]) - Static method in class javax.swing.SizeRequirements

Determines the total space necessary to place a set of components end-to-end.

getTileGridXOffset() - Method in interface java.awt.image.RenderedImage

Returns the X offset of the tile grid relative to the origin, i.e., the X coordinate of the upper-left pixel of tile (0, 0).

getTileGridXOffset() - Method in class java.awt.image.BufferedImage

Returns the x offset of the tile grid relative to the origin, For example, the x coordinate of the location of tile (0, 0).

getTileGridYOffset() - Method in interface java.awt.image.RenderedImage

Returns the Y offset of the tile grid relative to the origin, i.e., the Y coordinate of the upper-left pixel of tile (0, 0).

getTileGridYOffset() - Method in class java.awt.image.BufferedImage

Returns the y offset of the tile grid relative to the origin, For example, the y coordinate of the location of tile (0, 0).

[getTileHeight\(\)](#) - Method in interface [java.awt.image.RenderedImage](#)
Returns the tile height in pixels.

[getTileHeight\(\)](#) - Method in class [java.awt.image.BufferedImage](#)
Returns the tile height in pixels.

[getTileIcon\(\)](#) - Method in class [javax.swing.border.MatteBorder](#)
Returns the icon used for tiling the border or null if a solid color is being used.

[getTileWidth\(\)](#) - Method in interface [java.awt.image.RenderedImage](#)
Returns the tile width in pixels.

[getTileWidth\(\)](#) - Method in class [java.awt.image.BufferedImage](#)
Returns the tile width in pixels.

[getTime\(\)](#) - Method in class [java.util.Date](#)
Returns the number of milliseconds since January 1, 1970, 00:00:00 GMT represented by this Date object.

[getTime\(\)](#) - Method in class [java.util.Calendar](#)
Gets this Calendar's current time.

[getTime\(\)](#) - Method in class [java.util.zip.ZipEntry](#)
Returns the modification time of the entry, or -1 if not specified.

[getTime\(int\)](#) - Method in interface [java.sql.CallableStatement](#)
Get the value of a JDBC TIME parameter as a [java.sql.Time](#) object.

[getTime\(int\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a [java.sql.Time](#) object in the Java programming language.

[getTime\(int, Calendar\)](#) - Method in interface [java.sql.CallableStatement](#)
Gets the value of a JDBC TIME parameter as a [java.sql.Time](#) object, using the given Calendar object to construct the time.

[getTime\(int, Calendar\)](#) - Method in interface [java.sql.ResultSet](#)
Returns the value of the designated column in the current row of this ResultSet object as a [java.sql.Time](#) object in the Java programming language.

[getTime\(String\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a [java.sql.Time](#) object in the Java programming language.

[getTime\(String, Calendar\)](#) - Method in interface [java.sql.ResultSet](#)
Returns the value of the designated column in the current row of this ResultSet object as a [java.sql.Time](#) object in the Java programming language.

[getTimeDateFunctions\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
Gets a comma-separated list of time and date functions.

[getTimeInMillis\(\)](#) - Method in class [java.util.Calendar](#)
Gets this Calendar's current time as a long.

[getTimeInstance\(\)](#) - Static method in class [java.text.DateFormat](#)
Gets the time formatter with the default formatting style for the default locale.

[getTimeInstance\(int\)](#) - Static method in class [java.text.DateFormat](#)
Gets the time formatter with the given formatting style for the default locale.

[getTimeInstance\(int, Locale\)](#) - Static method in class [java.text.DateFormat](#)
Gets the time formatter with the given formatting style for the given locale.

[getTimeLimit\(\)](#) - Method in class [javax.naming.directory.SearchControls](#)
Retrieves the time limit of these SearchControls in milliseconds.

[getTimestamp\(int\)](#) - Method in interface [java.sql.CallableStatement](#)
Gets the value of a JDBC TIMESTAMP parameter as a [java.sql.Timestamp](#) object.

[getTimestamp\(int\)](#) - Method in interface [java.sql.ResultSet](#)
Gets the value of the designated column in the current row of this ResultSet object as a [java.sql.Timestamp](#) object in the Java programming language.

[getTimestamp\(int, Calendar\)](#) - Method in interface [java.sql.CallableStatement](#)
Gets the value of a JDBC TIMESTAMP parameter as a [java.sql.Timestamp](#) object, using the given Calendar object to construct the Timestamp object.

[getTimestamp\(int, Calendar\)](#) - Method in interface [java.sql.ResultSet](#)

Returns the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Timestamp` object in the Java programming language.

`getTimestamp(String)` - Method in interface `java.sql.ResultSet`
 Gets the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Timestamp` object.

`getTimestamp(String, Calendar)` - Method in interface `java.sql.ResultSet`
 Returns the value of the designated column in the current row of this `ResultSet` object as a `java.sql.Timestamp` object in the Java programming language.

`getTimeToLive()` - Method in class `java.net.MulticastSocket`
 Get the default time-to-live for multicast packets sent out on the socket.

`getTimeToLive()` - Method in class `java.net.DatagramSocketImpl`
 Retrieve the TTL (time-to-live) option.

`getTimeZone()` - Method in class `java.text.DateFormat`
 Gets the time zone.

`getTimeZone()` - Method in class `java.util.Calendar`
 Gets the time zone.

`getTimeZone(String)` - Static method in class `java.util.TimeZone`
 Gets the `TimeZone` for the given ID.

`getTimezoneOffset()` - Method in class `java.util.Date`
 Deprecated. *As of JDK version 1.1, replaced by `Calendar.get(Calendar.ZONE_OFFSET) + Calendar.get(Calendar.DST_OFFSET)`.*

`getTipText()` - Method in class `javax.swing.JToolTip`
 Returns the text that is shown when the tool tip is displayed.

`getTitle()` - Method in class `java.awt.Dialog`
 Gets the title of the dialog.

`getTitle()` - Method in class `java.awt.Frame`
 Gets the title of the frame.

`getTitle()` - Method in class `javax.swing.JInternalFrame`
 Returns the title of the `JInternalFrame`.

`getTitle()` - Method in class `javax.swing.border.TitledBorder`
 Returns the title of the titled border.

`getTitleAt(int)` - Method in class `javax.swing.JTabbedPane`
 Returns the tab title at index.

`getTitleColor()` - Method in class `javax.swing.border.TitledBorder`
 Returns the title-color of the titled border.

`getTitleFont()` - Method in class `javax.swing.border.TitledBorder`
 Returns the title-font of the titled border.

`getTitleJustification()` - Method in class `javax.swing.border.TitledBorder`
 Returns the title-justification of the titled border.

`getTitlePosition()` - Method in class `javax.swing.border.TitledBorder`
 Returns the title-position of the titled border.

`getToggleButtonBorder()` - Static method in class `javax.swing.plaf.basic.BasicBorders`

`getToggleButtonBorder()` - Static method in class `javax.swing.plaf.metal.MetalBorders`
 Returns a border instance for a `JToggleButton`

`getToggleClickCount()` - Method in class `javax.swing.JTree`
 Returns the number of mouse clicks needed to expand or close a node.

`getToIndex()` - Method in class `javax.swing.event.TableColumnModelEvent`
 Returns the `toIndex`.

`getTokenThreshold()` - Method in class `javax.swing.text.html.HTMLDocument`
 Gets the number of tokens to buffer before trying to update the documents element structure.

`getToolkit()` - Method in class `java.awt.Component`
 Gets the toolkit of this component.

`getToolkit()` - Method in class `java.awt.Window`
 Returns the toolkit of this frame.

`getToolTipLocation(MouseEvent)` - Method in class `javax.swing.JComponent`
 Returns the tooltip location in this component's coordinate system.

getToolTipText() - Method in class [javax.swing.JComponent](#)
Returns the tooltip string that has been set with [setToolTipText\(\)](#).

getToolTipText(MouseEvent) - Method in class [javax.swing.JComponent](#)
Returns the string to be used as the tooltip for *event*.

getToolTipText(MouseEvent) - Method in class [javax.swing.JTabbedPane](#)
Returns the tooltip text for the component determined by the mouse event location.

getToolTipText(MouseEvent) - Method in class [javax.swing.JTree](#)
Overrides [JComponent](#)'s [getToolTipText](#) method in order to allow renderer's tips to be used if it has text set.

getToolTipText(MouseEvent) - Method in class [javax.swing.JTable](#)
Overrides [JComponent](#)'s [getToolTipText](#) method in order to allow the renderer's tips to be used if it has text set.

getToolTipText(MouseEvent) - Method in class [javax.swing.table.JTableHeader](#)
Allows the renderer's tips to be used if there is text set.

getToolTipTextAt(int) - Method in class [javax.swing.JTabbedPane](#)
Returns the tab tooltip text at index.

getToPage() - Method in class [java.awt.JobAttributes](#)
Returns, for jobs using these attributes, the last page (inclusive) to be printed, if a range of pages is to be printed.

getTopComponent() - Method in class [javax.swing.JSplitPane](#)
Returns the component above, or to the left of the divider.

getTopInset() - Method in class [javax.swing.text.CompositeView](#)
Gets the top inset.

getTopInset() - Method in class [javax.swing.text.AsyncBoxView](#)
Get the top part of the margin around the view.

getTopLevelAncestor() - Method in class [javax.swing.JComponent](#)
Returns the top-level ancestor of this component (either the containing Window or Applet), or null if this component has not been added to any container.

getTotalColumnWidth() - Method in class [javax.swing.table.DefaultTableColumnModel](#)
Returns the total combined width of all columns.

getTotalColumnWidth() - Method in interface [javax.swing.table.TableColumnModel](#)
Returns the total width of all the columns.

getTotalIn() - Method in class [java.util.zip.Deflater](#)
Returns the total number of bytes input so far.

getTotalIn() - Method in class [java.util.zip.Inflater](#)
Returns the total number of bytes input so far.

getTotalOut() - Method in class [java.util.zip.Deflater](#)
Returns the total number of bytes output so far.

getTotalOut() - Method in class [java.util.zip.Inflater](#)
Returns the total number of bytes output so far.

getTrackBounds() - Method in class [javax.swing.plaf.basic.BasicScrollBarUI](#)
Return the current bounds of the track, i.e.

getTrackLength() - Method in class [javax.swing.plaf.metal.MetalSliderUI](#)
Returns the longer dimension of the slide bar.

getTrackMute(int) - Method in interface [javax.sound.midi.Sequencer](#)
Obtains the current mute state for a track.

getTracks() - Method in class [javax.sound.midi.Sequence](#)
Obtains an array containing all the tracks in this sequence.

getTrackSolo(int) - Method in interface [javax.sound.midi.Sequencer](#)
Obtains the current solo state for a track.

getTrackWidth() - Method in class [javax.swing.plaf.metal.MetalSliderUI](#)
Returns the shorter dimension of the track.

getTransactionIsolation() - Method in interface [java.sql.Connection](#)
Gets this Connection's current transaction isolation level.

getTransferable() - Method in class [java.awt.dnd.DropTargetContext](#)
get the Transferable (proxy) operand of this operation

getTransferable() - Method in class [java.awt.dnd.DropTargetDropEvent](#)

This method returns the Transferable object associated with the drop.

[getTransferable\(\)](#) - Method in class [java.awt.dnd.DragSourceContext](#)
 This method returns the Transferable associated with this DragSourceContext.

[getTransferData\(DataFlavor\)](#) - Method in interface [java.awt.datatransfer.Transferable](#)
 Returns an object which represents the data to be transferred.

[getTransferData\(DataFlavor\)](#) - Method in class [java.awt.datatransfer.StringSelection](#)
 Returns the Transferable's data in the requested DataFlavor if possible.

[getTransferData\(DataFlavor\)](#) - Method in class [java.awt.dnd.DropTargetContext.TransferableProxy](#)
 get the transfer data

[getTransferDataFlavors\(\)](#) - Method in interface [java.awt.datatransfer.Transferable](#)
 Returns an array of DataFlavor objects indicating the flavors the data can be provided in.

[getTransferDataFlavors\(\)](#) - Method in class [java.awt.datatransfer.StringSelection](#)
 Returns an array of flavors in which this Transferable can provide the data.

[getTransferDataFlavors\(\)](#) - Method in class [java.awt.dnd.DropTargetContext.TransferableProxy](#)
 get the flavors

[getTransferSize\(\)](#) - Method in class [java.sql.DataTruncation](#)
 Gets the number of bytes of data actually transferred.

[getTransferType\(\)](#) - Method in class [java.awt.image.SampleModel](#)
 Returns the TransferType used to transfer pixels via the [getDataElements](#) and [setDataElements](#) methods.

[getTransferType\(\)](#) - Method in class [java.awt.image.Raster](#)
 Returns the TransferType used to transfer pixels via the [getDataElements](#) and [setDataElements](#) methods.

[getTransferType\(\)](#) - Method in class [java.awt.image.ColorModel](#)
 Returns the transfer type of this ColorModel.

[getTransferType\(\)](#) - Method in class [java.awt.image.MultiPixelPackedSampleModel](#)
 Returns the TransferType used to transfer pixels by way of the [getDataElements](#) and [setDataElements](#) methods.

[getTransform\(\)](#) - Method in class [java.awt.Graphics2D](#)
 Returns a copy of the current Transform in the Graphics2D context.

[getTransform\(\)](#) - Method in class [java.awt.Font](#)
 Returns a copy of the transform associated with this Font.

[getTransform\(\)](#) - Method in class [java.awt.font.TransformAttribute](#)
 Returns a copy of the wrapped transform.

[getTransform\(\)](#) - Method in class [java.awt.font.FontRenderContext](#)
 Gets the transform that is used to scale typographical points to pixels in this FontRenderContext.

[getTransform\(\)](#) - Method in class [java.awt.image.AffineTransformOp](#)
 Returns the affine transform used by this transform operation.

[getTransform\(\)](#) - Method in class [java.awt.image.renderable.RenderContext](#)
 Gets the current user-to-device AffineTransform.

[getTranslateInstance\(double, double\)](#) - Static method in class [java.awt.geom.AffineTransform](#)
 Returns a transform representing a translation transformation.

[getTranslateX\(\)](#) - Method in class [java.awt.geom.AffineTransform](#)
 Returns the X coordinate of the translation element (m02) of the 3x3 affine transformation matrix.

[getTranslateY\(\)](#) - Method in class [java.awt.geom.AffineTransform](#)
 Returns the Y coordinate of the translation element (m12) of the 3x3 affine transformation matrix.

[getTransmitter\(\)](#) - Static method in class [javax.sound.midi.MidiSystem](#)
 Obtains a MIDI transmitter from an external MIDI port or other default source.

[getTransmitter\(\)](#) - Method in interface [javax.sound.midi.MidiDevice](#)
 Obtains a MIDI OUT connection from which the MIDI device will transmit MIDI data The returned transmitter must be closed when the application has finished using it.

[getTransparency\(\)](#) - Method in class [java.awt.TexturePaint](#)
 Returns the transparency mode for this TexturePaint.

[getTransparency\(\)](#) - Method in interface [java.awt.Transparency](#)

Returns the type of this Transparency.

getTransparency() - Method in class java.awt.GradientPaint
Returns the transparency mode for this GradientPaint.

getTransparency() - Method in class java.awt.Color
Returns the transparency mode for this Color.

getTransparency() - Method in class java.awt.image.ColorModel
Returns the transparency.

getTransparency() - Method in class java.awt.image.IndexColorModel
Returns the transparency.

getTransparentPixel() - Method in class java.awt.image.IndexColorModel
Returns the index of the transparent pixel in this IndexColorModel or -1 if there is no transparent pixel.

getTRC() - Method in class java.awt.color.ICC_ProfileGray
Returns the TRC as an array of shorts.

getTRC(int) - Method in class java.awt.color.ICC_ProfileRGB
Returns the TRC for a particular component as an array of shorts.

getTreeCellEditorComponent(JTree, Object, boolean, boolean, boolean, int) - Method in class javax.swing.DefaultCellEditor

getTreeCellEditorComponent(JTree, Object, boolean, boolean, boolean, boolean, int) - Method in interface javax.swing.tree.TreeCellEditor
Sets an initial *value* for the editor.

getTreeCellEditorComponent(JTree, Object, boolean, boolean, boolean, boolean, int) - Method in class javax.swing.tree.DefaultTreeCellEditor
Configures the editor.

getTreeCellRendererComponent(JTree, Object, boolean, boolean, boolean, int, boolean) - Method in class javax.swing.tree.DefaultTreeCellRenderer
Configures the renderer based on the passed in components.

getTreeCellRendererComponent(JTree, Object, boolean, boolean, boolean, int, boolean) - Method in interface javax.swing.tree.TreeCellRenderer
Sets the value of the current tree cell to value.

getTreeComputerIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeControlIcon(boolean) - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeFloppyDriveIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeFolderIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeHardDriveIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeLeafIcon() - Static method in class javax.swing.plaf.metal.MetalIconFactory

getTreeLock() - Method in class java.awt.Component
Gets the locking object for AWT component-tree and layout Gets this component's locking object (the object that owns the thread synchronization monitor) for AWT component-tree and layout operations.

getTreeLock() - Method in class java.awt.MenuComponent
Gets this component's locking object (the object that owns the thread synchronization monitor) for AWT component-tree and layout operations.

getTreePath() - Method in class javax.swing.event.TreeModelEvent
For all events, except treeStructureChanged, returns the parent of the changed nodes.

getTrigger() - Method in class java.awt.dnd.DragSourceContext
This method returns the DragGestureEvent that initially triggered the drag.

getTriggerEvent() - Method in class java.awt.dnd.DragGestureRecognizer
This method returns the first event in the series of events that initiated the Drag and Drop operation.

getTriggerEvent() - Method in class java.awt.dnd.DragGestureEvent

This method returns the initial event that triggered the gesture.

getTTL() - Method in class java.net.MulticastSocket

Deprecated. *use the getTimeToLive method instead, which returns an int instead of a byte.*

getTTL() - Method in class java.net.DatagramSocketImpl

Deprecated. *use getTimeToLive instead.*

getType() - Method in class java.awt.GraphicsDevice

Returns the type of this GraphicsDevice.

getType() - Method in class java.awt.Cursor

Returns the type for this cursor.

getType() - Method in class java.awt.color.ColorSpace

Returns the color space type of this ColorSpace (for example TYPE_RGB, TYPE_XYZ, ...).

getType() - Method in class java.awt.font.GlyphMetrics

Returns the raw glyph type code.

getType() - Method in class java.awt.geom.AffineTransform

Retrieves the flag bits describing the conversion properties of this transform.

getType() - Method in class java.awt.image.BufferedImage

Returns the image type.

getType() - Method in class java.io.ObjectStreamField

Get the type of the field.

getType() - Method in class java.lang.reflect.Field

Returns a Class object that identifies the declared type for the field represented by this Field object.

getType() - Method in class java.security.KeyStore

Returns the type of this keystore.

getType() - Method in class java.security.cert.CertificateFactory

Returns the name of the certificate type associated with this certificate factory.

getType() - Method in class java.security.cert.Certificate

Returns the type of this certificate.

getType() - Method in class java.security.cert.CRL

Returns the type of this CRL.

getType() - Method in interface java.sql.ResultSet

Returns the type of this ResultSet object.

getType() - Method in interface javax.accessibility.AccessibleTableModelChange

Returns the type of event

getType() - Method in class javax.sound.sampled.Control

Obtains the control's type.

getType() - Method in class javax.sound.sampled.AudioFileFormat

Obtains the audio file type, such as WAVE or AU.

getType() - Method in class javax.sound.sampled.LineEvent

Obtains the event's type.

getType() - Method in class javax.sound.midi.MetaMessage

Obtains the type of the MetaMessage.

getType() - Method in class javax.sound.midi.MidiFileFormat

Obtains the MIDI file type.

getType() - Method in class javax.naming.RefAddr

Retrieves the address type of this address.

getType() - Method in class javax.naming.event.NamingEvent

Returns the type of this event.

getType() - Method in class javax.swing.JTable.AccessibleJTable.AccessibleJTableModelChange

getType() - Method in interface javax.swing.event.DocumentEvent

Gets the type of event.

getType() - Method in class javax.swing.event.TableModelEvent

Returns the type of event - one of: INSERT, UPDATE and DELETE.

getType() - Method in class javax.swing.event.ListDataEvent

Returns the event type.

getType() - Method in class [javax.swing.text.AbstractDocument.DefaultDocumentEvent](#)
Returns the type of event.

getType() - Method in class [javax.swing.text.DefaultStyledDocument.ElementSpec](#)
Gets the element type.

getType() - Method in class [javax.swing.text.html.parser.AttributeList](#)

getType() - Method in class [javax.swing.text.html.parser.Element](#)
Get type.

getType() - Method in class [javax.swing.text.html.parser.Entity](#)
Get the type of the entity.

getType(char) - Static method in class [java.lang.Character](#)
Returns a value indicating a character category.

getTypeCode() - Method in class [java.io.ObjectStreamField](#)
Returns character encoding of field type.

getTypeDescription(File) - Method in class [javax.swing.JFileChooser](#)
Returns the file type.

getTypeDescription(File) - Method in class [javax.swing.filechooser.FileView](#)
A human readable description of the type of the file.

getTypeDescription(File) - Method in class [javax.swing.plaf.basic.BasicFileChooserUI.BasicFileView](#)

getTypeInfo() - Method in interface [java.sql.DatabaseMetaData](#)
Gets a description of all the standard SQL types supported by this database.

getTypeMap() - Method in interface [java.sql.Connection](#)
Gets the type map object associated with this connection.

getTypeString() - Method in class [java.io.ObjectStreamField](#)
Return the JVM type signature.

getUDTs(String, String, String, int[]) - Method in interface [java.sql.DatabaseMetaData](#)
Gets a description of the user-defined types defined in a particular schema.

getUI() - Method in class [javax.swing.JViewport](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JTabbedPane](#)
Returns the UI object which implements the L&F for this component.

getUI() - Method in class [javax.swing.AbstractButton](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JOptionPane](#)
Returns the UI object which implements the L&F for this component.

getUI() - Method in class [javax.swing.JColorChooser](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JPopupMenu](#)
Returns the look and feel (L&F) object that renders this component.

getUI() - Method in class [javax.swing.JSeparator](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JComboBox](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JList](#)
Returns the look and feel (L&F) object that renders this component.

getUI() - Method in class [javax.swing.JToolTip](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JInternalFrame](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JInternalFrame.JDesktopIcon](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JSplitPane](#)
Returns the SplitPaneUI that is providing the current look and feel.

getUI() - Method in class [javax.swing.JTree](#)
Returns the L&F object that renders this component.

getUI() - Method in class [javax.swing.JTable](#)

Returns the L&F object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JLabel`
Returns the L&F object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JFileChooser`
Gets the UI object which implements the L&F for this component.

[getUI\(\)](#) - Method in class `javax.swing.JDesktopPane`
Returns the L&F object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JToolBar`
Returns the toolbar's current UI.

[getUI\(\)](#) - Method in class `javax.swing.JMenuBar`
Returns the menubar's current UI.

[getUI\(\)](#) - Method in class `javax.swing.JScrollPane`
Returns the look and feel (L&F) object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JScrollBar`
Returns the delegate that implements the look and feel for this component.

[getUI\(\)](#) - Method in class `javax.swing.JProgressBar`
Returns the L&F object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JRootPane`
Returns the L&F object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.JSlider`
Gets the UI object which implements the L&F for this component.

[getUI\(\)](#) - Method in class `javax.swing.table.JTableHeader`
Returns the look and feel (L&F) object that renders this component.

[getUI\(\)](#) - Method in class `javax.swing.text.JTextComponent`
Fetches the user-interface factory for this text-oriented editor.

[getUI\(JComponent\)](#) - Method in class `javax.swing.UIManager`
Creates an ComponentUI implementation for the specified component.

[getUI\(JComponent\)](#) - Static method in class `javax.swing.UIManager`
Returns the L&F object that renders the target component.

[getUIActionMap\(JComponent\)](#) - Static method in class `javax.swing.SwingUtilities`
Returns the ActionMap provided by the UI in component component.

[getUIClass\(String\)](#) - Method in class `javax.swing.UIManager`
Returns the L&F class that renders this component.

[getUIClass\(String, ClassLoader\)](#) - Method in class `javax.swing.UIManager`
The value of `get(uidClassID)` must be the String name of a class that implements the corresponding ComponentUI class.

[getUIClassID\(\)](#) - Method in class `javax.swing.JComponent`
Returns the UIManager key used to look up the name of the swing.plaf.ComponentUI class that defines the look and feel for this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JEditorPane`
Gets the class ID for the UI.

[getUIClassID\(\)](#) - Method in class `javax.swing.JTextPane`
Returns the class ID for the UI.

[getUIClassID\(\)](#) - Method in class `javax.swing.JViewport`
Returns a string that specifies the name of the L&F class that renders this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JTabbedPane`
Returns the name of the UI class that implements the L&F for this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JMenuItem`
Returns the name of the L&F class that renders this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JCheckBoxMenuItem`
Returns the name of the L&F class that renders this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JToggleButton`
Returns a string that specifies the name of the l&f class that renders this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JCheckBox`
Returns a string that specifies the name of the L&F class that renders this component.

[getUIClassID\(\)](#) - Method in class `javax.swing.JTextField`
Gets the class ID for a UI.

getUIClassID() - Method in class javax.swing.JPasswordField
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JOptionPane
Returns the name of the UI class that implements the L&F for this component.

getUIClassID() - Method in class javax.swing.JMenu
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JColorChooser
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JButton
Returns a string that specifies the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JPopupMenu
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JSeparator
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JPopupMenu.Separator
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JComboBox
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JList
Returns the suffix used to construct the name of the look and feel (L&F) class used to render this component.

getUIClassID() - Method in class javax.swing.JToolTip
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JInternalFrame
Returns the name of the L&F class which renders this component.

getUIClassID() - Method in class javax.swing.JInternalFrame.JDesktopIcon
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JPanel
Returns a string that specifies the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JSplitPane
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JTree
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JTable
Returns the suffix used to construct the name of the L&F class used to render this component.

getUIClassID() - Method in class javax.swing.JLabel
Returns a string that specifies the name of the l&f class that renders this component.

getUIClassID() - Method in class javax.swing.JFileChooser
Returns a string that specifies the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JDesktopPane
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JRadioButton
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JToolBar
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JToolBar.Separator
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JMenuBar
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JRadioButtonMenuItem
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class javax.swing.JTextArea
Returns the class ID for the UI.

getUIClassID() - Method in class javax.swing.JScrollPane
Returns the suffix used to construct the name of the L&F class used to render this component.

getUIClassID() - Method in class javax.swing.ScrollBar
Returns the name of the LookAndFeel class for this component.

getUIClassID() - Method in class `javax.swing.JProgressBar`
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class `javax.swing.JRootPane`
Returns a string that specifies the name of the l&f class that renders this component.

getUIClassID() - Method in class `javax.swing.JSlider`
Returns the name of the L&F class that renders this component.

getUIClassID() - Method in class `javax.swing.table.JTableHeader`
Returns the suffix used to construct the name of the look and feel (L&F) class used to render this component.

getUIError(String) - Method in class `javax.swing.UIDefaults`
If `getUI()` fails for any reason, it calls this method before returning null.

getUIInputMap(JComponent, int) - Static method in class `javax.swing.SwingUtilities`
Returns the InputMap provided by the UI for condition condition in component component.

getUIs() - Method in class `javax.swing.plaf.multi.MultiListUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiSeparatorUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiLabelUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiPopupMenuUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiPanelUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiScrollbarUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiTextUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiComboBoxUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiTableHeaderUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiFileChooserUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiColorChooserUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiTreeUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiViewportUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiTabbedPaneUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiProgressBarUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiScrollPaneUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiOptionPaneUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiSplitPaneUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiButtonUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiToolBarUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiSliderUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class `javax.swing.plaf.multi.MultiDesktopPaneUI`
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiTableUI
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiDesktopIconUI
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiMenuItemUI
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiInternalFrameUI
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiToolTipUI
Return the list of UI's associated with this multiplexing UI.

getUIs() - Method in class javax.swing.plaf.multi.MultiMenuBarUI
Return the list of UI's associated with this multiplexing UI.

getUndeclaredThrowable() - Method in class java.lang.reflect.UndeclaredThrowableException
Returns the Throwable instance wrapped in this UndeclaredThrowableException.

getUnderlineOffset() - Method in class java.awt.font.LineMetrics
Returns the position of the underline relative to the baseline.

getUnderlineThickness() - Method in class java.awt.font.LineMetrics
Returns the thickness of the underline.

getUndoOrRedoPresentationName() - Method in class javax.swing.undo.UndoManager
Return the appropriate name for a command that toggles between undo and redo.

getUndoPresentationName() - Method in class javax.swing.text.AbstractDocument.DefaultDocumentEvent
Provides a localized, human readable description of the undoable form of this edit, e.g.

getUndoPresentationName() - Method in class javax.swing.undo.AbstractUndoableEdit
If getPresentationName() returns "", returns AbstractUndoableEdit.UndoName.

getUndoPresentationName() - Method in class javax.swing.undo.CompoundEdit
Returns getUndoPresentationName from the last UndoableEdit added to edits.

getUndoPresentationName() - Method in class javax.swing.undo.UndoManager
If inProgress, returns getUndoPresentationName of the significant edit that will be undone when undo() is invoked.

getUndoPresentationName() - Method in interface javax.swing.undo.UndoableEdit
Provide a localized, human readable description of the undoable form of this edit, e.g.

getUnexecutedModifications() - Method in class javax.naming.directory.AttributeModificationException
Retrieves the unexecuted modification list.

getUnicodeStream(int) - Method in interface java.sql.ResultSet
Deprecated. *use getCharacterStream in place of getUnicodeStream*

getUnicodeStream(String) - Method in interface java.sql.ResultSet
Deprecated.

getUnitIncrement() - Method in class java.awt.Scrollbar
Gets the unit increment for this scrollbar.

getUnitIncrement() - Method in interface java.awt.Adjustable
Gets the unit value increment for the adjustable object.

getUnitIncrement() - Method in class javax.swing.JScrollbar
For backwards compatibility with java.awt.Scrollbar.

getUnitIncrement(int) - Method in class javax.swing.JScrollbar
Returns the amount to change the scrollbar's value by, given a unit up/down request.

getUnitIncrement(int) - Method in class javax.swing.JScrollPane.ScrollBar
Computes the unit increment for scrolling if the viewport's view is a Scrollable object.

getUnits() - Method in class javax.sound.sampled.FloatControl
Obtains the label for the units in which the control's values are expressed, such as "dB" or "frames per second."

getUnnormalizedComponents(float[], int, int[], int) - Method in class java.awt.image.ColorModel
Returns an array of all of the color/alpha components in unnormalized form, given a normalized component array.

getUpdateAction() - Method in class javax.swing.plaf.basic.BasicFileChooserUI

getUpdateCount() - Method in interface java.sql.Statement
Returns the current result as an update count; if the result is a ResultSet object or there

are no more results, -1 is returned.

[getUpdateCounts\(\)](#) - Method in class [java.sql.BatchUpdateException](#)
Retrieves the update count for each update statement in the batch update that executed successfully before this exception occurred.

[getUpdateLevel\(\)](#) - Method in class [javax.swing.undo.UndoableEditSupport](#)
Returns the update level value.

[getUpdatePeriod\(\)](#) - Method in class [javax.sound.sampled.FloatControl](#)
Obtains the smallest time interval, in microseconds, over which the control's value can change during a shift.

[getUpdateRect\(\)](#) - Method in class [java.awt.event.PaintEvent](#)
Returns the rectangle representing the area which needs to be repainted in response to this event.

[getUpdateTableInRealTime\(\)](#) - Method in class [javax.swing.table.JTableHeader](#)
Obsolete as of Java 2 platform v1.3.

[getURL\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of this URLConnection's URL field.

[getURL\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
What's the url for this database?

[getURL\(\)](#) - Method in class [javax.swing.event.HyperlinkEvent](#)
Gets the URL that the link refers to.

[getURLContext\(String, Hashtable\)](#) - Static method in class [javax.naming.spi.NamingManager](#)
Creates a context for the given URL scheme id.

[getURLorDefaultInitCtx\(Name\)](#) - Method in class [javax.naming.InitialContext](#)
Retrieves a context for resolving name.

[getURLorDefaultInitCtx\(String\)](#) - Method in class [javax.naming.InitialContext](#)
Retrieves a context for resolving the string name name.

[getURLs\(\)](#) - Method in class [java.net.URLClassLoader](#)
Returns the search path of URLs for loading classes and resources.

[getUseCaches\(\)](#) - Method in class [java.net.URLConnection](#)
Returns the value of this URLConnection's useCaches field.

[getUserAction\(\)](#) - Method in class [java.awt.dnd.DragSourceDragEvent](#)
This method returns an int representing the user's currently selected drop action.

[getUserInfo\(\)](#) - Method in class [java.net.URL](#)
Returns the userInfo part of this URL.

[.getUserName\(\)](#) - Method in class [java.awt.print.PrinterJob](#)
Gets the name of the printing user.

[.getUserName\(\)](#) - Method in class [java.net.PasswordAuthentication](#)
Returns the user name.

[.getUserName\(\)](#) - Method in interface [java.sql.DatabaseMetaData](#)
What's our user name as known to the database?

[getUserObject\(\)](#) - Method in class [javax.swing.tree.DefaultMutableTreeNode](#)
Returns this node's user object.

[getUserObjectPath\(\)](#) - Method in class [javax.swing.tree.DefaultMutableTreeNode](#)
Returns the user object path, from the root, to get to this node.

[getUserTextColor\(\)](#) - Static method in class [javax.swing.plaf.metal.MetalLookAndFeel](#)

[getUserTextColor\(\)](#) - Method in class [javax.swing.plaf.metal.MetalTheme](#)

[getUserTextFont\(\)](#) - Static method in class [javax.swing.plaf.metal.MetalLookAndFeel](#)

[getUserTextFont\(\)](#) - Method in class [javax.swing.plaf.metal.MetalTheme](#)

[getUserTextFont\(\)](#) - Method in class [javax.swing.plaf.metal.DefaultMetalTheme](#)

[getVAdjustable\(\)](#) - Method in class [java.awt.ScrollPane](#)
Returns the Adjustable object which represents the state of the vertical scrollbar.

[getValidPixels\(\)](#) - Method in class [java.awt.image.IndexColorModel](#)

Returns a `BigInteger` that indicates the valid/invalid pixels in the colormap.

`getValue()` - Method in class `java.awt.Scrollbar`
Gets the current value of this scroll bar.

`getValue()` - Method in interface `java.awt.Adjustable`
Gets the current value of the adjustable object.

`getValue()` - Method in class `java.awt.event.AdjustmentEvent`
Returns the current value in the adjustment event.

`getValue()` - Method in interface `java.beans.PropertyEditor`
Gets the property value.

`getValue()` - Method in class `java.beans.PropertyEditorSupport`
Gets the value of the property.

`getValue()` - Method in class `java.rmi.dgc.Lease`
Returns the lease duration.

`getValue()` - Method in class `java.text.Annotation`
Returns the value of the attribute, which may be null.

`getValue()` - Method in interface `java.util.Map.Entry`
Returns the value corresponding to this entry.

`getValue()` - Method in class `java.util.zip.Adler32`
Returns checksum value.

`getValue()` - Method in interface `java.util.zip.Checksum`
Returns the current checksum value.

`getValue()` - Method in class `java.util.zip.CRC32`
Returns CRC-32 value.

`getValue()` - Method in class `javax.sound.sampled.EnumControl`
Obtains this control's current value.

`getValue()` - Method in class `javax.sound.sampled.FloatControl`
Obtains this control's current value.

`getValue()` - Method in class `javax.sound.sampled.BooleanControl`
Obtains this control's current value.

`getValue()` - Method in class `javax.swing.DefaultBoundedRangeModel`
Return the model's current value.

`getValue()` - Method in class `javax.swing.JOptionPane`
Returns the value the user has selected.

`getValue()` - Method in interface `javax.swing.BoundedRangeModel`
Returns the model's current value.

`getValue()` - Method in class `javax.swing.JScrollbar`
Returns the scrollbar's value.

`getValue()` - Method in class `javax.swing.JProgressBar`
Returns the model's current value.

`getValue()` - Method in class `javax.swing.JSlider`
Returns the sliders value.

`getValue()` - Method in class `javax.swing.text.html.Option`
Convenience method to return the string associated with the value attribute.

`getValue()` - Method in class `javax.swing.text.html.parser.AttributeList`

`getValue(Attributes.Name)` - Method in class `java.util.jar.Attributes`
Returns the value of the specified `Attributes.Name`, or null if the attribute was not found.

`getValue(String)` - Method in class `java.beans.FeatureDescriptor`
Retrieve a named attribute with this feature.

`getValue(String)` - Method in class `java.util.jar.Attributes`
Returns the value of the specified attribute name, specified as a string, or null if the attribute was not found.

`getValue(String)` - Method in interface `javax.swing.Action`
Gets one of this object's properties using the associated key.

`getValue(String)` - Method in class `javax.swing.AbstractAction`
Gets the Object associated with the specified key.

`getValueAt(int, int)` - Method in class `javax.swing.JTable`

Returns the cell value at row and column.

getValueAt(int, int) - Method in class javax.swing.table.DefaultTableModel
Returns an attribute value for the cell at row and column.

getValueAt(int, int) - Method in interface javax.swing.table.TableModel
Returns the value for the cell at columnIndex and rowIndex.

getValueIsAdjusting() - Method in class javax.swing.DefaultBoundedRangeModel
Returns true if the value is in the process of changing as a result of actions being taken by the user.

getValueIsAdjusting() - Method in class javax.swing.DefaultListSelectionModel

getValueIsAdjusting() - Method in class javax.swing.JList
Returns the value of the data model's isAdjusting property.

getValueIsAdjusting() - Method in interface javax.swing.ListSelectionModel
Returns true if the value is undergoing a series of changes.

getValueIsAdjusting() - Method in interface javax.swing.BoundedRangeModel
Returns true if the current changes to the value property are part of a series of changes.

getValueIsAdjusting() - Method in class javax.swing.JScrollBar
True if the scrollbar knob is being dragged.

getValueIsAdjusting() - Method in class javax.swing.JSlider
True if the slider knob is being dragged.

getValueIsAdjusting() - Method in class javax.swing.event.ListSelectionEvent
Returns true if this is one of multiple change events.

getValues() - Method in class javax.sound.sampled.EnumControl
Returns the set of possible values for this control.

getValues() - Method in class javax.swing.text.html.parser.AttributeList

getVariant() - Method in class java.util.Locale
Returns the variant code for this locale.

getVariation() - Method in class java.awt.im.InputMethodHighlight
Returns the variation of the text range.

getVendor() - Method in class javax.sound.sampled.Mixer.Info
Obtains the vendor of the mixer.

getVendor() - Method in interface javax.sound.midi.Soundbank
Obtains a string naming the company that provides the sound bank

getVendor() - Method in class javax.sound.midi.MidiDevice.Info
Obtains the name of the company who supplies the device.

getVerifyInputWhenFocusTarget() - Method in class javax.swing.JComponent
Get the value that indicates whether the input verifier for the current focus owner will be called before this component requests focus.

getVersion() - Method in interface java.awt.font.OpenType
Returns the version of the OpenType font.

getVersion() - Method in class java.security.Provider
Returns the version number for this provider.

getVersion() - Method in class java.security.cert.X509Certificate
Gets the version (version number) value from the certificate.

getVersion() - Method in class java.security.cert.X509CRL
Gets the version (version number) value from the CRL.

getVersion() - Method in class javax.sound.sampled.Mixer.Info
Obtains the version of the mixer.

getVersion() - Method in interface javax.sound.midi.Soundbank
Obtains the version string for the sound bank.

getVersion() - Method in class javax.sound.midi.MidiDevice.Info
Obtains the version of the device.

getVersionColumns(String, String, String) - Method in interface java.sql.DatabaseMetaData
Gets a description of a table's columns that are automatically updated when any value in a row is updated.

getVerticalAlignment() - Method in class javax.swing.AbstractButton

Returns the vertical alignment of the text and icon.

getVerticalAlignment() - Method in class `javax.swing.JLabel`

Returns the alignment of the label's contents along the Y axis.

getVerticalLegBuffer() - Method in class `javax.swing.plaf.basic.BasicTreeUI`

The vertical element of legs between nodes starts at the bottom of the parent node by default.

getVerticalScrollBar() - Method in class `javax.swing.ScrollPaneLayout`

Returns the JScrollBar object that handles vertical scrolling.

getVerticalScrollBar() - Method in class `javax.swing.JScrollPane`

Returns the vertical scroll bar that controls the viewports vertical view position.

getVerticalScrollBarPolicy() - Method in class `javax.swing.ScrollPaneLayout`

Returns the vertical scrollbar-display policy.

getVerticalScrollBarPolicy() - Method in class `javax.swing.JScrollPane`

Returns the vertical scroll bar policy value.

getVerticalSliderThumbIcon() - Static method in class `javax.swing.plaf.metal.MetalIconFactory`

getVerticalTextPosition() - Method in class `javax.swing.AbstractButton`

Returns the vertical position of the text relative to the icon.

getVerticalTextPosition() - Method in class `javax.swing.JLabel`

Returns the vertical position of the label's text, relative to its image.

getVgap() - Method in class `java.awt.CardLayout`

Gets the vertical gap between components.

getVgap() - Method in class `java.awt.GridLayout`

Gets the vertical gap between components.

getVgap() - Method in class `java.awt.BorderLayout`

Returns the vertical gap between components.

getVgap() - Method in class `java.awt.FlowLayout`

Gets the vertical gap between components.

getView() - Method in class `javax.swing.JViewport`

Returns the JViewports one child or null.

getView(int) - Method in class `javax.swing.text.View`

Gets the nth child view.

getView(int) - Method in class `javax.swing.text.CompositeView`

Gets the n-th view in this container.

getView(int) - Method in class `javax.swing.text.AsyncBoxView`

Gets the nth child view.

getViewAtPoint(int, int, Rectangle) - Method in class `javax.swing.text.CompositeView`

Fetches the child view at the given point.

getViewAtPoint(int, int, Rectangle) - Method in class `javax.swing.text.BoxView`

Fetches the child view at the given point.

getViewAtPosition(int, Rectangle) - Method in class `javax.swing.text.CompositeView`

Fetches the child view that represents the given position in the model.

getViewAtPosition(int, Rectangle) - Method in class `javax.swing.text.TableView`

Fetches the child view that represents the given position in the model.

getViewAtPosition(int, Rectangle) - Method in class `javax.swing.text.TableView.TableRow`

Fetches the child view that represents the given position in the model.

getViewAttributes(View) - Method in class `javax.swing.text.html.StyleSheet`

Fetches a set of attributes to use in the view for displaying.

getViewCount() - Method in class `javax.swing.text.View`

Returns the number of views in this view.

getViewCount() - Method in class `javax.swing.text.CompositeView`

Returns the number of child views of this view.

getViewCount() - Method in class `javax.swing.text.AsyncBoxView`

Returns the number of views in this view.

getViewFactory() - Method in class `javax.swing.text.View`

Fetches the ViewFactory implementation that is feeding the view hierarchy.

getViewFactory() - Method in class `javax.swing.text.EditorKit`

Fetches a factory that is suitable for producing views of any models that are produced by this

kit.

getViewFactory() - Method in class javax.swing.text.DefaultEditorKit
Fetches a factory that is suitable for producing views of any models that are produced by this kit.

getViewFactory() - Method in class javax.swing.text.StyledEditorKit
Fetches a factory that is suitable for producing views of any models that are produced by this kit.

getViewFactory() - Method in class javax.swing.text.html.HTMLEditorKit
Fetch a factory that is suitable for producing views of any models that are produced by this kit.

getViewIndex(int, Position.Bias) - Method in class javax.swing.text.View
Returns the child view index representing the given position in the model.

getViewIndex(int, Position.Bias) - Method in class javax.swing.text.CompositeView
Returns the child view index representing the given position in the model.

getViewIndex(int, Position.Bias) - Method in class javax.swing.text.AsyncBoxView
Returns the child view index representing the given position in the model.

getViewIndexAtPoint(float, float, Shape) - Method in class javax.swing.text.AsyncBoxView.ChildLocator
Fetches the child view index at the given point.

getViewIndexAtPosition(int) - Method in class javax.swing.text.CompositeView
Fetches the child view index representing the given position in the model.

getViewIndexAtPosition(int) - Method in class javax.swing.text.FlowView
Fetches the child view index representing the given position in the model.

getViewIndexAtPosition(int) - Method in class javax.swing.text.ZoneView
Fetches the child view index representing the given position in the model.

getViewIndexAtPosition(int, Position.Bias) - Method in class javax.swing.text.AsyncBoxView
Fetches the child view index representing the given position in the model.

getViewIndexAtVisualOffset(float) - Method in class javax.swing.text.AsyncBoxView.ChildLocator
Locate the view responsible for an offset into the box along the major axis.

getViewport() - Method in class javax.swing.ScrollPaneLayout
Returns the JViewport object that displays the scrollable contents.

getViewport() - Method in class javax.swing.JScrollPane
Returns the current JViewport.

getViewportBorder() - Method in class javax.swing.JScrollPane
Returns the Border object that surrounds the viewport.

getViewportBorderBounds() - Method in class javax.swing.JScrollPane
Returns the bounds of the viewport's border.

getViewportBorderBounds(JScrollPane) - Method in class javax.swing.ScrollPaneLayout
Deprecated. *As of JDK version Swing 1.1 replaced by JScrollPane.getViewportBorderBounds().*

getViewportSize() - Method in class java.awt.ScrollPane
Returns the current size of the scroll pane's view port.

getViewPosition() - Method in class javax.swing.JViewport
Returns the view coordinates that appear in the upper left hand corner of the viewport, or 0,0 if there's no view.

getViewRect() - Method in class javax.swing.JViewport
Returns a rectangle whose origin is getViewPosition and size is getExtentSize.

getViewSize() - Method in class javax.swing.JViewport
If the view's size hasn't been explicitly set, return the preferred size, otherwise return the view's current size.

getVisible() - Method in class java.awt.Scrollbar
Deprecated. *As of JDK version 1.1, replaced by getVisibleAmount().*

getVisibleAdvance() - Method in class java.awt.font.TextLayout
Returns the advance of this TextLayout, minus trailing whitespace.

getVisibleAmount() - Method in class java.awt.Scrollbar
Gets the visible amount of this scroll bar.

getVisibleAmount() - Method in interface java.awt.Adjustable
Gets the length of the proportional indicator.

getVisibleAmount() - Method in class `javax.swing.JScrollBar`
Returns the scrollbar's extent, aka its "visibleAmount".

getVisibleChildCount(TreePath) - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns the number of visible children for row.

getVisibleChildCount(TreePath) - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns the number of visible children for row.

getVisibleChildCount(TreePath) - Method in class `javax.swing.tree.FixedHeightLayoutCache`
Returns the number of visible children for row.

getVisibleComponent() - Method in class `javax.swing.plaf.basic.BasicTabbedPaneUI`

getVisibleEditorRect() - Method in class `javax.swing.plaf.basic.BasicTextUI`
Gets the allocation to give the root View.

getVisibleIndex() - Method in class `java.awt.List`
Gets the index of the item that was last made visible by the method `makeVisible`.

getVisiblePathsFrom(TreePath) - Method in class `javax.swing.tree.AbstractLayoutCache`
Returns an Enumerator that increments over the visible paths starting at the passed in location.

getVisiblePathsFrom(TreePath) - Method in class `javax.swing.tree.VariableHeightLayoutCache`
Returns an Enumerator that increments over the visible paths starting at the passed in location.

getVisiblePathsFrom(TreePath) - Method in class `javax.swing.tree.FixedHeightLayoutCache`
Returns an Enumerator that increments over the visible paths starting at the passed in location.

getVisiblePosition() - Method in class `java.awt.event.InputMethodEvent`
Gets the position that's most important to be visible.

getVisibleRect() - Method in class `javax.swing.JComponent`
Returns the Component's "visible rectangle" - the intersection of this component's visible rectangle:

getVisibleRowCount() - Method in class `javax.swing.JList`
Returns the preferred number of visible rows.

getVisibleRowCount() - Method in class `javax.swing.JTree`
Returns the number of rows that are displayed in the display area.

getVisualBounds() - Method in class `java.awt.font.GlyphVector`
Returns the visual bounds of this GlyphVector The visual bounds is the tightest rectangle enclosing all non-background pixels in the rendered representation of this GlyphVector.

getVisualHighlightShape(TextHitInfo, TextHitInfo) - Method in class `java.awt.font.TextLayout`
Returns a Shape enclosing the visual selection in the specified range, extended to the bounds.

getVisualHighlightShape(TextHitInfo, TextHitInfo, Rectangle2D) - Method in class `java.awt.font.TextLayout`
Returns a path enclosing the visual selection in the specified range, extended to bounds.

getVisualOtherHit(TextHitInfo) - Method in class `java.awt.font.TextLayout`
Returns the hit on the opposite side of the specified hit's caret.

getVMID() - Method in class `java.rmi.dgc.Lease`
Returns the client VMID associated with the lease.

getVoiceStatus() - Method in interface `javax.sound.midi.Synthesizer`
Obtains the current status of the voices produced by this synthesizer.

getVScrollbarWidth() - Method in class `java.awt.ScrollPane`
Returns the width that would be occupied by a vertical scrollbar, which is independent of whether it is currently displayed by the scroll pane or not.

getWantsInput() - Method in class `javax.swing.JOptionPane`
Returns true if a parentComponent will be provided for the user to input.

getWarnings() - Method in interface `java.sql.Statement`
Retrieves the first warning reported by calls on this Statement object.

getWarnings() - Method in interface `java.sql.Connection`
Returns the first warning reported by calls on this Connection.

getWarnings() - Method in interface `java.sql.ResultSet`
Returns the first warning reported by calls on this ResultSet object.

getWarningString() - Method in class java.awt.Window
Gets the warning string that is displayed with this window.

getWarningString() - Method in class javax.swing.JInternalFrame
Gets the warning string that is displayed with this window.

getWeekdays() - Method in class java.text.DateFormatSymbols
Gets weekday strings.

getWestPane() - Method in class javax.swing.plaf.basic.BasicInternalFrameUI

getWhen() - Method in class java.awt.event.InputEvent
Returns the timestamp of when this event occurred.

getWhite() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWhite() - Method in class javax.swing.plaf.metal.MetalTheme

getWidth() - Method in class java.awt.Component
Return the current width of this component.

getWidth() - Method in class java.awt.Dimension
Returns the width of this dimension in double precision.

getWidth() - Method in class java.awt.Rectangle
Returns the width of the bounding Rectangle in double precision.

getWidth() - Method in class java.awt.geom.Dimension2D
Returns the width of this Dimension in double precision.

getWidth() - Method in class java.awt.geom.RectangularShape
Returns the width of the framing rectangle in double precision.

getWidth() - Method in class java.awt.geom.RoundRectangle2D.Float
Returns the width of this RoundRectangle2D in double precision.

getWidth() - Method in class java.awt.geom.RoundRectangle2D.Double
Returns the width of this RoundRectangle2D in double precision.

getWidth() - Method in class java.awt.geom.Rectangle2D.Float
Returns the width of this Rectangle2D in double precision.

getWidth() - Method in class java.awt.geom.Rectangle2D.Double
Returns the width of this Rectangle2D in double precision.

getWidth() - Method in class java.awt.geom.Arc2D.Float
Returns the width of the ellipse of which this arc is a partial section

getWidth() - Method in class java.awt.geom.Arc2D.Double
Returns the width of the ellipse of which this arc is a partial section

getWidth() - Method in class java.awt.geom.Ellipse2D.Float
Returns the overall width of this Ellipse2D in double precision.

getWidth() - Method in class java.awt.geom.Ellipse2D.Double
Returns the overall width of this Ellipse2D in double precision.

getWidth() - Method in class java.awt.image.SampleModel
Returns the width in pixels.

getWidth() - Method in class java.awt.image.Kernel
Returns the width of this Kernel.

getWidth() - Method in class java.awt.image.PixelGrabber
Get the width of the pixel buffer (after adjusting for image width).

getWidth() - Method in interface java.awt.image.RenderedImage
Returns the width of the RenderedImage.

getWidth() - Method in class java.awt.image.BufferedImage
Returns the width of the BufferedImage.

getWidth() - Method in class java.awt.image.Raster
Returns the width in pixels of the Raster.

getWidth() - Method in class java.awt.image.renderable.RenderableImageOp
Gets the width in user coordinate space.

getWidth() - Method in interface java.awt.image.renderable.RenderableImage
Gets the width in user coordinate space.

getWidth() - Method in class java.awt.print.Paper

Returns the width of the page in 1/72nds of an inch.
getWidth() - Method in class java.awt.print.PageFormat
 Returns the width, in 1/72nds of an inch, of the page.
getWidth() - Method in class javax.swing.JComponent
 Returns the current width of this component.
getWidth() - Method in class javax.swing.table.TableColumn
 Returns the width of the TableColumn.
getWidth() - Method in class javax.swing.text.BoxView
 The current width of the box.
getWidth(ImageObserver) - Method in class java.awt.Image
 Determines the width of the image.
getWidth(ImageObserver) - Method in class java.awt.image.BufferedImage
 Returns the actual width of the image.
getWidthOfHighValueLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getWidthOfLowValueLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getWidthOfWidestLabel() - Method in class javax.swing.plaf.basic.BasicSliderUI

getWidths() - Method in class java.awt.FontMetrics
 Gets the advance widths of the first 256 characters in the Font.
getWindingRule() - Method in interface java.awt.geom.PathIterator
 Returns the winding rule for determining the interior of the path.
getWindingRule() - Method in class java.awt.geom.GeneralPath
 Returns the fill style winding rule.
getWindingRule() - Method in class java.awt.geom.FlatteningPathIterator
 Returns the winding rule for determining the interior of the path.
getWindow() - Method in class java.awt.event.WindowEvent
 Returns the originator of the event.
getWindowAncestor(Component) - Static method in class javax.swing.SwingUtilities

getWindowBackground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowBackground() - Method in class javax.swing.plaf.metal.MetalTheme

getWindowTitleBackground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowTitleBackground() - Method in class javax.swing.plaf.metal.MetalTheme

getWindowTitleFont() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowTitleFont() - Method in class javax.swing.plaf.metal.MetalTheme

getWindowTitleFont() - Method in class javax.swing.plaf.metal.DefaultMetalTheme

getWindowTitleForeground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowTitleForeground() - Method in class javax.swing.plaf.metal.MetalTheme

getWindowTitleInactiveBackground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowTitleInactiveBackground() - Method in class javax.swing.plaf.metal.MetalTheme

getWindowTitleInactiveForeground() - Static method in class javax.swing.plaf.metal.MetalLookAndFeel

getWindowTitleInactiveForeground() - Method in class javax.swing.plaf.metal.MetalTheme

getWordEnd(JTextComponent, int) - Static method in class javax.swing.text.Utilities
Determines the end of a word for the given location.

getWordInstance() - Static method in class java.text.BreakIterator
Create BreakIterator for word-breaks using default locale.

getWordInstance(Locale) - Static method in class java.text.BreakIterator
Create BreakIterator for word-breaks using specified locale.

getWordStart(JTextComponent, int) - Static method in class javax.swing.text.Utilities
Determines the start of a word for the given model location.

getWrapStyleWord() - Method in class javax.swing.JTextArea
Get the style of wrapping used if the text area is wrapping lines.

getWritableParent() - Method in class java.awt.image.WritableRaster
Returns the parent WritableRaster (if any) of this WritableRaster, or else null.

getWritableTile(int, int) - Method in class java.awt.image.BufferedImage
Checks out a tile for writing.

getWritableTile(int, int) - Method in interface java.awt.image.WritableRenderedImage
Checks out a tile for writing.

getWritableTileIndices() - Method in class java.awt.image.BufferedImage
Returns an array of Point objects indicating which tiles are checked out for writing.

getWritableTileIndices() - Method in interface java.awt.image.WritableRenderedImage
Returns an array of Point objects indicating which tiles are checked out for writing.

getWriteMethod() - Method in class java.beans.PropertyDescriptor
Gets the method that should be used to write the property value.

getWriter() - Method in class javax.swing.text.AbstractWriter
Returns the Writer that is used to output the content.

getX() - Method in class java.awt.Component
Return the current x coordinate of the components origin.

getX() - Method in class java.awt.Point
Returns the X coordinate of the point in double precision.

getX() - Method in class java.awt.Rectangle
Returns the X coordinate of the bounding Rectangle in double precision.

getX() - Method in class java.awt.event.MouseEvent
Returns the horizontal x position of the event relative to the source component.

getX() - Method in class java.awt.geom.Point2D
Returns the X coordinate of this Point2D in double precision.

getX() - Method in class java.awt.geom.RectangularShape
Returns the X coordinate of the upper left corner of the framing rectangle in double precision.

getX() - Method in class java.awt.geom.RoundRectangle2D.Float
Returns the X coordinate of this RoundRectangle2D in double precision.

getX() - Method in class java.awt.geom.RoundRectangle2D.Double
Returns the X coordinate of this RoundRectangle2D in double precision.

getX() - Method in class java.awt.geom.Rectangle2D.Float
Returns the X coordinate of this Rectangle2D in double precision.

getX() - Method in class java.awt.geom.Rectangle2D.Double
Returns the X coordinate of this Rectangle2D in double precision.

getX() - Method in class java.awt.geom.Point2D.Float
Returns the X coordinate of this Point2D in double precision.

getX() - Method in class java.awt.geom.Point2D.Double
Returns the X coordinate of this Point2D in double precision.

getX() - Method in class java.awt.geom.Arc2D.Float
Returns the x coordinate of the upper left corner of the arc.

getX() - Method in class java.awt.geom.Arc2D.Double
Returns the x coordinate of the upper left corner of the arc.

getX() - Method in class java.awt.geom.Ellipse2D.Float
Returns the X coordinate of the upper left corner of this Ellipse2D in double precision.

getX() - Method in class java.awt.geom.Ellipse2D.Double
Returns the X coordinate of the upper left corner of this Ellipse2D in double precision.

getX() - Method in interface [java.security.interfaces.DSAPrivateKey](#)
Returns the value of the private key, x.

getX() - Method in class [java.security.spec.DSAPrivateKeySpec](#)
Returns the private key x.

getX() - Method in class [javax.swing.JComponent](#)
Returns the current x coordinate of the component's origin.

getX1() - Method in class [java.awt.geom.Line2D](#)
Returns the X coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.Line2D.Float](#)
Returns the X coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.Line2D.Double](#)
Returns the X coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.QuadCurve2D](#)
Returns the x coordinate of the start point in double in precision.

getX1() - Method in class [java.awt.geom.QuadCurve2D.Float](#)
Returns the x coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.QuadCurve2D.Double](#)
Returns the x coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.CubicCurve2D](#)
Returns the X coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.CubicCurve2D.Float](#)
Returns the X coordinate of the start point in double precision.

getX1() - Method in class [java.awt.geom.CubicCurve2D.Double](#)
Returns the X coordinate of the start point in double precision.

getX2() - Method in class [java.awt.geom.Line2D](#)
Returns the X coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.Line2D.Float](#)
Returns the X coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.Line2D.Double](#)
Returns the X coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.QuadCurve2D](#)
Returns the x coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.QuadCurve2D.Float](#)
Returns the x coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.QuadCurve2D.Double](#)
Returns the x coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.CubicCurve2D](#)
Returns the X coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.CubicCurve2D.Float](#)
Returns the X coordinate of the end point in double precision.

getX2() - Method in class [java.awt.geom.CubicCurve2D.Double](#)
Returns the X coordinate of the end point in double precision.

getXOrigin() - Method in class [java.awt.image.Kernel](#)
Returns the X origin of this Kernel.

getY() - Method in class [java.awt.Component](#)
Return the current y coordinate of the components origin.

getY() - Method in class [java.awt.Point](#)
Returns the Y coordinate of the point in double precision.

getY() - Method in class [java.awt.Rectangle](#)
Returns the Y coordinate of the bounding Rectangle in double precision.

getY() - Method in class [java.awt.event.MouseEvent](#)
Returns the vertical y position of the event relative to the source component.

getY() - Method in class [java.awt.geom.Point2D](#)
Returns the Y coordinate of this Point2D in double precision.

getY() - Method in class [java.awt.geom.RectangularShape](#)
Returns the Y coordinate of the upper left corner of the framing rectangle in double precision.

getY() - Method in class java.awt.geom.RoundRectangle2D.Float
Returns the Y coordinate of this RoundRectangle2D in double precision.

getY() - Method in class java.awt.geom.RoundRectangle2D.Double
Returns the Y coordinate of this RoundRectangle2D in double precision.

getY() - Method in class java.awt.geom.Rectangle2D.Float
Returns the Y coordinate of this Rectangle2D in double precision.

getY() - Method in class java.awt.geom.Rectangle2D.Double
Returns the Y coordinate of this Rectangle2D in double precision.

getY() - Method in class java.awt.geom.Point2D.Float
Returns the Y coordinate of this Point2D in double precision.

getY() - Method in class java.awt.geom.Point2D.Double
Returns the Y coordinate of this Point2D in double precision.

getY() - Method in class java.awt.geom.Arc2D.Float
Returns the y coordinate of the upper left corner of the arc.

getY() - Method in class java.awt.geom.Arc2D.Double
Returns the y coordinate of the upper left corner of the arc.

getY() - Method in class java.awt.geom.Ellipse2D.Float
Returns the Y coordinate of the upper left corner of this Ellipse2D in double precision.

getY() - Method in class java.awt.geom.Ellipse2D.Double
Returns the Y coordinate of the upper left corner of this Ellipse2D in double precision.

getY() - Method in interface java.security.interfaces.DSAPublicKey
Returns the value of the public key, y.

getY() - Method in class java.security.spec.DSAPublicKeySpec
Returns the public key y.

getY() - Method in class javax.swing.JComponent
Returns the current y coordinate of the component's origin.

getY1() - Method in class java.awt.geom.Line2D
Returns the Y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.Line2D.Float
Returns the Y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.Line2D.Double
Returns the Y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.QuadCurve2D
Returns the y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.CubicCurve2D
Returns the Y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.CubicCurve2D.Float
Returns the Y coordinate of the start point in double precision.

getY1() - Method in class java.awt.geom.CubicCurve2D.Double
Returns the Y coordinate of the start point in double precision.

getY2() - Method in class java.awt.geom.Line2D
Returns the Y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.Line2D.Float
Returns the Y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.Line2D.Double
Returns the Y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.QuadCurve2D
Returns the y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.QuadCurve2D.Float
Returns the y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.QuadCurve2D.Double
Returns the y coordinate of the end point in double precision.

getY2() - Method in class java.awt.geom.CubicCurve2D
Returns the y coordinate of the end point in double precision.

Returns the Y coordinate of the end point in double precision.
getY2() - Method in class java.awt.geom.CubicCurve2D.Float
 Returns the Y coordinate of the end point in double precision.
getY2() - Method in class java.awt.geom.CubicCurve2D.Double
 Returns the Y coordinate of the end point in double precision.
getYear() - Method in class java.sql.Time
 Deprecated.
getYear() - Method in class java.util.Date
 Deprecated. *As of JDK version 1.1, replaced by Calendar.get(Calendar.YEAR) - 1900.*
getYOrigin() - Method in class java.awt.image.Kernel
 Returns the Y origin of this Kernel.
getZeroDigit() - Method in class java.text.DecimalFormatSymbols
 Gets the character used for zero.
getZoneStrings() - Method in class java.text.DateFormatSymbols
 Gets timezone strings.
GLASS_PANE - Static variable in class javax.accessibility.AccessibleRole
 A pane that is guaranteed to be painted on top of all panes beneath it.
GLASS_PANE_PROPERTY - Static variable in class javax.swing.JInternalFrame
 Bound property name.
glassPane - Variable in class javax.swing.JRootPane
 The glass pane that overlays the menu bar and content pane, so it can intercept mouse movements and such.
glassPaneDispatcher - Variable in class javax.swing.plaf.basic.BasicInternalFrameUI

globalHierarchyLock - Static variable in interface java.beans.beancontext.BeanContext
 This global lock is used by both BeanContext and BeanContextServices implementors to serialize changes in a BeanContext hierarchy and any service requests etc.
GlyphJustificationInfo - class java.awt.font.GlyphJustificationInfo.
 The GlyphJustificationInfo class represents information about the justification properties of a glyph.
GlyphJustificationInfo(float, boolean, int, float, float, boolean, int, float, float) - Constructor for class java.awt.font.GlyphJustificationInfo
 Constructs information about the justification properties of a glyph.
GlyphMetrics - class java.awt.font.GlyphMetrics.
 The GlyphMetrics class represents information for a single glyph.
GlyphMetrics(float, Rectangle2D, byte) - Constructor for class java.awt.font.GlyphMetrics
 Constructs a GlyphMetrics object.
GlyphVector - class java.awt.font.GlyphVector.
 A GlyphVector object is a collection of glyphs containing geometric information for the placement of each glyph in a transformed coordinate space which corresponds to the device on which the GlyphVector is ultimately displayed.
GlyphVector() - Constructor for class java.awt.font.GlyphVector

GlyphView - class javax.swing.text.GlyphView.
 A GlyphView is a styled chunk of text that represents a view mapped over an element in the text model.
GlyphView.GlyphPainter - class javax.swing.text.GlyphView.GlyphPainter.
 A class to perform rendering of the glyphs.
GlyphView.GlyphPainter() - Constructor for class javax.swing.text.GlyphView.GlyphPainter

GlyphView(Element) - Constructor for class javax.swing.text.GlyphView
 Constructs a new view wrapped on an element.
GoodBreakWeight - Static variable in class javax.swing.text.View
 The weight to indicate a view supports breaking, but better opportunities probably exist.
GOT_FOCUS - Static variable in class java.awt.Event
 A component gained the focus.
gotDefault - Variable in class javax.naming.InitialContext

Field indicating whether the initial context has been obtained by calling `NamingManager.getInitialContext()`.

gotFocus(Event, Object) - Method in class `java.awt.Component`
 Deprecated. As of JDK version 1.1, replaced by `processFocusEvent(FocusEvent)`.

grabFocus() - Method in class `javax.swing.JComponent`
 Sets the focus on the receiving component if it doesn't already have it.

grabPixels() - Method in class `java.awt.image.PixelGrabber`
 Request the Image or ImageProducer to start delivering pixels and wait for all of the pixels in the rectangle of interest to be delivered.

grabPixels(long) - Method in class `java.awt.image.PixelGrabber`
 Request the Image or ImageProducer to start delivering pixels and wait for all of the pixels in the rectangle of interest to be delivered or until the specified timeout has elapsed.

GradientPaint - class `java.awt.GradientPaint`.
 The GradientPaint class provides a way to fill a Shape with a linear color gradient pattern.

GradientPaint(float, float, Color, float, float, Color) - Constructor for class `java.awt.GradientPaint`
 Constructs a simple acyclic GradientPaint object.

GradientPaint(float, float, Color, float, float, Color, boolean) - Constructor for class `java.awt.GradientPaint`
 Constructs either a cyclic or acyclic GradientPaint object depending on the boolean parameter.

GradientPaint(Point2D, Color, Point2D, Color) - Constructor for class `java.awt.GradientPaint`
 Constructs a simple acyclic GradientPaint object.

GradientPaint(Point2D, Color, Point2D, Color, boolean) - Constructor for class `java.awt.GradientPaint`
 Constructs either a cyclic or acyclic GradientPaint object depending on the boolean parameter.

GraphicAttribute - class `java.awt.font.GraphicAttribute`.
 This class is used with the CHAR_REPLACEMENT attribute.

GraphicAttribute(int) - Constructor for class `java.awt.font.GraphicAttribute`
 Constructs a GraphicAttribute.

Graphics - class `java.awt.Graphics`.
 The Graphics class is the abstract base class for all graphics contexts that allow an application to draw onto components that are realized on various devices, as well as onto off-screen images.

Graphics() - Constructor for class `java.awt.Graphics`
 Constructs a new Graphics object.

Graphics2D - class `java.awt.Graphics2D`.
 This Graphics2D class extends the Graphics class to provide more sophisticated control over geometry, coordinate transformations, color management, and text layout.

Graphics2D() - Constructor for class `java.awt.Graphics2D`
 Constructs a new Graphics2D object.

GraphicsConfigTemplate - class `java.awt.GraphicsConfigTemplate`.
 The GraphicsConfigTemplate class is used to obtain a valid GraphicsConfiguration.

GraphicsConfigTemplate() - Constructor for class `java.awt.GraphicsConfigTemplate`
 This class is an abstract class so only subclasses can be instantiated.

GraphicsConfiguration - class `java.awt.GraphicsConfiguration`.
 The GraphicsConfiguration class describes the characteristics of a graphics destination such as a printer or monitor.

GraphicsConfiguration() - Constructor for class `java.awt.GraphicsConfiguration`
 This is an abstract class that cannot be instantiated directly.

GraphicsDevice - class `java.awt.GraphicsDevice`.
 The GraphicsDevice class describes the graphics devices that might be available in a particular graphics environment.

GraphicsDevice() - Constructor for class `java.awt.GraphicsDevice`
 This is an abstract class that cannot be instantiated directly.

GraphicsEnvironment - class `java.awt.GraphicsEnvironment`.
 The GraphicsEnvironment class describes the collection of GraphicsDevice objects and Font objects available to a Java(tm) application on a particular platform.

GraphicsEnvironment() - Constructor for class java.awt.GraphicsEnvironment

This is an abstract class and cannot be instantiated directly.

gray - Static variable in class java.awt.Color

The color gray.

GrayFilter - class javax.swing.GrayFilter.

An image filter that "disables" an image by turning it into a grayscale image, and brightening the pixels in the image.

GrayFilter(boolean, int) - Constructor for class javax.swing.GrayFilter

Constructs a GrayFilter object that filters a color image to a grayscale image.

GREEK - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

GREEK_EXTENDED - Static variable in class java.lang.Character.UnicodeBlock

Constant for the Unicode character block of the same name.

green - Static variable in class java.awt.Color

The color green.

GREENCOMPONENT - Static variable in class java.awt.color.ICC_ProfileRGB

To request a gamma value or TRC for the green component.

GregorianCalendar - class java.util.GregorianCalendar.

GregorianCalendar is a concrete subclass of Calendar and provides the standard calendar used by most of the world.

GregorianCalendar() - Constructor for class java.util.GregorianCalendar

Constructs a default GregorianCalendar using the current time in the default time zone with the default locale.

GregorianCalendar(int, int, int) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar with the given date set in the default time zone with the default locale.

GregorianCalendar(int, int, int, int, int) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar with the given date and time set for the default time zone with the default locale.

GregorianCalendar(int, int, int, int, int, int) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar with the given date and time set for the default time zone with the default locale.

GregorianCalendar(Locale) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar based on the current time in the default time zone with the given locale.

GregorianCalendar(TimeZone) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar based on the current time in the given time zone with the default locale.

GregorianCalendar(TimeZone, Locale) - Constructor for class java.util.GregorianCalendar

Constructs a GregorianCalendar based on the current time in the given time zone with the given locale.

GridBagConstraints - class java.awt.GridBagConstraints.

The GridBagConstraints class specifies constraints for components that are laid out using the GridBagLayout class.

GridBagConstraints() - Constructor for class java.awt.GridBagConstraints

Creates a GridBagConstraint object with all of its fields set to their default value.

GridBagConstraints(int, int, int, int, double, double, int, int, Insets, int, int) - Constructor for class java.awt.GridBagConstraints

Creates a GridBagConstraints object with all of its fields set to the passed-in arguments.

GridBagLayout - class java.awt.GridBagLayout.

The GridBagLayout class is a flexible layout manager that aligns components vertically and horizontally, without requiring that the components be of the same size.

GridBagLayout() - Constructor for class java.awt.GridBagLayout

Creates a grid bag layout manager.

gridColor - Variable in class javax.swing.JTable

The color of the grid.

gridheight - Variable in class java.awt.GridBagConstraints